



ISO/IEC 29341-8-18

Edition 1.0 2008-11

INTERNATIONAL STANDARD

**Information technology – UPnP Device Architecture –
Part 8-18: Internet Gateway Device Control Protocol – Wide Area Network
Internet Protocol Connection Service**



THIS PUBLICATION IS COPYRIGHT PROTECTED
Copyright © 2008 ISO/IEC, Geneva, Switzerland

All rights reserved. Unless otherwise specified, no part of this publication may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm, without permission in writing from either IEC or IEC's member National Committee in the country of the requester.

If you have any questions about ISO/IEC copyright or have an enquiry about obtaining additional rights to this publication, please contact the address below or your local IEC member National Committee for further information.

IEC Central Office
3, rue de Varembe
CH-1211 Geneva 20
Switzerland
Email: inmail@iec.ch
Web: www.iec.ch

About the IEC

The International Electrotechnical Commission (IEC) is the leading global organization that prepares and publishes International Standards for all electrical, electronic and related technologies.

About IEC publications

The technical content of IEC publications is kept under constant review by the IEC. Please make sure that you have the latest edition, a corrigenda or an amendment might have been published.

- Catalogue of IEC publications: www.iec.ch/searchpub

The IEC on-line Catalogue enables you to search by a variety of criteria (reference number, text, technical committee,...). It also gives information on projects, withdrawn and replaced publications.

- IEC Just Published: www.iec.ch/online_news/justpub

Stay up to date on all new IEC publications. Just Published details twice a month all new publications released. Available on-line and also by email.

- Electropedia: www.electropedia.org

The world's leading online dictionary of electronic and electrical terms containing more than 20 000 terms and definitions in English and French, with equivalent terms in additional languages. Also known as the International Electrotechnical Vocabulary online.

- Customer Service Centre: www.iec.ch/webstore/custserv

If you wish to give us your feedback on this publication or need further assistance, please visit the Customer Service Centre FAQ or contact us:

Email: csc@iec.ch
Tel.: +41 22 919 02 11
Fax: +41 22 919 03 00



ISO/IEC 29341-8-18

Edition 1.0 2008-11

INTERNATIONAL STANDARD

**Information technology – UPnP Device Architecture –
Part 8-18: Internet Gateway Device Control Protocol – Wide Area Network
Internet Protocol Connection Service**

INTERNATIONAL
ELECTROTECHNICAL
COMMISSION

PRICE CODE

W

ICS 35.200

ISBN 2-8318-1010-5

CONTENTS

FOREWORD	4
ORIGINAL UPNP DOCUMENTS (informative)	6
1. Overview and Scope	8
2. Service Modeling Definitions	9
2.1. ServiceType	9
2.2. State Variables	9
2.2.1. ConnectionType	12
2.2.2. PossibleConnectionTypes	12
2.2.3. ConnectionStatus	12
2.2.4. Uptime	12
2.2.5. LastConnectionError	12
2.2.6. AutoDisconnectTime	12
2.2.7. IdleDisconnectTime	13
2.2.8. WarnDisconnectDelay	13
2.2.9. RSIPAvailable	13
2.2.10. NATEnabled	13
2.2.11. ExternalIPAddress	13
2.2.12. PortMappingNumberOfEntries	13
2.2.13. PortMappingEnabled	13
2.2.14. PortMappingLeaseDuration	13
2.2.15. RemoteHost	13
2.2.16. ExternalPort	14
2.2.17. InternalPort	14
2.2.18. PortMappingProtocol	14
2.2.19. InternalClient	14
2.2.20. PortMappingDescription	14
2.2.21. Relationships Between State Variables	15
2.3. Eventing and Moderation	16
2.3.1. Event Model	16
2.4. Actions	17
2.4.1. SetConnectionType	17
2.4.2. GetConnectionTypeInfo	18
2.4.3. RequestConnection	18
2.4.4. RequestTermination	19
2.4.5. ForceTermination	20
2.4.6. SetAutoDisconnectTime	20
2.4.7. SetIdleDisconnectTime	21
2.4.8. SetWarnDisconnectDelay	21
2.4.9. GetStatusInfo	22
2.4.10. GetAutoDisconnectTime	22
2.4.11. GetIdleDisconnectTime	23
2.4.12. GetWarnDisconnectDelay	23
2.4.13. GetNATRSIPStatus	24
2.4.14. GetGenericPortMappingEntry	24
2.4.15. GetSpecificPortMappingEntry	25
2.4.16. AddPortMapping	26
2.4.17. DeletePortMapping	27
2.4.18. GetExternalIPAddress	28
2.4.19. Non-Standard Actions Implemented by a UPnP Vendor	28
2.4.20. Relationships Between Actions	28
2.4.21. Common Error Codes	28
2.5. Theory of Operation	29
2.5.1. Connection Initiation	29
2.5.2. Connection Termination	30

2.5.3.	Connection Scenarios	31
2.5.4.	Non-UPnP compliant clients	33
2.5.5.	VPN connections	33
3.	XML Service Description	34
4.	Test	41

LIST OF TABLES

Table 1:	State Variables	9
Table 1.1:	AllowedValueList for PossibleConnectionTypes	10
Table 1.2:	AllowedValueList for ConnectionStatus	11
Table 1.3:	AllowedValueList for LastConnectionError	11
Table 1.4:	AllowedValueList for PortMappingProtocol	11
Table 2:	Event Moderation.....	16
Table 3:	Actions	17
Table 4:	Arguments for SetConnectionType	17
Table 5:	Arguments for GetConnectionTypeInfo	18
Table 6:	Arguments for SetAutoDisconnectTime	20
Table 7:	Arguments for SetIdleDisconnectTime	21
Table 8:	Arguments for SetWarnDisconnectDelay	21
Table 9:	Arguments for GetStatusInfo.....	22
Table 10:	Arguments for GetAutoDisconnectTime	22
Table 11:	Arguments for GetIdleDisconnectTime	23
Table 12:	Arguments for GetWarnDisconnectDelay	23
Table 13:	Arguments for GetNATRSIPStatus	24
Table 14:	Arguments for GetGenericPortMappingEntry	24
Table 15:	Arguments for GetSpecificPortMappingEntry	25
Table 16:	Arguments for AddPortMapping.....	26
Table 17:	Arguments for DeletePortMapping.....	27
Table 18:	Arguments for GetExternalIPAddress.....	28
Table 19:	Common Error Codes.....	28

INFORMATION TECHNOLOGY – UPNP DEVICE ARCHITECTURE –

Part 8-18: Internet Gateway Device Control Protocol – Wide Area Network Internet Protocol Connection Service

FOREWORD

- 1) ISO (International Organization for Standardization) and IEC (International Electrotechnical Commission) form the specialized system for worldwide standardization. National bodies that are members of ISO or IEC participate in the development of International Standards. Their preparation is entrusted to technical committees; any ISO and IEC member body interested in the subject dealt with may participate in this preparatory work. International governmental and non-governmental organizations liaising with ISO and IEC also participate in this preparation.
- 2) In the field of information technology, ISO and IEC have established a joint technical committee, ISO/IEC JTC 1. Draft International Standards adopted by the joint technical committee are circulated to national bodies for voting. Publication as an International Standard requires approval by at least 75 % of the national bodies casting a vote.
- 3) The formal decisions or agreements of IEC and ISO on technical matters express, as nearly as possible, an international consensus of opinion on the relevant subjects since each technical committee has representation from all interested IEC and ISO member bodies.
- 4) IEC, ISO and ISO/IEC publications have the form of recommendations for international use and are accepted by IEC and ISO member bodies in that sense. While all reasonable efforts are made to ensure that the technical content of IEC, ISO and ISO/IEC publications is accurate, IEC or ISO cannot be held responsible for the way in which they are used or for any misinterpretation by any end user.
- 5) In order to promote international uniformity, IEC and ISO member bodies undertake to apply IEC, ISO and ISO/IEC publications transparently to the maximum extent possible in their national and regional publications. Any divergence between any ISO/IEC publication and the corresponding national or regional publication should be clearly indicated in the latter.
- 6) ISO and IEC provide no marking procedure to indicate their approval and cannot be rendered responsible for any equipment declared to be in conformity with an ISO/IEC publication.
- 7) All users should ensure that they have the latest edition of this publication.
- 8) No liability shall attach to IEC or ISO or its directors, employees, servants or agents including individual experts and members of their technical committees and IEC or ISO member bodies for any personal injury, property damage or other damage of any nature whatsoever, whether direct or indirect, or for costs (including legal fees) and expenses arising out of the publication of, use of, or reliance upon, this ISO/IEC publication or any other IEC, ISO or ISO/IEC publications.
- 9) Attention is drawn to the normative references cited in this publication. Use of the referenced publications is indispensable for the correct application of this publication.

IEC and ISO draw attention to the fact that it is claimed that compliance with this document may involve the use of patents as indicated below.

ISO and IEC take no position concerning the evidence, validity and scope of the putative patent rights. The holders of the putative patent rights have assured IEC and ISO that they are willing to negotiate free licences or licences under reasonable and non-discriminatory terms and conditions with applicants throughout the world. In this respect, the statements of the holders of the putative patent rights are registered with IEC and ISO.

Intel Corporation has informed IEC and ISO that it has patent applications or granted patents.

Information may be obtained from:

Intel Corporation
Standards Licensing Department
5200 NE Elam Young Parkway
MS: JFS-98
USA – Hillsboro, Oregon 97124

Microsoft Corporation has informed IEC and ISO that it has patent applications or granted patents as listed below:

6101499 / US; 6687755 / US; 6910068 / US; 7130895 / US; 6725281 / US; 7089307 / US; 7069312 / US;
10/783 524 / US

Information may be obtained from:

Microsoft Corporation
One Microsoft Way
USA – Redmond WA 98052

Philips International B.V. has informed IEC and ISO that it has patent applications or granted patents.

Information may be obtained from:

Philips International B.V. – IP&S
High Tech campus, building 44 3A21
NL – 5656 Eindhoven

NXP B.V. (NL) has informed IEC and ISO that it has patent applications or granted patents.

Information may be obtained from:

NXP B.V. (NL)
High Tech campus 60
NL – 5656 AG Eindhoven

Matsushita Electric Industrial Co. Ltd. has informed IEC and ISO that it has patent applications or granted patents.

Information may be obtained from:

Matsushita Electric Industrial Co. Ltd.
1-3-7 Shiomi, Chuoh-ku
JP – Osaka 540-6139

Hewlett Packard Company has informed IEC and ISO that it has patent applications or granted patents as listed below:

5 956 487 / US; 6 170 007 / US; 6 139 177 / US; 6 529 936 / US; 6 470 339 / US; 6 571 388 / US; 6 205 466 / US

Information may be obtained from:

Hewlett Packard Company
1501 Page Mill Road
USA – Palo Alto, CA 94304

Samsung Electronics Co. Ltd. has informed IEC and ISO that it has patent applications or granted patents.

Information may be obtained from:

Digital Media Business, Samsung Electronics Co. Ltd.
416 Maetan-3 Dong, Yeongtang-Gu,
KR – Suwon City 443-742

Attention is drawn to the possibility that some of the elements of this document may be the subject of patent rights other than those identified above. IEC and ISO shall not be held responsible for identifying any or all such patent rights.

ISO/IEC 29341-8-18 was prepared by UPnP Implementers Corporation and adopted, under the PAS procedure, by joint technical committee ISO/IEC JTC 1, *Information technology*, in parallel with its approval by national bodies of ISO and IEC.

The list of all currently available parts of the ISO/IEC 29341 series, under the general title *Universal plug and play (UPnP) architecture*, can be found on the IEC web site.

This International Standard has been approved by vote of the member bodies, and the voting results may be obtained from the address given on the second title page.

ORIGINAL UPnP DOCUMENTS (informative)

Reference may be made in this document to original UPnP documents. These references are retained in order to maintain consistency between the specifications as published by ISO/IEC and by UPnP Implementers Corporation. The following table indicates the original UPnP document titles and the corresponding part of ISO/IEC 29341:

UPnP Document Title	ISO/IEC 29341 Part
UPnP Device Architecture 1.0	ISO/IEC 29341-1
UPnP Basic:1 Device	ISO/IEC 29341-2
UPnP AV Architecture:1	ISO/IEC 29341-3-1
UPnP MediaRenderer:1 Device	ISO/IEC 29341-3-2
UPnP MediaServer:1 Device	ISO/IEC 29341-3-3
UPnP AVTransport:1 Service	ISO/IEC 29341-3-10
UPnP ConnectionManager:1 Service	ISO/IEC 29341-3-11
UPnP ContentDirectory:1 Service	ISO/IEC 29341-3-12
UPnP RenderingControl:1 Service	ISO/IEC 29341-3-13
UPnP MediaRenderer:2 Device	ISO/IEC 29341-4-2
UPnP MediaServer:2 Device	ISO/IEC 29341-4-3
UPnP AV Datastructure Template:1	ISO/IEC 29341-4-4
UPnP AVTransport:2 Service	ISO/IEC 29341-4-10
UPnP ConnectionManager:2 Service	ISO/IEC 29341-4-11
UPnP ContentDirectory:2 Service	ISO/IEC 29341-4-12
UPnP RenderingControl:2 Service	ISO/IEC 29341-4-13
UPnP ScheduledRecording:1	ISO/IEC 29341-4-14
UPnP DigitalSecurityCamera:1 Device	ISO/IEC 29341-5-1
UPnP DigitalSecurityCameraMotionImage:1 Service	ISO/IEC 29341-5-10
UPnP DigitalSecurityCameraSettings:1 Service	ISO/IEC 29341-5-11
UPnP DigitalSecurityCameraStillImage:1 Service	ISO/IEC 29341-5-12
UPnP HVAC_System:1 Device	ISO/IEC 29341-6-1
UPnP HVAC_ZoneThermostat:1 Device	ISO/IEC 29341-6-2
UPnP ControlValve:1 Service	ISO/IEC 29341-6-10
UPnP HVAC_FanOperatingMode:1 Service	ISO/IEC 29341-6-11
UPnP FanSpeed:1 Service	ISO/IEC 29341-6-12
UPnP HouseStatus:1 Service	ISO/IEC 29341-6-13
UPnP HVAC_SetpointSchedule:1 Service	ISO/IEC 29341-6-14
UPnP TemperatureSensor:1 Service	ISO/IEC 29341-6-15
UPnP TemperatureSetpoint:1 Service	ISO/IEC 29341-6-16
UPnP HVAC_UserOperatingMode:1 Service	ISO/IEC 29341-6-17
UPnP BinaryLight:1 Device	ISO/IEC 29341-7-1
UPnP DimmableLight:1 Device	ISO/IEC 29341-7-2
UPnP Dimming:1 Service	ISO/IEC 29341-7-10
UPnP SwitchPower:1 Service	ISO/IEC 29341-7-11
UPnP InternetGatewayDevice:1 Device	ISO/IEC 29341-8-1
UPnP LANDevice:1 Device	ISO/IEC 29341-8-2
UPnP WANDevice:1 Device	ISO/IEC 29341-8-3
UPnP WANConnectionDevice:1 Device	ISO/IEC 29341-8-4
UPnP WLANAccessPointDevice:1 Device	ISO/IEC 29341-8-5
UPnP LANHostConfigManagement:1 Service	ISO/IEC 29341-8-10
UPnP Layer3Forwarding:1 Service	ISO/IEC 29341-8-11
UPnP LinkAuthentication:1 Service	ISO/IEC 29341-8-12
UPnP RadiusClient:1 Service	ISO/IEC 29341-8-13
UPnP WANCableLinkConfig:1 Service	ISO/IEC 29341-8-14
UPnP WANCommonInterfaceConfig:1 Service	ISO/IEC 29341-8-15
UPnP WANDSLLinkConfig:1 Service	ISO/IEC 29341-8-16
UPnP WANEthernetLinkConfig:1 Service	ISO/IEC 29341-8-17
UPnP WANIPConnection:1 Service	ISO/IEC 29341-8-18
UPnP WANPOTSLinkConfig:1 Service	ISO/IEC 29341-8-19
UPnP WANPPPConnection:1 Service	ISO/IEC 29341-8-20
UPnP WLANConfiguration:1 Service	ISO/IEC 29341-8-21
UPnP Printer:1 Device	ISO/IEC 29341-9-1
UPnP Scanner:1.0 Device	ISO/IEC 29341-9-2
UPnP ExternalActivity:1 Service	ISO/IEC 29341-9-10
UPnP Feeder:1.0 Service	ISO/IEC 29341-9-11
UPnP PrintBasic:1 Service	ISO/IEC 29341-9-12
UPnP Scan:1 Service	ISO/IEC 29341-9-13
UPnP QoS Architecture:1.0	ISO/IEC 29341-10-1
UPnP QoSDevice:1 Service	ISO/IEC 29341-10-10
UPnP QoSManager:1 Service	ISO/IEC 29341-10-11
UPnP QoSPolicyHolder:1 Service	ISO/IEC 29341-10-12
UPnP QoS Architecture:2	ISO/IEC 29341-11-1
UPnP QOS v2 Schema Files	ISO/IEC 29341-11-2

UPnP Document Title	ISO/IEC 29341 Part
UPnP QosDevice:2 Service	ISO/IEC 29341-11-10
UPnP QosManager:2 Service	ISO/IEC 29341-11-11
UPnP QosPolicyHolder:2 Service	ISO/IEC 29341-11-12
UPnP RemoteUIClientDevice:1 Device	ISO/IEC 29341-12-1
UPnP RemoteUIServerDevice:1 Device	ISO/IEC 29341-12-2
UPnP RemoteUIClient:1 Service	ISO/IEC 29341-12-10
UPnP RemoteUIServer:1 Service	ISO/IEC 29341-12-11
UPnP DeviceSecurity:1 Service	ISO/IEC 29341-13-10
UPnP SecurityConsole:1 Service	ISO/IEC 29341-13-11

1. Overview and Scope

This service definition is compliant with the UPnP Device Architecture version 1.0.

This service-type enables a UPnP control point to configure and control IP connections on the WAN interface of a UPnP compliant *InternetGatewayDevice*^{*}. Any type of WAN interface (e.g., DSL or Cable) that can support a IP connection can use this service.

The service is REQUIRED if an IP connection is used for WAN access, and is specified in

urn:schemas-upnp-org:device:WANConnectionDevice

one or more instances of which are specified under the device

urn:schemas-upnp-org:device:WANDevice

An instance of *WANDevice* is specified under the root device

urn:schemas-upnp-org:device:InternetGatewayDevice

All IP Internet connections are set up from a WAN interface of the *InternetGatewayDevice* or bridged through the gateway to Internet Service Providers (ISPs). *WANDevice* is a container for all UPnP services associated with a physical WAN device. It is assumed that clients are connected to *InternetGatewayDevice* via a LAN (IP-based network).

An instance of a *WANIPConnection* service is activated (refer to SST below) for each actual Internet Connection instance on a *WANConnectionDevice*. *WANIPConnection* service provides IP-level connectivity with an ISP for networked clients on the LAN.

In accordance with UPnP Architecture version 1.0, the maximum number of *WANIPConnection* service instances is static and specified in the *InternetGatewayDevice* description document.

A *WANConnectionDevice* MAY include a *WAN{POTS/DSL/Cable/Ethernet}LinkConfig* service that encapsulates Internet access properties pertaining to the physical link of a particular WAN access type. These properties are common to all instances of *WANIPConnection* in a *WANConnectionDevice*.

A *WANDevice* provides a *WANCommonInterfaceConfig* service that encapsulates Internet access properties common across all *WANConnectionDevice* instances.

^{*} Refer to companion documents defined by the UPnP Internet Gateway working committee for more details on specific devices and services referenced in this document.

2. Service Modeling Definitions

2.1. ServiceType

The following service type identifies a service that is compliant with this template:

urn:schemas-upnp-org:service:*WANIPConnection:1*.

2.2. State Variables

Table 1: State Variables

Variable Name	Req. or Opt. ¹	Data Type	Allowed	Default Value ³	Eng. Units
ConnectionType	R	string	Depends on PossibleConnectionTypes	Not specified	N/A
PossibleConnectionTypes	R	string	See Table 1.1	Not specified	N/A
ConnectionStatus	R	string	See Table 1.2	Not specified	N/A
Uptime	R	ui4	Undefined	Not specified	seconds
LastConnectionError	R	string	See Table 1.3	Not specified	N/A
AutoDisconnectTime	O	ui4	>= 0	Not specified	seconds
IdleDisconnectTime	O	ui4	>= 0	Not specified	seconds
WarnDisconnectDelay	O	ui4	>= 0	Not specified	seconds
RSIPAvailable	R	boolean	0, 1	Not specified	N/A
NATEnabled	R	boolean	0,1	Not specified	N/A
ExternalIPAddress	R	string	String of the type "x.x.x.x"	Empty string	N/A
PortMappingNumberOfEntries	R	ui2	>=0	Not specified	N/A
PortMappingEnabled	R	boolean	0,1	Not specified	N/A
PortMappingLeaseDuration	R	ui4	0 to maximum value of ui4	Not specified	seconds
RemoteHost	R	string	String of the type "x.x.x.x" or empty string	Empty string	N/A
ExternalPort	R	ui2	Between 0 and 65535 inclusive	Not specified	N/A
InternalPort	R	ui2	Between 1 and 65535 inclusive	Not specified	N/A
PortMappingProtocol	R	string	See Table 1.4	Empty string	N/A
InternalClient	R	string	String of the type "x.x.x.x"	Empty string	N/A
PortMappingDescription	R	string	Undefined	Empty string	N/A
<i>Non-standard state variables implemented by an UPnP vendor go here.</i>	<i>X</i>	<i>TBD</i>	<i>TBD</i>	<i>TBD</i>	<i>TBD</i>

- ¹ R = Required, O = Optional, X = Non-standard.
- ² Values listed in this column are required. To specify standard optional values or to delegate assignment of values to the vendor, you must reference a specific instance of an appropriate table below.
- ³ Default values are not specified in the DCP. A vendor may however choose to provide default values for SST variables where appropriate.

Table 1.1: AllowedValueList for PossibleConnectionTypes

PLEASE NOTE: PossibleConnectionTypes is defined as a comma-separated string. However, the values within the string are restricted to the list given in the table below. We have used the allowedValueList table format only as a convenience to represent these values.

Value	Req. or Opt. ¹	Description
<i>Unconfigured</i>	<u>R</u>	Valid connection types cannot be identified. This may be due to the fact that the LinkType variable (if specified in the WAN*LinkConfig service) is uninitialized. THIS VALUE IS DEPENDENT ON THE DEPLOYMENT AND TESTING SHOULD BE DEFERED TO THE VENDOR.
<i>IP_Routed</i>	<u>R</u>	The Internet Gateway is an IP router between the LAN and the WAN connection. THIS VALUE IS ONLY APPLICABLE FOR AN IGD DEVICE SUPPORTING NAT. SHOULD NOT BE TESTED IN OTHER DEVICE CONFIGURATIONS.
<i>IP_Bridged</i>	<u>R</u>	The Internet Gateway is an Ethernet bridge between the LAN and the WAN connection. A router at the other end of the WAN connection from the IGD routes IP packets. THIS VALUE IS ONLY APPLICABLE FOR AN IGD DEVICE CONFIGURED AS AN ETHERNET BRIDGE. SHOULD NOT BE TESTED IN OTHER DEVICE CONFIGURATIONS.

- ¹ R = Required, O = Optional, X = Non-standard.

NOTE: Refer to the **WANConnectionDevice** specification for valid combinations of LinkType and PossibleConnectionTypes for different modems that can support IP based connections.

Table 1.2: AllowedValueList for ConnectionStatus

Value	Req. or Opt. ¹	Description
<i>Unconfigured</i>	<u>R</u>	This value indicates that other variables in the service table are uninitialized or in an invalid state. Examples of such variables include <i>PossibleConnectionTypes</i> and <i>ConnectionType</i> .
<i>Connecting</i>	<u>O</u>	The WANConnectionDevice is in the process of initiating a connection for the first time after the connection became disconnected.
<i>Connected</i>	<u>R</u>	At least one client has successfully initiated an Internet connection using this instance.
<i>PendingDisconnect</i>	<u>O</u>	The connection is active (packets are allowed to flow through), but will transition to <i>Disconnecting</i> state after a certain period (indicated by <i>WarnDisconnectDelay</i>).
<i>Disconnecting</i>	<u>O</u>	The WANConnectionDevice is in the process of terminating a connection. On successful termination, <i>ConnectionStatus</i> transitions to <i>Disconnected</i> .
<i>Disconnected</i>	<u>R</u>	No ISP connection is active (or being activated) from this connection instance. No packets are transiting the gateway.

¹ R = Required, O = Optional, X = Non-standard.

NOTE: Whether or not a control point gets notified of the intermediary states of a connection transition may depend on the gateway implementation.

Table 1.3: AllowedValueList for LastConnectionError

Value	Req. or Opt. ¹
<i>ERROR_NONE</i>	<u>R</u>
<i>ERROR_COMMAND_ABORTED</i>	<u>O</u>
<i>ERROR_NOT_ENABLED_FOR_INTERNET</i>	<u>O</u>
<i>ERROR_USER_DISCONNECT</i>	<u>O</u>
<i>ERROR_ISP_DISCONNECT</i>	<u>O</u>
<i>ERROR_IDLE_DISCONNECT</i>	<u>O</u>
<i>ERROR_FORCED_DISCONNECT</i>	<u>O</u>
<i>ERROR_NO_CARRIER</i>	<u>O</u>
<i>ERROR_IP_CONFIGURATION</i>	<u>O</u>
<i>ERROR_UNKNOWN</i>	<u>O</u>

¹ R = Required, O = Optional, X = Non-standard.

Table 1.4: AllowedValueList for PortMappingProtocol

Value	Req. or Opt. ¹
<i>TCP</i>	<u>R</u>
<i>UDP</i>	<u>R</u>

¹ R = Required, O = Optional, X = Non-standard.

2.2.1. ConnectionType

This variable is set to specify the connection type for a specific active connection. The value selected must be one from the list specified in *PossibleConnectionTypes*.

2.2.2. PossibleConnectionTypes

This variable represents a comma-separated string indicating the types of connections possible in the context of a specific modem and link type. Possible values are a subset or proper subset of values listed in table 1.1.

2.2.3. ConnectionStatus

This variable represents current status of an Internet connection. Possible string values are specified in table 1.2.

2.2.4. Uptime

This variable represents the time in seconds that this connection has stayed up.

2.2.5. LastConnectionError

This variable is a string that provides information about the cause of failure for the last connection setup attempt. The restricted list of enumeration values are listed in table 1.3

2.2.6. AutoDisconnectTime

This variable represents time in seconds (since the establishment of the connection – measured from the time *ConnectionStatus* transitions to *Connected*), after which connection termination is automatically initiated by the gateway. This occurs irrespective of whether the connection is being used or not. A value of *zero* for *AutoDisconnectTime* indicates that the connection is not to be turned off automatically. However, this may be overridden by –

- An implementation specific WAN/Gateway device policy
- *EnabledForInternet* variable (see *WANCommonInterfaceConfig*^{*}) being set to 0 by a user control point
- Connection termination initiated by ISP.

If *WarnDisconnectDelay* is non-zero, the connection state is changed to *PendingDisconnect*. It stays in this state for *WarnDisconnectDelay* seconds (if no connection requests are made) before switching to *Disconnected*.

^{*} Refer to companion document defined by the UPnP Internet Gateway working committee for more details on this variable

2.2.7. IdleDisconnectTime

It represents the idle time of a connection in seconds (since the establishment of the connection), after which connection termination is initiated by the gateway. A value of *zero* for this variable allows infinite idle time – connection will not be terminated due to idle time.

Note: Layer 2 heartbeat packets are included as part of an idle state i.e., they do not reset the idle timer.

If WarnDisconnectDelay is non-zero, the connection state is changed to *PendingDisconnect*. It stays in this state for WarnDisconnectDelay seconds (if no connection requests are made) before switching to *Disconnected*.

2.2.8. WarnDisconnectDelay

This variable represents time in seconds the ConnectionStatus remains in the *PendingDisconnect* state before transitioning to *Disconnecting* state to drop the connection. For example, if this variable was set to 5 seconds, and one of the clients terminates an active connection, the gateway will wait (with ConnectionStatus as *PendingDisconnect*) for 5 seconds before actual termination of the connection.

A value of *zero* for this variable indicates that no warning will be given to clients before terminating the connection.

2.2.9. RSIPAvailable

This variable indicates if Realm-specific IP (RSIP) is available as a feature on the *InternetGatewayDevice*. RSIP is being defined in the NAT working group in the IETF to allow host-NATing using a standard set of message exchanges. It also allows end-to-end applications that otherwise break if NAT is introduced (e.g. IPsec-based VPNs).

A gateway that does not support RSIP should set this variable to 0.

2.2.10. NATEnabled

This variable indicates if Network Address Translation (NAT) is enabled for this connection.

2.2.11. ExternalIPAddress

This is the external IP address used by NAT for the connection.

2.2.12. PortMappingNumberOfEntries

This variable indicates the number of NAT port mapping entries (number of elements in the array) configured on this connection.

2.2.13. PortMappingEnabled

This variable allows security conscious users to disable and enable dynamic and static NAT port mappings on the IGD.

2.2.14. PortMappingLeaseDuration

This variable determines the time to live in seconds of a port-mapping lease. A value of 0 means the port mapping is static. Non-zero values will allow support for dynamic port mappings. Note that static port mappings do not necessarily mean persistence of these mappings across device resets or reboots. It is up to a gateway vendor to implement persistence as appropriate for their IGD device.

2.2.15. RemoteHost

This variable represents the source of inbound IP packets. This will be a wildcard in most cases (i.e. an empty string). NAT vendors are only required to support wildcards. A non-wildcard value will allow for “narrow” port mappings, which may be desirable in some usage scenarios. When RemoteHost is a

wildcard, all traffic sent to the `ExternalPort` on the WAN interface of the gateway is forwarded to the `InternalClient` on the `InternalPort`. When `RemoteHost` is specified as one external IP address as opposed to a wildcard, the NAT will only forward inbound packets from this `RemoteHost` to the `InternalClient`, all other packets will be dropped.

2.2.16.ExternalPort

This variable represents the external port that the NAT gateway would “listen” on for connection requests to a corresponding `InternalPort` on an `InternalClient`. Inbound packets to this external port on the WAN interface of the gateway should be forwarded to `InternalClient` on the `InternalPort` on which the message was received. If this value is specified as a wildcard (i.e. 0), connection request on all external ports (that are not otherwise mapped) will be forwarded to `InternalClient`. In the wildcard case, the value(s) of `InternalPort` on `InternalClient` are ignored by the IGD for those connections that are forwarded to `InternalClient`. Obviously only one such entry can exist in the NAT at any time and conflicts are handled with a “first write wins” behavior.

2.2.17.InternalPort

This variable represents the port on `InternalClient` that the gateway should forward connection requests to. A value of 0 is not allowed. NAT implementations that do not permit different values for `ExternalPort` and `InternalPort` will return an error.

2.2.18.PortMappingProtocol

This variable represents the protocol of the port mapping. Possible values are TCP or UDP.

2.2.19.InternalClient

This variable represents the IP address or DNS host name of an internal client (on the residential LAN). Note that if the gateway does not support DHCP, it does not have to support DNS host names. Consequently, support for an IP address is mandatory and support for DNS host names is recommended. This value cannot be a wildcard (i.e. empty string). It must be possible to set the `InternalClient` to the broadcast IP address 255.255.255.255 for UDP mappings. This is to enable multiple NAT clients to use the same well-known port simultaneously.

2.2.20.PortMappingDescription

This is a string representation of a port mapping and is applicable for static and dynamic port mappings. The format of the description string is not specified and is application dependent. If specified, the description string can be displayed to a user via the UI of a control point, enabling easier management of port mappings. The description string for a port mapping (or a set of related port mappings) may or may not be unique across multiple instantiations of an application on multiple nodes in the residential LAN.

The purpose of NAT port mappings is 2-fold:

- To support the programmatic creation of static port mappings from any control point on the residential network to enable a majority of network services and applications that listen on well known ports.
- To support the programmatic creation of short-lived dynamic port mappings from any control point on the residential network for applications such as multiplayer games, Internet chat and Peer-to-Peer messaging that use external ports for short session-based communication.

A port mapping is essentially an 8-tuple of the type:

```
<PortMappingEnabled, PortMappingLeaseDuration, RemoteHost, ExternalPort,
InternalPort, PortMappingProtocol, InternalClient, PortMappingDescription>
```

The port mapping is used by clients to enable forwarding of inbound service requests, if NAT is used as the address translation mechanism between the residential (private) LAN and the Internet. Each 8-

tuple configures NAT to listen for packets on the external interface of the **WANConnectionDevice** on behalf of a specific client and dynamically forward connection requests to that client.

If a firewall is co-resident on the gateway, it is assumed that the gateway will appropriately configure the firewall for the port mapping.

For example, a client on a residential LAN could run an HTTP server and configure the gateway to forward requests from specific hosts on the Internet (WAN) on specific WAN interfaces.

These mappings are represented as an array of entries.

Following details about NAT port mappings are worth noting:

Adding / Creating a New Port Mapping:

If the mapping contains a unique `ExternalPort` and `PortMappingProtocol` pair the addition will be successful, unless the NAT is out of resources.

Overwriting Previous / Existing Port Mappings:

If the `RemoteHost`, `ExternalPort`, `PortMappingProtocol` and `InternalClient` are exactly the same as an existing mapping, the existing mapping values for `InternalPort`, `PortMappingDescription`, `PortMappingEnabled` and `PortMappingLeaseDuration` are overwritten.

Rejecting a New Port Mapping:

In cases where the `RemoteHost`, `ExternalPort` and `PortMappingProtocol` are the same as an existing mapping, but the `InternalClient` is different, the `AddPortMapping` action is rejected with an appropriate error.

Add or Reject New Port Mapping behavior based on vendor implementation:

In cases where the `ExternalPort`, `PortMappingProtocol` and `InternalClient` are the same, but `RemoteHost` is different, the vendor can choose to support both mappings simultaneously, or reject the second mapping with an appropriate error.

2.2.21. Relationships Between State Variables

If `ConnectionStatus` is set to *Unconfigured*, all other variables are set to their default values.

If `ConnectionStatus` is set to *Disconnected*, `Uptime` is set to its default value.

If `NATEnabled` is set to 0, other port mapping related set actions are essentially disabled. Get actions may still succeed.

For dynamic port mappings (i.e. port mappings with a finite lease duration), the `PortMappingLeaseDuration` variable counts down from the value set by the `AddPortMapping` action. The value counts down **independent** of the state of `PortMappingEnabled` for that specific port mapping. If a `GetGenericPortMappingEntry` or `GetSpecificPortMappingEntry` action is invoked, the remaining time on a port-mapping lease is returned to the control point. For example if a port mapping is added with a lease duration of 1500 seconds and `GetSpecificPortMappingEntry` is invoked on that port mapping 500 seconds later, `PortMappingLeaseDuration` will return 1000 as its value (+/- a few seconds accounting for clock drift). When `PortMappingLeaseDuration` counts to zero, the entry will be deleted by the IGD, **independent** of the state of `PortMappingEnabled` for that specific port mapping. The IGD will correspondingly modify local NAT (and firewall settings if appropriate) to stop forwarding packets as was specified in the deleted port mapping. This will also cause `PortMappingNumberOfEntries` to decrement by 1, which will be evented. Dynamic port mappings will not be automatically reinitiated by the IGD – it is the responsibility of a control point to reinstall the port mapping a few “threshold” seconds before the port mapping is set to expire (i.e. `PortMappingLeaseDuration` equals zero) to prevent service disruption. The value of “threshold” seconds is implementation dependent.

`PortMappingLeaseDuration` does not change for static port mappings (i.e. mappings with infinite lease duration) **independent** of the state of `PortMappingEnabled` variable.

2.3. Eventing and Moderation

Table 2: Event Moderation

Variable Name	Evented	Moderated Event	Max Event Rate ¹	Logical Combination	Min Delta per Event ²
ConnectionType	No	No	N/A	N/A	N/A
PossibleConnectionTypes	Yes	No	N/A	N/A	N/A
ConnectionStatus	Yes	No	N/A	N/A	N/A
Uptime	No	No	N/A	N/A	N/A
LastConnectionError	No	No	N/A	N/A	N/A
AutoDisconnectTime	No	No	N/A	N/A	N/A
IdleDisconnectTime	No	No	N/A	N/A	N/A
WarnDisconnectDelay	No	No	N/A	N/A	N/A
RSIPAvailable	No	No	N/A	N/A	N/A
NATEnabled	No	No	N/A	N/A	N/A
ExternalIPAddress	Yes	No	N/A	N/A	N/A
PortMappingNumberOfEntries	Yes	No	N/A	N/A	N/A
PortMappingEnabled	No	No	N/A	N/A	N/A
PortMappingLeaseDuration	No	No	N/A	N/A	N/A
RemoteHost	No	No	N/A	N/A	N/A
ExternalPort	No	No	N/A	N/A	N/A
InternalPort	No	No	N/A	N/A	N/A
PortMappingProtocol	No	No	N/A	N/A	N/A
InternalClient	No	No	N/A	N/A	N/A
PortMappingDescription	No	No	N/A	N/A	N/A
<i>Non-standard state variables implemented by an UPnP vendor go here.</i>	<i>TBD</i>	<i>TBD</i>	<i>TBD</i>	<i>TBD</i>	<i>TBD</i>

¹ Determined by N, where Rate = (Event)/(N secs).

² (N) * (allowedValueRange Step).

2.3.1. Event Model

Eventing is self-explanatory. Clients use event updates on `ConnectionStatus` to provide local user feedback and manage connections initiated by local applications. None of the events are moderated.

2.4. Actions

Immediately following this table is detailed information about these actions, including short descriptions of the actions, the effects of the actions on state variables, and error codes defined by the actions.

Table 3: Actions

Name	Req. or Opt. ¹
SetConnectionType	<u>R</u>
GetConnectionTypeInfo	<u>R</u>
RequestConnection	<u>R</u>
RequestTermination	<u>O</u>
ForceTermination	<u>R</u>
SetAutoDisconnectTime	<u>O</u>
SetIdleDisconnectTime	<u>O</u>
SetWarnDisconnectDelay	<u>O</u>
GetStatusInfo	<u>R</u>
GetAutoDisconnectTime	<u>O</u>
GetIdleDisconnectTime	<u>O</u>
GetWarnDisconnectDelay	<u>O</u>
GetNATRSIPStatus	<u>R</u>
GetGenericPortMappingEntry	<u>R</u>
GetSpecificPortMappingEntry	<u>R</u>
AddPortMapping	<u>R</u>
DeletePortMapping	<u>R</u>
GetExternalIPAddress	<u>R</u>
<i>Non-standard actions implemented by an UPnP vendor go here.</i>	X

¹ R = Required, O = Optional, X = Non-standard.

2.4.1. SetConnectionType

This action sets up a specific connection type. Clients on the LAN may initiate or share connection only after this action completes or `ConnectionType` is set to a value other than *Unconfigured*.

`ConnectionType` can be a read-only variable in cases where some form of auto configuration is employed.

2.4.1.1. Arguments

Table 4: Arguments for SetConnectionType

Argument	Direction	relatedStateVariable
NewConnectionType	<u>IN</u>	ConnectionType

2.4.1.2. Dependency on State (if any)

2.4.1.3. Effect on State (if any)

This action sets the connection to a specific type.

2.4.1.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.
703	InactiveConnection StateRequired	Current value of <code>ConnectionStatus</code> should be either <i>Disconnected</i> or <i>Unconfigured</i> to permit this action.

2.4.2. GetConnectionTypeInfo

This action retrieves the values of the current connection type and allowable connection types.

2.4.2.1. Arguments

Table 5: Arguments for GetConnectionTypeInfo

Argument	Direction	relatedStateVariable
NewConnectionType	<i>OUT</i>	ConnectionType
NewPossibleConnectionTypes	<i>OUT</i>	PossibleConnectionTypes

2.4.2.2. Dependency on State (if any)

2.4.2.3. Effect on State (if any)

None.

2.4.2.4. Errors

ErrorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.

2.4.3. RequestConnection

A client sends this action to initiate a connection on an instance of a connection service that has a configuration already defined. `RequestConnection` causes the `ConnectionStatus` to immediately change to `Connecting` (if implemented) unless the action is not permitted in the current state of the IGD or the specific service instance. This change of state will be evented. `RequestConnection` should synchronously return at this time in accordance with UPnP architecture requirements that mandate that an action can take no more than 30 seconds to respond synchronously. However, the actual connection setup may take several seconds more to complete. If the connection setup is successful, `ConnectionStatus` will change to `Connected` and will be evented. If the connection setup is not successful, `ConnectionStatus` will eventually revert back to `Disconnected` and will be evented. `LastConnectionError` will be set appropriately in either case. While this may be obvious, it is worth noting that a control point must not source packets to the Internet until `ConnectionStatus` is updated to `Connected`, or the IGD may drop packets until it transitions to the `Connected` state.

The following implementation guidelines are also worth noting:

- The IGD should implement a timeout mechanism to ensure that it does not remain in the `Connecting` state forever. The timeout values are implementation dependent.
- The IGD may take several seconds (or even a few minutes) to transition from the `Connecting` state to the `Connected` state. Control points should moderate the polling frequency of the `ConnectionStatus` variable on the IGD so as to not create data storms on the network.
- Control points should manage a timeout for initiated connections to recover from catastrophic failures on the IGD. The timeout values are implementation dependent.

See the 'Theory of Operation' section below for more details.

2.4.3.1. Arguments

This action does not have any arguments.

2.4.3.2. Dependency on State (if any)

2.4.3.3. Effect on State (if any)

If successful, `ConnectionStatus` is changed to `Connected`.

2.4.3.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
704	ConnectionSetupFailed	There was a failure in setting up the IP or PPP connection with the service provider.
705	ConnectionSetupInProgress	The connection is already in the process of being setup.
706	ConnectionNotConfigured	Current <code>ConnectionStatus</code> is <i>Unconfigured</i>
707	DisconnectInProgress	The connection is in the process of being torn down.
708	InvalidLayer2Address	Corresponding Link Config service has an invalid VPI/VCI or phone number.
709	InternetAccessDisabled	The <code>EnabledForInternet</code> flag is set to 0.
710	InvalidConnectionType	This action is not permitted for the specified <code>ConnectionType</code> .

2.4.4. RequestTermination

A client may send this command to any connection instance in *Connected* or *Connecting* state to change `ConnectionStatus` to *Disconnected*. Connection state changes to *PendingDisconnect* depending on the value of `WarnDisconnectDelay` variable. Connection termination will depend on whether other clients intend to continue to use the connection. The process of terminating a connection is described in Theory of Operation section.

2.4.4.1. Arguments

This action does not have any arguments.

2.4.4.2. Dependency on State (if any)

2.4.4.3. Effect on State (if any)

If successful, `ConnectionStatus` is changed to `Disconnected`.

2.4.4.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.
707	DisconnectInProgress	The connection is in the process of being torn down.
710	InvalidConnectionType	This command is valid only when <code>ConnectionType</code> is <i>IP-Routed</i>
711	ConnectionAlreadyTerminated	An attempt was made to terminate a connection that is no longer active.

2.4.5. ForceTermination

A client may send this command to any connection instance in *Connected*, *Connecting*, *PendingDisconnect* or *Disconnecting* state to change `ConnectionStatus` to *Disconnected*. Connection state immediately transitions to *Disconnected* irrespective of the setting of `WarnDisconnectDelay` variable. The process of terminating a connection is described in Theory of Operation section.

2.4.5.1. Arguments

This action does not have any arguments.

2.4.5.2. Dependency on State (if any)

2.4.5.3. Effect on State (if any)

If successful, `ConnectionStatus` is changed to *Disconnected*.

2.4.5.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.
707	DisconnectInProgress	The connection is in the process of being torn down.
710	InvalidConnectionType	This command is valid only when <code>ConnectionType</code> is <i>IP-Routed</i>
711	ConnectionAlreadyTerminated	An attempt was made to terminate a connection that is no longer active.

2.4.6. SetAutoDisconnectTime

This action sets the time (in seconds) after which an active connection is automatically disconnected.

2.4.6.1. Arguments

Table 6: Arguments for `SetAutoDisconnectTime`

Argument	Direction	relatedStateVariable
<code>NewAutoDisconnectTime</code>	<i>IN</i>	<code>AutoDisconnectTime</code>

2.4.6.2. *Dependency on State (if any)*

2.4.6.3. *Effect on State (if any)*

After expiration of specified time, `ConnectionStatus` is changed to `Disconnected`.

2.4.6.4. *Errors*

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.

2.4.7. **SetIdleDisconnectTime**

This action specifies the idle time (in seconds) after which a connection may be disconnected. The actual disconnect will occur after `WarnDisconnectDelay` time elapses.

2.4.7.1. *Arguments*

Table 7: Arguments for `SetIdleDisconnectTime`

Argument	Direction	relatedStateVariable
<code>NewIdleDisconnectTime</code>	<i>IN</i>	<code>IdleDisconnectTime</code>

2.4.7.2. *Dependency on State (if any)*

2.4.7.3. *Effect on State (if any)*

After the time specified in seconds expires, connection termination is initiated. The intermediate connection states before the connection is terminated will depend on `WarnDisconnectDelay`.

2.4.7.4. *Errors*

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.

2.4.8. **SetWarnDisconnectDelay**

This action specifies the number of seconds of warning to each (potentially) active user of a connection before a connection is terminated.

2.4.8.1. *Arguments*

Table 8: Arguments for `SetWarnDisconnectDelay`

Argument	Direction	relatedStateVariable
<code>NewWarnDisconnectDelay</code>	<i>IN</i>	<code>WarnDisconnectDelay</code>

2.4.8.2. *Dependency on State (if any)*

2.4.8.3. *Effect on State (if any)*

After the time specified in seconds expires, the connection is terminated.

2.4.8.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.

2.4.9. GetStatusInfo

This action retrieves the values of state variables pertaining to connection status.

2.4.9.1. Arguments

Table 9: Arguments for GetStatusInfo

Argument	Direction	relatedStateVariable
NewConnectionStatus	<u>OUT</u>	ConnectionStatus
NewLastConnectionError	<u>OUT</u>	LastConnectionError
NewUptime	<u>OUT</u>	Uptime

2.4.9.2. Dependency on State (if any)

2.4.9.3. Effect on State (if any)

None.

2.4.9.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.

2.4.10. GetAutoDisconnectTime

This action retrieves the values of various timeouts related to the termination of a connection.

2.4.10.1. Arguments

Table 10: Arguments for GetAutoDisconnectTime

Argument	Direction	relatedStateVariable
NewAutoDisconnectTime	<u>OUT</u>	AutoDisconnectTime

2.4.10.2. Dependency on State (if any)

2.4.10.3. Effect on State (if any)

None.

2.4.10.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.

2.4.11. GetIdleDisconnectTime

This action retrieves the values of various timeouts related to the termination of a connection.

2.4.11.1. Arguments

Table 11: Arguments for GetIdleDisconnectTime

Argument	Direction	relatedStateVariable
NewIdleDisconnectTime	<i>OUT</i>	IdleDisconnectTime

2.4.11.2. Dependency on State (if any)

2.4.11.3. Effect on State (if any)

None.

2.4.11.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.

2.4.12. GetWarnDisconnectDelay

This action retrieves the values of various timeouts related to the termination of a connection.

2.4.12.1. Arguments

Table 12: Arguments for GetWarnDisconnectDelay

Argument	Direction	relatedStateVariable
NewWarnDisconnectDelay	<i>OUT</i>	WarnDisconnectDelay

2.4.12.2. Dependency on State (if any)

2.4.12.3. Effect on State (if any)

None.

2.4.12.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.

2.4.13. GetNATRSIPStatus

This action retrieves the current state of NAT and RSIP on the gateway for this connection.

2.4.13.1. Arguments

Table 13: Arguments for GetNATRSIPStatus

Argument	Direction	relatedStateVariable
NewRSIPAvailable	<u>OUT</u>	RSIPAvailable
NewNATEnabled	<u>OUT</u>	NATEnabled

2.4.13.2. Dependency on State (if any)

2.4.13.3. Effect on State (if any)

None.

2.4.13.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.

2.4.14. GetGenericPortMappingEntry

This action retrieves NAT port mappings one entry at a time. Control points can call this action with an incrementing array index until no more entries are found on the gateway. If

PortMappingNumberOfEntries is updated during a call, the process may have to start over.

Entries in the array are contiguous. As entries are deleted, the array is compacted, and the evented variable PortMappingNumberOfEntries is decremented. Port mappings are logically stored as an array on the IGD and retrieved using an array index ranging from 0 to PortMappingNumberOfEntries-1.

2.4.14.1. Arguments

Table 14: Arguments for GetGenericPortMappingEntry

Argument	Direction	relatedStateVariable
NewPortMappingIndex	<u>IN</u>	PortMappingNumberOfEntries
NewRemoteHost	<u>OUT</u>	RemoteHost
NewExternalPort	<u>OUT</u>	ExternalPort
NewProtocol	<u>OUT</u>	PortMappingProtocol
NewInternalPort	<u>OUT</u>	InternalPort
NewInternalClient	<u>OUT</u>	InternalClient
NewEnabled	<u>OUT</u>	PortMappingEnabled
NewPortMappingDescription	<u>OUT</u>	PortMappingDescription
NewLeaseDuration	<u>OUT</u>	PortMappingLeaseDuration

2.4.14.2. Dependency on State (if any)

2.4.14.3. Effect on State (if any)

None.

2.4.14.4.Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
713	SpecifiedArrayIndexInvalid	The specified array index is out of bounds

2.4.15.GetSpecificPortMappingEntry

This action reports the Static Port Mapping specified by the unique tuple of RemoteHost, ExternalPort and PortMappingProtocol.

2.4.15.1.Arguments**Table 15: Arguments for GetSpecificPortMappingEntry**

Argument	Direction	relatedStateVariable
NewRemoteHost	<u>IN</u>	RemoteHost
NewExternalPort	<u>IN</u>	ExternalPort
NewProtocol	<u>IN</u>	PortMappingProtocol
NewInternalPort	<u>OUT</u>	InternalPort
NewInternalClient	<u>OUT</u>	InternalClient
NewEnabled	<u>OUT</u>	PortMappingEnabled
NewPortMappingDescription	<u>OUT</u>	PortMappingDescription
NewLeaseDuration	<u>OUT</u>	PortMappingLeaseDuration

2.4.15.2.Dependency on State (if any)**2.4.15.3.Effect on State (if any)**

None.

2.4.15.4.Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
714	NoSuchEntryInArray	The specified value does not exist in the array

2.4.16.AddPortMapping

This action creates a new port mapping or overwrites an existing mapping with the same internal client. If the `ExternalPort` and `PortMappingProtocol` pair is already mapped to another internal client, an error is returned.

NOTE: Not all NAT implementations will support:

- Wildcard value (i.e. 0) for `ExternalPort`
- `InternalPort` values that are different from `ExternalPort`
- Dynamic port mappings i.e. with non-Infinite `PortMappingLeaseDuration`

2.4.16.1.Arguments

Table 16: Arguments for AddPortMapping

Argument	Direction	relatedStateVariable
NewRemoteHost	<u>IN</u>	RemoteHost
NewExternalPort	<u>IN</u>	ExternalPort
NewProtocol	<u>IN</u>	PortMappingProtocol
NewInternalPort	<u>IN</u>	InternalPort
NewInternalClient	<u>IN</u>	InternalClient
NewEnabled	<u>IN</u>	PortMappingEnabled
NewPortMappingDescription	<u>IN</u>	PortMappingDescription
NewLeaseDuration	<u>IN</u>	PortMappingLeaseDuration

2.4.16.2.Dependency on State (if any)

2.4.16.3.Effect on State (if any)

None.

2.4.16.4.Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.
715	WildCardNotPermittedInSrcIP	The source IP address cannot be wild-carded
716	WildCardNotPermittedInExtPort	The external port cannot be wild-carded
718	ConflictInMappingEntry	The port mapping entry specified conflicts with a mapping assigned previously to another client
724	SamePortValuesRequired	Internal and External port values must be the same
725	OnlyPermanentLeasesSupported	The NAT implementation only supports permanent lease times on port mappings
726	RemoteHostOnlySupportsWildcard	RemoteHost must be a wildcard and cannot be a specific IP address or DNS name
727	ExternalPortOnlySupportsWildcard	ExternalPort must be a wildcard and cannot be a specific port value

2.4.17.DeletePortMapping

This action deletes a previously instantiated port mapping. As each entry is deleted, the array is compacted, and the evented variable `PortMappingNumberOfEntries` is decremented.

2.4.17.1.Arguments

Table 17: Arguments for DeletePortMapping

Argument	Direction	relatedStateVariable
NewRemoteHost	<u>IN</u>	RemoteHost
NewExternalPort	<u>IN</u>	ExternalPort
NewProtocol	<u>IN</u>	PortMappingProtocol

2.4.17.2.Dependency on State (if any)

2.4.17.3.Effect on State (if any)

Inbound connections are no longer permitted on the port mapping being deleted.

2.4.17.4.Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
714	NoSuchEntryInArray	The specified value does not exist in the array

2.4.18. GetExternalIPAddress

This action retrieves the value of the external IP address on this connection instance.

2.4.18.1. Arguments

Table 18: Arguments for GetExternalIPAddress

Argument	Direction	relatedStateVariable
NewExternalIPAddress	<i>OUT</i>	ExternalIPAddress

2.4.18.2. Dependency on State (if any)

2.4.18.3. Effect on State (if any)

None.

2.4.18.4. Errors

errorCode	errorDescription	Description
402	Invalid Args	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.

2.4.19. Non-Standard Actions Implemented by a UPnP Vendor

To facilitate certification, non-standard actions implemented by UPnP vendors should be included in this service template. The UPnP Device Architecture lists naming requirements for non-standard actions (see the section on Description).

2.4.20. Relationships Between Actions

Actions initiated by a client may have different results depending on whether the state of the gateway was changed as a result of another client's actions. For example, the action `RequestConnection` might not be successful in changing the `ConnectionStatus` to *Connected* if the gateway receives `RequestTermination` on the same connection (while it is in the process of connecting) from another client.

2.4.21. Common Error Codes

The following table lists error codes common to actions for this service type. If an action results in multiple errors, the most specific error should be returned.

Table 19: Common Error Codes

errorCode	errorDescription	Description
401	Invalid Action	See UPnP Device Architecture section on Control.
402	Invalid Args	See UPnP Device Architecture section on Control.
404	Invalid Var	See UPnP Device Architecture section on Control.
501	Action Failed	See UPnP Device Architecture section on Control.
600-699	TBD	Common action errors. Defined by UPnP Forum Technical Committee.
701-799		Common action errors defined by the UPnP Forum working committees.
<i>800-899</i>	<i>TBD</i>	<i>(Specified by UPnP vendor.)</i>

2.5. Theory of Operation

When a **WANDevice** is initialized, it is initialized with one or more instances of **WANConnectionDevice** depending on the number of physical links the gateway is configured to support. For example, Cable modem would typically implement one **WANConnectionDevice** instance, but multiple instances may exist for supporting VCs in the case of DSL.

Refer to the **WANPPPConnection** service definition for more details on connection setup procedures. A table summarizing connection procedures follows.

Connection Procedures

Value of ConnectionType	Control point capabilities	Step N°	Follow-up steps for a control point
<i>IP_Routed</i>	IP Stack	1	Set the default gateway address to the Internet Gateway address
		2	Send IP packets through the gateway
<i>IP_Bridged</i>	IP Stack	1	Get the ISP IP address (through DHCP?) and set it as the default gateway address.
		2	Send IP packets to ISP IP address

2.5.1. Connection Initiation

When a **WANConnectionDevice** is initialized, an instance of **WANIPConnection** service will be initialized. If an IP connection is automatically initiated i.e. ‘always on’ as soon as the underlying link is up, no action is needed from a UPnP control point to initiate the connection. However, the IP connection may become inactive (*Disconnected*) because of network or server issues.

A UPnP client sends the `RequestConnection` action to a specific instance of the **WANIPConnection** service on a particular **WANConnectionDevice** to inform the gateway of its intent to use Internet access.

When a client sends a `RequestConnection` command to a *Disconnected* connection, the **WANConnectionDevice** initiates the connection to ISP and may set `ConnectionStatus` to *Connecting*. Depending on whether the connection is successful, `ConnectionStatus` is changed to *Connected* or *Disconnected*.




Figure 1 State Diagram for IP Connections

Figure 1 – State Diagram for IP Connections

When a connection service gets a RequestConnection command, if the ConnectionStatus is:

- *Connecting* or *Disconnecting*: an error is returned.
- *Disconnected*: a connection is attempted (ConnectionStatus may transition to *Connecting*). If this is successful, ConnectionStatus changes to *Connected*.
- *PendingDisconnect*: it is changed to *Connected*.
- *Connected*: the client is allowed to use the connection if ConnectionType is *IP_routed*, otherwise an error is returned.

Figure 1 illustrates the state transition diagram when all states are implemented by the gateway. Required states are in shaded ovals.

RequestConnection may fail (causing an error code to be returned) under the following conditions:

1. Network failure
2. ConnectionStatus is *Connecting*
3. EnabledForInternet variable in **WANCommonInterfaceConfig** is set to 0 (false)

The connection set up may be aborted by a client (by issuing RequestTermination or ForceTermination)

2.5.2. Connection Termination

Connection Termination can be explicit (by a client sending RequestTermination or ForceTermination action) or implicit (because of AutoDisconnectTime or IdleDisconnectTime coming into effect).

A UPnP client sends RequestTermination or ForceTermination action to a specific instance of the **WANIPConnection** service on a particular **WANConnectionDevice** to inform the gateway that this client no

longer needs IP services. A connection termination command is acted upon only if the `ConnectionType` is *IP_routed* and `ConnectionStatus` is *Connecting* or *Connected*.

A connection termination may be initiated due to:

1. A `RequestTermination` or `ForceTermination` command from a client
2. `AutoDisconnectTime` or `IdleDisconnectTime` coming into effect
3. A deployment specific Gateway policy
4. `EnabledForInternet` variable (in *WANCommonInterfaceConfig* service) being set to 0
5. An ISP initiated connection termination or network failure

At this point `ConnectionStatus` transitions (resulting in notification to clients registered for this event) immediately to one of the following:

- *PendingDisconnect* (if this state is implemented and `RequestTermination` is called): This occurs if `WarnDisconnectDelay` is non-zero and the cause for termination is 1 or 2 (as mentioned above). The IP connection is still active in this state. This is useful for giving clients using a connection a chance to react when a connection termination is in progress. If the termination is due to a Gateway policy (3 above), a specific implementation of the Gateway may choose to warn the clients by transitioning to this state.
 - If clients choose to ignore the notification, the connection will be terminated after the time (in seconds) specified as `WarnDisconnectDelay`. `ConnectionStatus` transitions to *Disconnecting*.
 - If any client sends `RequestConnection` command at this point, the gateway MAY choose to discontinue the termination process by changing `ConnectionStatus` to *Connected*. If connection is not restored, the gateway will return error code indicating that the connection was in the process of being torn down.
- *Disconnecting* –this can happen in the following cases –
 - `ForceTermination` command was called
 - `RequestTermination` called, and if no other clients are using the connection, the gateway may choose to skip *PendingDisconnect* state.
 - `WarnDisconnectDelay` is zero and the cause for termination is `RequestTermination` or 2 (as mentioned above).
 - Termination was triggered by `EnabledForInternet` variable being set to 0
 - Termination was triggered by ISP
 - Termination occurred due to a Gateway policy, and the specific implementation chose not to warn the clients by switching directly to this state – essentially overriding the value of `WarnDisconnectDelay`.
- *Disconnected* – if the above two optional states are not implemented.

When transitioning to this state, the connection is terminated immediately.

If the connection state is *Connecting* when a client issues a `RequestTermination`, the state transitions to *Disconnected* directly – it does not go to *PendingDisconnect* even if `WarnDisconnectDelay` is non-zero.

As mentioned before, in the case of termination because of a Gateway policy the action (whether clients are warned or not) depends upon the gateway implementation.

When a client receives a *PendingDisconnect* notification, it can do one of two things:

- Ignore it and let the disconnect proceed
- Send a `RequestConnection` command – the client can keep the connection from disconnecting – this is implementation dependent as pointed out earlier.

2.5.3. Connection Scenarios

As previously mentioned, the possible connection types for a *WANIPConnection* are *IP_Routed* and *IP_Bridged*. The connection scenarios for these two types of connections and the role of connection related actions are described in more detail below.

2.5.3.1. IP_Routed

Unlike the *WANPPPConnection*, a *WANIPConnection* instance typically does not require a priori configuration. If the IP_Routed connection is the default connection on the IGD a CP on the LAN that desires to use the connection is not required to send the *RequestConnection* action even if the connection is not *active*. If the connection is *inactive*, the IGD will initiate a WAN connection upon receiving any outbound packets from the CP (assuming the ‘dial-on-demand’ option is enabled on the IGD) **or** upon receiving a *RequestConnection* action. This may translate to the IGD obtaining an IP address via DHCP from the ISP. It results in a transition of *ConnectionStatus* to *active*. The IGD shares the routable WAN IP address with CPs on the LAN using Network Address Translation (NAT). The CPs on the LAN are assigned private IP addresses in response to their DHCP requests (CPs may self-assign non-routable IP addresses in certain IGD configurations).

If the IGD supports multiple WAN connection instances, the *RequestConnection* action is intended for a CP to specify a *WANIPConnection* instance (that in all likelihood is different from the default connection). A CP may use *RequestTermination* or *ForceTermination* to disconnect the IGD from the WAN (this involves releasing any previously acquired IP resources from the ISP).

RequestTermination: A CP can invoke this action, if available, to terminate an *active* connection. As an example, if three CPs were sharing a WAN connection instance and if each were to call *RequestTermination*, the IGD may release IP resources acquired from the ISP on the three instances of *RequestTermination* to conserve IP resources. If *WarnDisconnectDelay* is implemented and is non-zero the IGD is required to change the *ConnectionStatus* from *Connected* to *PendingDisconnect* and wait until *WarnDisconnectDelay* seconds elapse before transitioning to the *Disconnected* state.

ForceTermination: The IGD will immediately release all WAN IP resources, disregarding the value of *WarnDisconnectDelay* variable.

An example of an implementation of this connection type is a routing IGD modeling a PC or embedded gateway with a Cable modem as a WAN interface.

2.5.3.2. IP_Bridged

In this scenario, all Ethernet packets from a CP on the LAN are bridged to the WAN by the IGD. If this were the default connection, all Ethernet traffic across all LAN interfaces will be bridged to the WAN side. The actions *RequestConnection*, *RequestTermination* and *ForceTermination* are not relevant in this case since the IGD is not IP addressable by the CP over the LAN.

If this were not the default, a CP may use the *RequestConnection* action to select a specific WAN connection instance, followed typically by a DHCP renewal request. All Ethernet packets (including DHCP requests) from this CP get redirected (bridged) through the default WAN connection. This assumes that the IGD is capable of source (MAC) address based bridging. The CP that is actively using the connection may issue *RequestTermination* or *ForceTermination* actions through a secondary interface (if the CP is multi-homed) to end the use of this connection and change the *ConnectionStatus* to *inactive*.

Alternatively, a CP that is not using the connection may issue *RequestTermination* or *ForceTermination* to disconnect IGD from the WAN.

An example of an implementation of this scenario would be a bridging IGD with an integrated Cable modem on the WAN interface that, in turn, has an Ethernet link to CM Termination System (CMTS).

If an IGD supports multiple WAN connection instances and has one active (IP) bridged connection, it cannot allow other WAN connections to be simultaneously active unless it supports source (MAC) address based bridging on that bridged connection, where the source MAC address identifies a CP. The *RequestConnection* action returns an error if this were the case.

2.5.4. Non-UPnP compliant clients

The gateway SHOULD support non-UPnP compliant devices by making it possible for a client to start accessing the Internet (effectively Dial-on-Demand) without sending `RequestConnection` command. The client in this scenario cannot specify which particular *WANConnectionDevice* or *WANIPConnection* it wants to use. The *WANIPConnection* to be used is identified using the `DefaultConnectionService` identified in *Layer3Forwarding* service. Also, the client will not be able to terminate the connection or use the other features of *WANIPConnection* service (like detecting connection speed or specifying a new port mapping).

2.5.5. VPN connections

VPN sessions may be established on an IP connection initiated at the gateway. There are 2 cases to consider:

- A VPN client is initiated by a client on the residential LAN. In this case, the VPN is transparent to the *WANIPConnection* instance and is not visible in the UPnP context.
- A VPN client is initiated on the gateway. In this case, the VPN session would use an *WANIPConnection* instance. A VPN service to model this scenario is not standardized in this WC – it is possible however, as a vendor extension. One possible way to do this is to provide a VPN service in *InternetGatewayDevice* outside of *WANDevice*. The state table for this service would support configuration attributes that are essential for setting up a VPN connection. These would include parameters such as
 - IP address(es) of VPN Gateway
 - Security Protocols to be used
 - Authentication and Privacy parameters specific to a security protocol
 - Session time-out delay

In addition, it would also contain a `ConnectionService` variable that specifies a *WANIPConnection* service instance in a *WANConnectionDevice*. A comma-separated 2-tuple uniquely identifies the service:

uuid:*device-UUID:WANConnectionDevice:y* , urn:*upnp-org:serviceId:serviceID*.

The VPN service would support a `RequestConnection` action that would in turn invoke the `RequestConnection` of the corresponding *WANIPConnection* service like any other UPnP client.

NOTES:

- For `IP_Bridged` connections, it is assumed that either all LAN ports (*LANDevices*) or none of the LAN ports are bridged to the connection. `RequestConnection()` is a NOP in this case.
- In the case of Always-On IP connections, an implementation may return an appropriate error code if `ForceTermination()` is not supported.

3. XML Service Description

```

<?xml version="1.0"?>
<scpd xmlns="urn:schemas-upnp-org:service-1-0">
  <specVersion>
    <major>1</major>
    <minor>0</minor>
  </specVersion>
  <actionList>
    <action>
      <name>SetConnectionType</name>
      <argumentList>
        <argument>
          <name>NewConnectionType</name>
          <direction>in</direction>
          <relatedStateVariable>ConnectionType</relatedStateVariable>
        </argument>
      </argumentList>
    </action>
    <action>
      <name>GetConnectionTypeInfo</name>
      <argumentList>
        <argument>
          <name>NewConnectionType</name>
          <direction>out</direction>
          <relatedStateVariable>ConnectionType</relatedStateVariable>
        </argument>
        <argument>
          <name>NewPossibleConnectionTypes</name>
          <direction>out</direction>
        </argument>
      </argumentList>
    <relatedStateVariable>PossibleConnectionTypes</relatedStateVariable>
  </action>
  <action>
    <name>RequestConnection</name>
  </action>
  <action>
    <name>RequestTermination</name>
  </action>
  <action>
    <name>ForceTermination</name>
  </action>
  <action>
    <name>SetAutoDisconnectTime</name>
    <argumentList>
      <argument>
        <name>NewAutoDisconnectTime</name>
        <direction>in</direction>
        <relatedStateVariable>AutoDisconnectTime</relatedStateVariable>
      </argument>
    </argumentList>
  </action>
  <action>
    <name>SetIdleDisconnectTime</name>
    <argumentList>
      <argument>
        <name>NewIdleDisconnectTime</name>
        <direction>in</direction>
        <relatedStateVariable>IdleDisconnectTime</relatedStateVariable>
      </argument>
    </argumentList>
  </action>

```

```

<action>
<name>SetWarnDisconnectDelay</name>
  <argumentList>
    <argument>
      <name>NewWarnDisconnectDelay</name>
      <direction>in</direction>
      <relatedStateVariable>WarnDisconnectDelay</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
<name>GetStatusInfo</name>
  <argumentList>
    <argument>
      <name>NewConnectionStatus</name>
      <direction>out</direction>
      <relatedStateVariable>ConnectionStatus</relatedStateVariable>
    </argument>
    <argument>
      <name>NewLastConnectionError</name>
      <direction>out</direction>
      <relatedStateVariable>LastConnectionError</relatedStateVariable>
    </argument>
    <argument>
      <name>NewUptime</name>
      <direction>out</direction>
      <relatedStateVariable>Uptime</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
<name>GetAutoDisconnectTime</name>
  <argumentList>
    <argument>
      <name>NewAutoDisconnectTime</name>
      <direction>out</direction>
      <relatedStateVariable>AutoDisconnectTime</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
<name>GetIdleDisconnectTime</name>
  <argumentList>
    <argument>
      <name>NewIdleDisconnectTime</name>
      <direction>out</direction>
      <relatedStateVariable>IdleDisconnectTime</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
<name>GetWarnDisconnectDelay</name>
  <argumentList>
    <argument>
      <name>NewWarnDisconnectDelay</name>
      <direction>out</direction>
      <relatedStateVariable>WarnDisconnectDelay</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
<name>GetNATRSIPStatus</name>
  <argumentList>
    <argument>

```

```

    <name>NewRSIPAvailable</name>
    <direction>out</direction>
    <relatedStateVariable>RSIPAvailable</relatedStateVariable>
  </argument>
  <argument>
    <name>NewNATEnabled</name>
    <direction>out</direction>
    <relatedStateVariable>NATEnabled</relatedStateVariable>
  </argument>
</argumentList>
</action>
<action>
  <name>GetGenericPortMappingEntry</name>
  <argumentList>
    <argument>
      <name>NewPortMappingIndex</name>
      <direction>in</direction>
    <relatedStateVariable>PortMappingNumberOfEntries</relatedStateVariable>
  </argument>
  <argument>
    <name>NewRemoteHost</name>
    <direction>out</direction>
    <relatedStateVariable>RemoteHost</relatedStateVariable>
  </argument>
  <argument>
    <name>NewExternalPort</name>
    <direction>out</direction>
    <relatedStateVariable>ExternalPort</relatedStateVariable>
  </argument>
  <argument>
    <name>NewProtocol</name>
    <direction>out</direction>
    <relatedStateVariable>PortMappingProtocol</relatedStateVariable>
  </argument>
  <argument>
    <name>NewInternalPort</name>
    <direction>out</direction>
    <relatedStateVariable>InternalPort</relatedStateVariable>
  </argument>
  <argument>
    <name>NewInternalClient</name>
    <direction>out</direction>
    <relatedStateVariable>InternalClient</relatedStateVariable>
  </argument>
  <argument>
    <name>NewEnabled</name>
    <direction>out</direction>
    <relatedStateVariable>PortMappingEnabled</relatedStateVariable>
  </argument>
  <argument>
    <name>NewPortMappingDescription</name>
    <direction>out</direction>
    <relatedStateVariable>PortMappingDescription</relatedStateVariable>
  </argument>
  <argument>
    <name>NewLeaseDuration</name>
    <direction>out</direction>
    <relatedStateVariable>PortMappingLeaseDuration</relatedStateVariable>
  </argument>
</argumentList>
</action>
<action>
  <name>GetSpecificPortMappingEntry</name>
  <argumentList>

```

```

    <argument>
      <name>NewRemoteHost</name>
      <direction>in</direction>
      <relatedStateVariable>RemoteHost</relatedStateVariable>
    </argument>
    <argument>
      <name>NewExternalPort</name>
      <direction>in</direction>
      <relatedStateVariable>ExternalPort</relatedStateVariable>
    </argument>
    <argument>
      <name>NewProtocol</name>
      <direction>in</direction>
      <relatedStateVariable>PortMappingProtocol</relatedStateVariable>
    </argument>
    <argument>
      <name>NewInternalPort</name>
      <direction>out</direction>
      <relatedStateVariable>InternalPort</relatedStateVariable>
    </argument>
    <argument>
      <name>NewInternalClient</name>
      <direction>out</direction>
      <relatedStateVariable>InternalClient</relatedStateVariable>
    </argument>
    <argument>
      <name>NewEnabled</name>
      <direction>out</direction>
      <relatedStateVariable>PortMappingEnabled</relatedStateVariable>
    </argument>
    <argument>
      <name>NewPortMappingDescription</name>
      <direction>out</direction>
      <relatedStateVariable>PortMappingDescription</relatedStateVariable>
    </argument>
    <argument>
      <name>NewLeaseDuration</name>
      <direction>out</direction>
      <relatedStateVariable>PortMappingLeaseDuration</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
  <name>AddPortMapping</name>
  <argumentList>
    <argument>
      <name>NewRemoteHost</name>
      <direction>in</direction>
      <relatedStateVariable>RemoteHost</relatedStateVariable>
    </argument>
    <argument>
      <name>NewExternalPort</name>
      <direction>in</direction>
      <relatedStateVariable>ExternalPort</relatedStateVariable>
    </argument>
    <argument>
      <name>NewProtocol</name>
      <direction>in</direction>
      <relatedStateVariable>PortMappingProtocol</relatedStateVariable>
    </argument>
    <argument>
      <name>NewInternalPort</name>
      <direction>in</direction>
      <relatedStateVariable>InternalPort</relatedStateVariable>
    </argument>
  </argumentList>

```

```

    </argument>
    <argument>
      <name>NewInternalClient</name>
      <direction>in</direction>
      <relatedStateVariable>InternalClient</relatedStateVariable>
    </argument>
    <argument>
      <name>NewEnabled</name>
      <direction>in</direction>
      <relatedStateVariable>PortMappingEnabled</relatedStateVariable>
    </argument>
    <argument>
      <name>NewPortMappingDescription</name>
      <direction>in</direction>
    <relatedStateVariable>PortMappingDescription</relatedStateVariable>
    </argument>
    <argument>
      <name>NewLeaseDuration</name>
      <direction>in</direction>
    <relatedStateVariable>PortMappingLeaseDuration</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
  <name>DeletePortMapping</name>
  <argumentList>
    <argument>
      <name>NewRemoteHost</name>
      <direction>in</direction>
      <relatedStateVariable>RemoteHost</relatedStateVariable>
    </argument>
    <argument>
      <name>NewExternalPort</name>
      <direction>in</direction>
      <relatedStateVariable>ExternalPort</relatedStateVariable>
    </argument>
    <argument>
      <name>NewProtocol</name>
      <direction>in</direction>
      <relatedStateVariable>PortMappingProtocol</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<action>
  <name>GetExternalIPAddress</name>
  <argumentList>
    <argument>
      <name>NewExternalIPAddress</name>
      <direction>out</direction>
      <relatedStateVariable>ExternalIPAddress</relatedStateVariable>
    </argument>
  </argumentList>
</action>
<!-- Declarations for other actions added by UPnP vendor (if any) go
here -->
</actionList>
<serviceStateTable>
  <stateVariable sendEvents="no">
    <name>ConnectionType</name>
    <dataType>string</dataType>
  </stateVariable>
  <stateVariable sendEvents="yes">
    <name>PossibleConnectionTypes</name>
    <dataType>string</dataType>
  </stateVariable>

```



```

    <allowedValueList>
      <allowedValue>Unconfigured</allowedValue>
      <allowedValue>IP_Routed</allowedValue>
      <allowedValue>IP_Bridged</allowedValue>
    </allowedValueList>
  </stateVariable>
  <stateVariable sendEvents="yes">
    <name>ConnectionStatus</name>
    <dataType>string</dataType>
    <allowedValueList>
      <allowedValue>Unconfigured</allowedValue>
      <allowedValue>Connecting</allowedValue>
      <allowedValue>Connected</allowedValue>
      <allowedValue>PendingDisconnect</allowedValue>
      <allowedValue>Disconnecting</allowedValue>
      <allowedValue>Disconnected</allowedValue>
    </allowedValueList>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>Uptime</name>
    <dataType>ui4</dataType>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>LastConnectionError</name>
    <dataType>string</dataType>
    <allowedValueList>
      <allowedValue>ERROR_NONE</allowedValue>
      <allowedValue>ERROR_COMMAND_ABORTED</allowedValue>
      <allowedValue>ERROR_NOT_ENABLED_FOR_INTERNET</allowedValue>
      <allowedValue>ERROR_USER_DISCONNECT</allowedValue>
      <allowedValue>ERROR_ISP_DISCONNECT</allowedValue>
      <allowedValue>ERROR_IDLE_DISCONNECT</allowedValue>
      <allowedValue>ERROR_FORCED_DISCONNECT</allowedValue>
      <allowedValue>ERROR_NO_CARRIER</allowedValue>
      <allowedValue>ERROR_IP_CONFIGURATION</allowedValue>
      <allowedValue>ERROR_UNKNOWN</allowedValue>
    </allowedValueList>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>AutoDisconnectTime</name>
    <dataType>ui4</dataType>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>IdleDisconnectTime</name>
    <dataType>ui4</dataType>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>WarnDisconnectDelay</name>
    <dataType>ui4</dataType>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>RSIPAvailable</name>
    <dataType>boolean</dataType>
  </stateVariable>
  <stateVariable sendEvents="no">
    <name>NATEnabled</name>
    <dataType>boolean</dataType>
  </stateVariable>
  <stateVariable sendEvents="yes">
    <name>ExternalIPAddress</name>
    <dataType>string</dataType>
  </stateVariable>
  <stateVariable sendEvents="yes">
    <name>PortMappingNumberOfEntries</name>

```

```

    <dataType>ui2</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>PortMappingEnabled</name>
  <dataType>boolean</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>PortMappingLeaseDuration</name>
  <dataType>ui4</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>RemoteHost</name>
  <dataType>string</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>ExternalPort</name>
  <dataType>ui2</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>InternalPort</name>
  <dataType>ui2</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>PortMappingProtocol</name>
  <dataType>string</dataType>
  <allowedValueList>
    <allowedValue>TCP</allowedValue>
    <allowedValue>UDP</allowedValue>
  </allowedValueList>
</stateVariable>
<stateVariable sendEvents="no">
  <name>InternalClient</name>
  <dataType>string</dataType>
</stateVariable>
<stateVariable sendEvents="no">
  <name>PortMappingDescription</name>
  <dataType>string</dataType>
</stateVariable>
<!-- Declarations for other state variables added by UPnP vendor (if
any) go here -->
</serviceStateTable>
</scpd>

```

4. Test

SetConnectionType / GetConnectionTypeInfo

Test Sequence 1: To test success path

Semantic class: 4

Pre-condition:

- Connection must be inactive. To verify, call `GetStatusInfo` and check OUT argument `ConnectionStatus`. Value should be `Unconfigured` or `Disconnected`.

GetConnectionTypeInfo Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionType	NA			
PossibleConnectionTypes	Initialized to a list of allowable connection types (see Table 1.1)			
		Error Code (if any)	NA	NA

SetConnectionType Success=200

In-Arg	Values	State Variables	Current State	Expected State
ConnectionType	Must be one of the values returned in PossibleConnectionTypes	ConnectionStatus*	Unconfigured	Disconnected
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

* The state change on `ConnectionStatus` will not occur if the current state is already set to `Disconnected`.

Test Sequence 2: To test Set followed by Get

Semantic class: 1

Pre-condition: None

Same as test sequence 1, followed by the following:

GetConnectionTypeInfo **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionType	Set in previous SetConnectionType action			
PossibleConnectionTypes	Initialized to a list of allowable connection types (see Table 1.1)			
		Error Code (if any)	NA	NA

Test Sequence 3: To test error 703

Semantic class: 4

Pre-conditions:

- If `ConnectionStatus` is set to **Unconfigured**, dependent variables such as `ConnectionType` may have to be initialized first
- If `EnabledForInternet` is implemented and set to 0, action `SetEnabledForInternet` in `WANCommonInterfaceConfig` MUST be invoked first to set the value to 1 prior to invoking `RequestConnection`.
- WAN connectivity must be provisioned to allow `RequestConnection` to complete successfully.
- For DSL-integrated IGD Only: If the device does NOT support `AutoConfig`, `LinkType` in `WANDSLLinkConfig` MUST be set to a valid value PRIOR to executing the above sequence of actions

GetStatusInfo **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionStatus	Not Unconfigured			
LastConnectionError	NA			
Uptime	NA			
		Error Code (if any)	NA	NA

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

SetConnectionType **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
ConnectionType	Must be one of the values returned in <code>PossibleConnectionTypes</code>	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	703	NA

RequestConnection

Test Sequence 4: To test success path

Semantic class: 3

Pre-conditions:

- IGD settings (e.g. LinkType) should be pre-configured and WAN connectivity provisioned as described earlier, to enable RequestConnection to succeed.
- If EnabledForInternet is implemented in WANCommonInterfaceConfig, it should be set to 1 prior to executing this sequence of actions.

GetStatusInfo Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionStatus	Disconnected			
LastConnectionError	NA			
Uptime	NA			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

GetStatusInfo Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionStatus	Connected			
LastConnectionError	ERROR_NONE			
Uptime	NA			
		Error Code (if any)	NA	NA

Test Sequence 5: To test error 704

Semantic class: 3

Pre-conditions:

- The IGD must be physically disconnected from the ISP/headend or the WAN link must be in use prior to running the following test sequence
- IGD settings (e.g. `LinkType`) should be pre-configured to otherwise enable `RequestConnection` to succeed

RequestConnection

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	No change
Out-Arg	Expected Value			
		Error Code (if any)	704	NA

GetStatusInfo

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
ConnectionStatus	Connected			
LastConnectionError	Valid error code; see below			
Uptime	NA			
		Error Code (if any)	NA	NA

Some examples of possible error values for `LastConnectionError` are `ERROR_NO_DIALTONE` or `ERROR_LINE_BUSY`

Test Sequence 6: To test error 706

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Unconfigured`.

RequestConnection

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	No change
Out-Arg	Expected Value			
		Error Code (if any)	706	NA

Test Sequence 7: To test error 705

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.
- IGD settings (e.g. `LinkType`) should be pre-configured and WAN connectivity provisioned as described earlier, to enable `RequestConnection` to succeed.

RequestConnection

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		<code>ConnectionStatus</code>	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	706	NA

RequestConnection

Success=200

Executed in sequence with no time delay

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	705	NA

NOTE: It may not be possible to reproduce this test in certain deployments where connection setup is almost instantaneous.

Test Sequence 8: To test error 707

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.
- IGD settings (e.g. `LinkType`) should be pre-configured and WAN connectivity provisioned as described earlier, to enable `RequestConnection` to succeed.

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		<code>ConnectionStatus</code>	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		<code>ConnectionStatus</code>	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

`ConnectionStatus` will change to `Disconnecting` and eventually `Disconnected` and will be evented.

RequestConnection **Success=200** Executed in sequence with no time delay

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	707	NA

NOTE: It may not be possible to reproduce this test in certain deployments where connection teardown is almost instantaneous.

Test Sequence 9: To test error 709

Semantic class: 3

Pre-conditions:

- Vendor must implement `SetEnabledForInternet` and related actions in the `WANCommonInterfaceConfig` service.

SetEnabledForInternet Success=200 in WANCommonInterfaceConfig

In-Arg	Values	State Variables	Current State	Expected State
EnabledForInternet	0	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	709	NA

Test Sequence 10: To test error 708

Semantic class: 3

Pre-conditions:

- POTS IGD Only: SetISPInfo in POTSLinkConfig with empty ISPPhoneNumber. The action should succeed.
- DSL-integrated IGD Only: SetDestinationAddress in WANDSLLinkConfig to invalid value.

SetISPInfo **Success=200** POTS IGD Only in WANPOTSLinkConfig

In-Arg	Values	State Variables	Current State	Expected State
ISPPhoneNumber	Empty string	NA	NA	NA
ISPInfo	NA			
LinkType	NA			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

SetDestinationAddress **Success=200** DSL IGD Only in WANDSLLinkConfig

In-Arg	Values	State Variables	Current State	Expected State
DestinationAddress	Empty string	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	708	NA

Test Sequence 11: To test error 710
 Semantic class: 3
 Pre-conditions: None

SetConnectionType **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
ConnectionType	Must be one of the values returned in PossibleConnectionTypes but incompatible with RequestConnection. An example is PPPoE_Bridged	NA	NA	NA
Out-Arg	Expected Value	ConnectionStatus	Disconnected	No change
		Error Code (if any)	NA	NA

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	710	NA

RequestConnection / SetAutoDisconnectTime

Test Sequence 12: To test success path

Semantic class: 3

Pre-conditions:

Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetAutoDisconnectTime Success=200

In-Arg	Values	State Variables	Current State	Expected State
AutoDisconnectTime	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

After 30 seconds, `ConnectionStatus` will change to `Disconnecting` and eventually `Disconnected` and will be evented.

RequestConnection / SetIdleDisconnectTime

Test Sequence 13: To test success path

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetIdleDisconnectTime Success=200

In-Arg	Values	State Variables	Current State	Expected State
IdleDisconnectTime	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

After 30 seconds of no IP traffic on the connection, `ConnectionStatus` will change to `Disconnecting` and eventually `Disconnected` and will be evented.

NOTE: `IdleDisconnectTime` requires no traffic for specified period of time in seconds, which may be difficult to reproduce.

RequestConnection /SetWarnDisconnectDelay

Test Sequence 14: To test success path

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetAutoDisconnectTime Success=200

In-Arg	Values	State Variables	Current State	Expected State
AutoDisconnectTime	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

SetWarnDisconnectDelay Success=200

In-Arg	Values	State Variables	Current State	Expected State
WarnDisconnectDelay	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

After 30 seconds, `ConnectionStatus` will change to `PendingDisconnect` and eventually will be evented.
 After 15 seconds, `ConnectionStatus` will change to `Disconnected` and will be evented.

RequestTermination

Test Sequence 15: To test success path

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (event)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestTermination

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (event)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

NOTE: This test sequence presumes that the connection is configured a priori. If not, follow steps to configure the connection.

Test Sequence 16: To test error 711

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestTermination Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		ERROR CODE (IF ANY)	NA	NA

RequestTermination Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	711	NA

Test Sequence 17: To test error 707

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestTermination **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestTermination **Success=200** Executed in sequence with no time delay

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	707	NA

NOTE: This test may not be possible in certain deployments where connection teardown is almost instantaneous.

Test Sequence 18: To test error 710

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetConnectionType

Success=200

In-Arg	Values	State Variables	Current State	Expected State
ConnectionType	Must be one of the values returned in <code>PossibleConnectionTypes</code> but incompatible with <code>RequestConnection</code> . An example is <code>PPPoE_Bridged</code>	NA	NA	NA
Out-Arg	Expected Value	ConnectionStatus	Disconnected	No change
		Error Code (if any)	NA	NA

Follow steps to activate the connection (i.e. `ConnectionStatus` is `Connected`).

RequestTermination

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	710	NA

RequestTermination / SetWarnDisconnectDelay

Test Sequence 19: To test success path

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetWarnDisconnectDelay Success=200

In-Arg	Values	State Variables	Current State	Expected State
WarnDisconnectDelay	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestTermination Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Pending Disconnect (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

After 30 seconds, `ConnectionStatus` will change to `Disconnected` and will be evented.

ForceTermination

Test Sequence 20: To test success path

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (event)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (event)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

NOTE: This test sequence presumes that the connection is configured a priori. If not, follow steps to configure the connection.

Test Sequence 21: To test error 711

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	711	NA

Test Sequence 22: To test error 707

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

RequestConnection **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination **Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination **Success=200** Executed in sequence with no time delay

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	707	NA

NOTE: This test may not be possible in certain deployments where connection teardown is almost instantaneous.

Test Sequence 23: To test error 710

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetConnectionType

Success=200

In-Arg	Values	State Variables	Current State	Expected State
ConnectionType	Must be one of the values returned in PossibleConnectionTypes but incompatible with RequestConnection. An example is PPPoE_Bridged	NA	NA	NA
Out-Arg	Expected Value	ConnectionStatus	Disconnected	No change
		Error Code (if any)	NA	NA

Follow steps to activate the connection (i.e. `ConnectionStatus` is `Connected`).

ForceTermination

Success=200

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	710	NA

ForceTermination / SetWarnDisconnectDelay

Test Sequence 24: To test the fact that WarnDisconnectDelay has no effect on ForceTermination

Semantic class: 3

Pre-conditions:

- Follow sequence of actions outlined earlier to ensure that `ConnectionStatus` is `Disconnected`.

SetWarnDisconnectDelay**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
WarnDisconnectDelay	30	NA	NA	NA
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

RequestConnection**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Disconnected	Connected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

ForceTermination**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		ConnectionStatus	Connected	Disconnected (evented)
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping / DeletePortMapping

Test Sequence 25: To test success path

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

GetPortMappingNumberOfEntries**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
PortMappingNumberOfEntries	0 or a positive integer	Error Code (if any)	NA	NA

AddPortMapping**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (event)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

GetPortMappingNumberOfEntries**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
		NA	NA	NA
Out-Arg	Expected Value			
PortMappingNumberOfEntries	1 more than the value retrieved prior to the AddPortMapping action	Error Code (if any)	NA	NA

Test Sequence 26: To test error 718

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (eventuated)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	No change
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	81			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	718	NA

Test Sequence 27: To test success path with DeletePortMapping

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

DeletePortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	A positive integer	Decrement by 1 (evented)
ExternalPort	80			
PortMappingProtocol	TCP			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

Action should cause PortMappingNumberOfEntries to decrement by 1 and will be evented.

Test Sequence 28: To test error 714

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (eventuated)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

DeletePortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	A positive integer	Decrement by 1 (eventuated)
ExternalPort	80			
PortMappingProtocol	TCP			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

DeletePortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	No change
ExternalPort	80			
PortMappingProtocol	TCP			
Out-Arg	Expected Value			
		Error Code (if any)	714	NA

Test Sequence 29: To test error 724

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

NOTE: This test is ONLY for implementations that do not support different values for ExternalPort and InternalPort.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	No change
ExternalPort	85			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	724	NA

Test Sequence 30: To test error 725

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

NOTE: This test is ONLY for implementations that do not support dynamic port mappings (i.e. those with finite lease durations).

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	No change
ExternalPort	85			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	2000			
Out-Arg	Expected Value			
		Error Code (if any)	725	NA

AddPortMapping / GetGenericPortMapping / GetSpecificPortMapping

Test Sequence 31: To test success path

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	81			
PortMappingProtocol	TCP			
InternalPort	81			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	81			
PortMappingProtocol	TCP			
InternalPort	81			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

GetGenericPortMappingEntry

Success = 200

In-Arg	Values	State Variables	Current State	Expected State
A_PortMappingIndex	0 to 2			
Out-Arg	Expected Value			
RemoteHost	Values should correspond to those previously added			
ExternalPort	Values should correspond to those previously added			
PortMappingProtocol	Values should correspond to those previously added			
InternalPort	Values should correspond to those previously added			
InternalClient	Values should correspond to those previously added			
PortMappingEnabled	Values should correspond to those previously added			
PortMappingDescription	Values should correspond to those previously added			
PortMappingLeaseDuration	Values should correspond to those previously added			
		Error Code (if any)	NA	NA

GetSpecificPortMappingEntry

Success = 200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	Values should correspond to those previously added			
ExternalPort	Values should correspond to those previously added			
PortMappingProtocol	Values should correspond to those previously added			
Out-Arg	Expected Value		_____	
InternalPort	Values should correspond to those previously added			
InternalClient	Values should correspond to those previously added			
PortMappingEnabled	Values should correspond to those previously added			
PortMappingDescription	Values should correspond to those previously added			
PortMappingLeaseDuration	Values should correspond to those previously added			
		Error Code (if any)	NA	NA

Test Sequence 32: To test error 713

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (eventuated)
ExternalPort	81			
PortMappingProtocol	TCP			
InternalPort	81			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

GetGenericPortMappingEntry

Success = 200

In-Arg	Values	State Variables	Current State	Expected State
A_PortMappingIndex	2			
Out-Arg	Expected Value			
RemoteHost	NA			
ExternalPort	NA			
PortMappingProtocol	NA			
InternalPort	NA			
InternalClient	NA			
PortMappingEnabled	NA			
PortMappingDescription	NA			
PortMappingLeaseDuration	NA			
		Error Code (if any)	713	NA

Test Sequence 33: To test error 714

Semantic class: 2

Pre-conditions:

- Port mapping entry being added should not already exist in the port mapping table. Values provided below serve only as an example.

AddPortMapping

Success=200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (eventuated)
ExternalPort	80			
PortMappingProtocol	TCP			
InternalPort	80			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

AddPortMapping**Success=200**

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	A valid IP address	PortMappingNumberOfEntries	0 or a positive integer	Increment by 1 (evented)
ExternalPort	81			
PortMappingProtocol	TCP			
InternalPort	81			
InternalClient	A valid IP address			
PortMappingEnabled	1			
PortMappingDescription	Test Description			
PortMappingLeaseDuration	0			
Out-Arg	Expected Value			
		Error Code (if any)	NA	NA

GetSpecificPortMappingEntry

Success = 200

In-Arg	Values	State Variables	Current State	Expected State
RemoteHost	Values should correspond to those previously added			
ExternalPort	Values should correspond to those previously added			
PortMappingProtocol	5000			
Out-Arg	Expected Value			
InternalPort	Values should correspond to those previously added			
InternalClient	Values should correspond to those previously added			
PortMappingEnabled	Values should correspond to those previously added			
PortMappingDescription	Values should correspond to those previously added			
PortMappingLeaseDuration	Values should correspond to those previously added			
		Error Code (if any)	714	NA

INTERNATIONAL
ELECTROTECHNICAL
COMMISSION

3, rue de Varembé
PO Box 131
CH-1211 Geneva 20
Switzerland

Tel: + 41 22 919 02 11
Fax: + 41 22 919 03 00
info@iec.ch
www.iec.ch