

We're integrating Linode and Akamai.



Set Up Automatic Backups to a Lin...



 **Products** 393 ▾

 **Guides** 1638 ▴

Akamai + Linode 1 ▾

Applications 208 ▾

Databases 172 ▾

Development 263 ▾

Email Server Guides 67 ▾

Game Servers 25 ▾

IPs, Networking & Domains 80 ▾

Kubernetes 57 ▾

Linode Platform 29 ▾

Quick Answers 58 ▾

Security, Upgrades & Backups 137 ▴

Authentication 7 ▾

Backups 2 ▴

Backing Up Your Data

Using Rdiff-backup With SSHFS

Data Portability 2 ▾

Encryption 7 ▾

Firewalls 8 ▾

Mitigations 2 ▾

Monitoring 7 ▾

SELinux 2 ▾

SSL Certificates 28 ▾

Secrets Management 1 ▾

Security Basics 32 ▾

Security Patches 5 ▾


System Recovery 1 ▾

Upgrading 17 ▾

Vulnerability Detection 16 ▾

Tools & Reference 112 ▾

Uptime & Analytics 51 ▾

 **Server Guides** 215 ▾

Website Guides 162 ▾

Backing Up Your Data

Updated Thursday, March 9, 2023, by [Linode](#)

[Create a Linode account](#) to try this guide with a \$100 credit.

This credit will be applied to any valid services used during your first 60 days.



If you store any customer or personal data on a Linode, it's important to make regular backups. Backups protect your data from being corrupted or inaccessible for any number of reasons - accidental deletions, misconfigurations, or updates that don't play nicely with the rest of your configuration. Having a recent backup makes it easier to recover from these mishaps.

Assess Your Needs

Backups are not one-size-fits-all. Before you make your first backup (or create a new one), assess what you need to back up and what tool is best for your situation.

What to Back Up

Think about the things on your Linode that would be difficult or impossible to recover. Here are some common examples of data that should be backed up:

CMS websites: Database-driven websites, such as websites made with WordPress, use a database to store content. Make sure you include a database dump in your backup.

HTML websites: If you have standard HTML websites, you can probably just b

Email: If you use your Linode as a mail server, you should back up your raw e

Media: Make sure you back up your images, videos, and audio files.

Customer data: Customer data from sales and financial transactions are ofte
to include a database dump in your backup.

Custom backend: If your Linode is highly customized (or took a long time to s
entire Linode from the root level, or at least your software configuration setti
content.

Once you have a list of items to be backed up, find where those files are on your s
paths and databases for each item.

The type of backup that you make is important, too, because its format affects w
think about the circumstances under which you will be making the restoration, s
backup. There are two basic types of backups:

File-system backup: Copying all or part of your file system, along with its stru
HTML files, software configuration files, email (in most cases), and media. If y
to a Linode, it should work the way it did before. A full-server snapshot backu
that preserves your entire server from a specific point in time. If you back up
permissions, you'll have the content, but it may take a lot longer to get the re

Database dump: File-system backups are not always the best choice for data
will of course also restore your databases, but raw database files are fairly us
Running a SQL dump or something similar is better: you will get a human-rea
can be imported to any other server running the same database type.

Decide whether you need a file-system backup, a database dump, or both. If you
made first, and then the dump file can be saved as part of a file-system backup.

When to Back Up

The next consideration is how often you need to back up your data. This decision
content on your server changes, and how critical it is that you capture those char
intervals:

Online store: At least daily

Blog or news site: As often as you update it

Development server: As often as you make changes

Game server: At least daily

Static site: Every six months, or before and after making significant changes

Email server: At least daily

Your requirements should help you decide whether you can use a manual backu

Where to Store Backups



Where to Store Backups

Next, think about where you want to store your backups. Here are some of the most common options:

Same server: This is the easiest place to store your backups, but if your server is accidentally erased, your backups will disappear too.

Different server: You can store your backups on a different Linode, or a non-Linode cloud storage option.

Personal device: You can back up to your desktop computer or a portable hard drive. This is probably not as secure as a professional data center, and your hardware is prone to failure.

You should also think about how many backups your storage platform can hold. It's a good idea to keep at least two backups (an older, reliable one and a recent one), and possibly every backup on a different platform to avoid running out of disk space.

Backup Rotation

Finally, you should decide how long to keep your old backups and how many to store. There's no better option than none, most people will want *at least two*. For example, if you replace your server and keep any of your old ones, you would be out of luck if you discovered that your old backups were corrupted. The safest option is to store backups as frequently as possible without overwriting old ones. If you run out of space on your backup machine! Backup types that include compression can help you store multiple backups.

Choose the Right Backup Utility

Once you know what your backup needs are, you can choose an appropriate utility. Here are some good ideas of the following:

What files and databases you want to back up

When you need to make new backups

Where you want to store your backups

How many old backups you want to keep on file

This guide will evaluate six different backup utilities to see how they meet these criteria.

Linode's Backup Service

[Linode's Backup Service](#) is a hassle-free backup service for your Linode. You can manage your backups through Linode Manager. This is a safe and easy-to-use option.

What: Full-server file system backup.

When: Snapshots are automatically created daily.

Where: The files are stored in our secure data centers.

Rotation: Backups are rotated automatically so you'll always have a daily, weekly, and monthly backup.



also store one snapshot of your choice indefinitely.

To configure Linode's Backup Service for your Linode, follow [these instructions](#).

Linode's Disks

You can use the Cloud Manager to [duplicate/clone your Linode's disk](#). This is not an easy way to create a full snapshot of your Linode. Once you've duplicated the disk, you can restore it to a different Linode.

What: Full-server file system backup.

When: Duplicate disks are created manually. You have to shut down your server.

Where: The disk is stored on your Linode.

Rotation: Manual. The number of backups you can store at once depends on your plan.

See [Managing Disks and Storage on a Linode](#) to learn more about disks.

Rsync

Rsync is a free file copying utility that we highly recommend. It's a great backup tool for Linux servers.

Simple configuration. Many advanced options are also available.

Easy automation. Rsync commands can be set as cron jobs.

Efficient. Rsync only updates the files that have changed, which saves time and space.

You need a basic level of comfort with the command line to make the initial backup.

What: You set the file path for this file-system backup.

When: The basic command is manual, but you can set it to run automatically. You can also set up automatic daily backups with rsync.

Where: You set the destination. You can back up to a different folder on your server, or to a remote location like a home computer. As long as you can establish an SSH connection between the server and the destination, and the destination is capable of running rsync, you can store your backups anywhere.

Rotation: Basic rotation is manual. However, with the right options, you can set up automatic rotation to a minimal amount of space. This will be covered later.

Rsync will be covered in more detail later in this guide. You can also read our [rsync guide](#).

MySQL Backups

The data stored in your database can change quickly. Running a MySQL dump is a simple way to create a snapshot of your database. You can also create a snapshot of your database using a backup tool like mysqldump. You can also create a snapshot of your database using a backup tool like mysqldump. You can also create a snapshot of your database using a backup tool like mysqldump. You can also create a snapshot of your database using a backup tool like mysqldump.

What: MySQL databases and tables.



When: The basic command is manual, but you can set it to run automatically

Where: The backup file is saved on your server or downloaded to your home the file somewhere else if you want it stored in a different location.

Rotation: Basic rotation is manual.

To make human-readable backups of your databases that can be imported to a n [instructions](#).

Tar

Tar can copy and compress the files on your Linode into a small backup file. This

- Saves space on your backup machine

- Reduces the amount of transfer used if you're saving your backup to a remot

- Makes it easier to manipulate the backup since you're dealing with just one fi

On the other hand, you'll have to uncompress your backup file to make it usable through it looking for one folder.

What: You set the file path for this file-system backup.

When: The basic command is manual, but you can set it to run automatically

Where: By default, the archive file is created on the server itself. If you want t to set that up manually.

Rotation: Basic rotation is manual. The compressed nature of the backup ma

Here is a basic tar command:

```
tar pczvf my_backup_file.tar.gz /path/to/source/content
```

Explanation of flags:

- p or `-preserve-permissions`: Preserves permissions

- c or `-create`: Creates a new archive

- z or `-gzip`: Compresses the archive with gzip

- v or `-verbose`: Shows which files were processed

- f or `-file=ARCHIVE`: Tells us that the next argument is the name for the new ar

For a more detailed discussion of tar and more examples, see [Archiving and Com Zip](#).

Rdiff-backup

Rdiff-backup is a utility designed to make incremental backups. As their [website](#) features of a mirror and an incremental backup "You end up with a replicated ve



features of a mirror and an incremental backup. You end up with a replicated file system and the ability to go back to older files as well.

What: You set the file path for this file-system backup.

When: The basic command is manual, but you can set it up to run automatic.

Where : You set the destination. You can back up to a different folder on your home computer.

Rotation: Both old and new files are kept.

For information, see [Using Rdiff-backup with SSHFS](#).

Manual Backup via Rsync

The remainder of this guide will use rsync as an example; similar steps can be used above. This section explains how to perform a one-time manual backup.

What: You set the file path for this file-system backup.

When: This is a one-time backup.

Where: The files will get stored on the machine from which you are running the command. If you are logged into the server or computer where you want to store your backups.

Rotation: This tutorial does not include any automatic rotation.

Throughout this guide, the Linode you want to back up will be referred to as your *production_server*; the computer where you are storing your backups will be referred to as the *backup_server*. Examples given are for a *production_server* running Ubuntu 12.04 LTS and several *personal_computers*.

Follow these steps to make a manual backup of your Linode:

1. Install rsync on your Linode and *backup_server* by entering the following commands:

```
sudo apt-get install rsync
```

2. Run the rsync command from your *backup_server* or *personal_computer*:

```
rsync -ahvz user@production_server:/path/to/source/content /path/to/destination
```

Note

For a deeper explanation of the rsync command's options and arguments, please see the [Understanding the Rsync Command](#) section of the [Rsync](#) guide.

3. Type your SSH password for the *production_server* when prompted. You will see a confirmation message like this:

```
sent 100 bytes, received 2.75K bytes, 1.00K bytes/sec
```



```
sent 100 bytes  received 2.70K bytes  1.90K bytes/sec
total size is 20.73K  speedup is 7.26
```

That's it! You can double-check the folder you designated as your local storage folder over correctly. The next sections will cover how to automate your backups.

Set Up Automatic Backups to a Linux Server

In this section, you'll use `rsync` to automate daily snapshot-style backups and store them in remote folders. You will need only slightly more disk space for the backups than you use for the original files; you'll be storing identical files as hard links rather than separate files. (If you have a small disk, you will need more space.)

This process is ideal for individuals who want to automatically store backups of their data. This is the easiest and most secure option. It also works for backing up to a Linux computer that is turned on when the backup is initiated.

What: You set the file path for this file-system backup.

When: This is an automatic daily backup.

Where: The files will get stored on the machine from which you are running `tlp`. You can also log into the server or computer where you want to store your backups. The backups are stored on a remote Linux server.

Rotation: All your old backups are saved. Disk space is economized by using `ln`.

Follow these steps to set up automatic backups of your Linode to a Linux server:

1. Install `rsync` on both servers by entering the following command:

```
sudo apt install rsync
```

2. On your *backup_server*, generate a passwordless SSH key by entering the following command. You will be prompted to enter a password - *do not enter a password*.

```
ssh-keygen
```

3. From your *backup_server*, copy the public key to your *production_server* by entering the following command:

```
scp ~/.ssh/id_rsa.pub user@production_server:~/.ssh/uploaded_key
ssh user@production_server 'echo `cat ~/.ssh/uploaded_key` > ~/.ssh/authorized_keys'
```

4. Try connecting to your *production_server* from your *backup_server* by entering the following command:

```
ssh user@production_server 'ls -al'
```

5. Create a directory to store your backups on your *backup_server* by entering the following command:



5. Create a directory to store your backups on your *backup_server* by entering:

```
mkdir ~/backups/
```

6. Try creating a manual backup and storing it in `~/backups/public_orig/`. This future backups will be checked. From your *backup_server*, enter the following:

```
rsync -ahvz user@production_server:~/public ~/backups/pub
```

You should see a bunch of folders whizzing by and a confirmation message si

```
sent 100 bytes  received 2.76K bytes  1.90K bytes/sec
total size is 20.73K  speedup is 7.26
```

7. Now you need to build the command for automatic scheduled backups. We've below, but you can modify it for your needs. Run the following command ma make sure you don't get any errors:

```
rsync -ahvz --delete --link-dest=~/backups/public_orig us
```

Note

For an explanation of the `rsync` command's options and arguments, and to command, please see the [Understanding the Rsync Command](#) section of t

8. The output should be similar to the output that was generated in Step 6. Feel make sure everything was created.
9. Add the command to cron so it gets executed automatically every day. Open editing by entering the following command:

```
crontab -e
```

Note

If this is your first time running the command, select your favorite text edit

10. Copy and paste the following line to the bottom of the file. This is the same li frequency information added at the beginning. Use this and cron will automa server every day at 3 AM.

```
0 3 * * * rsync -ahvz --delete --link-dest=~/ba
```

Note

For more information about cron and to learn how to create a custom sch



For more information about cron, and to learn how to create a custom script, see [Schedule Tasks with Cron](#).

Congratulations! You have now configured daily automatic snapshot-style backup server, you'll be able to restore from a backup at any time.

Set Up Automatic Backups to a Desktop Computer

Now that you've learned how to back up your Linode to another Linux server, it's time to learn how to back up your Linode to a desktop computer. There are several reasons why you may want to do this. It's a bit cheaper than pay for two virtual servers, you can keep everything on your home computer, and you don't need to set up development environments on their desktop computers.

What: You set the file path for this file-system backup.

When: This is an automatic daily backup.

Where: The files are stored on the machine running the command, so make sure you have enough space you want to use to store your backups. This section is designed to make backup to a desktop computer.

Rotation: All of the old backups are saved. Disk space is saved by using hard links.

Verify that rsync is installed on your desktop computer. Linux users can execute `yum install rsync` to install rsync. Mac OS X already has rsync installed by default. See [this article for more details](#).

Linux

Linux users should follow the instructions presented in the previous [Set Up Automatic Backups to a Desktop Computer](#) section of this guide.

Mac OS X

OS X users can also follow the instructions presented in the previous [Set Up Automatic Backups to a Desktop Computer](#) section of this guide. The only difference is that you do not have to install rsync, and you need to change the `date` variable slightly. Your final rsync command in Step 7 should look like this:

```
rsync -ahvz --delete --link-dest=~/.backups/public_orig user@
```

Your final crontab entry in Step 9 should look like this:

```
0 3 * * * rsync -ahvz --delete
```

Note

If you run into a permissions error with cron but not when you run the command manually, you may need to add your password on your SSH key which doesn't normally pop up because you have it in your keychain. You might want to set up a new OS X user with a passwordless key for the purpose of running cron jobs.



Windows

Windows is a bit different. You'll need to install a lot of tools that are available by mind that Windows doesn't have the same type of file ownership and permission extra work to restore permissions and ownership when you restore one of your [backups](#) [walkthrough](#) that shows you how to install cwRsync for Windows, and explains how automatic backups.

Follow these steps to set up automatic backups of your Linode to a Windows desktop.

1. Install cwRsync. You can [get the latest free version here](#) (grab the top one, no
2. It's important that the SSH key runs as the same user as cwRsync, so first navigate to a command prompt, navigate to the folder where you installed cwRsync. For example:

```
cd C:\Program Files (x86)\cwRsync\bin
```

3. Generate an SSH key for your computer.

```
ssh-keygen
```

4. You will have to specify a valid file path to where you want to save the key. The path should be something like this for the path (make sure all of the directories already exist):

```
C:\Users\user\.ssh\id_rsa
```

5. When prompted for a passphrase, just press Return. You should see the private key directory you specified.
6. Now you need to upload your public key to the server. You can use your preferred method. For example, we will use PSCP, which is another program in the PuTTY family that lets you upload files to a remote server.
7. Next you'll add both PSCP and cwRsync to your Path environment variable, so you can run them from any location. These instructions are for Windows 7 and later.

1. From your Start menu, open the **Control Panel**.
2. Choose **System and Security**.
3. Choose **System**.
4. Choose **Advanced system settings** from the left sidebar.
5. Go to the **Advanced** tab.
6. Click the **Environment Variables...** button.
7. Under **System variables**, scroll down until you find the **Path** variable. Highlight it.



8. Do NOT delete what is currently there. You just want to add to it.

9. Add the paths to pscp.exe and cwRsync's bin directory. Separate paths wi

```
C:\Program Files (x86)\PuTTY;C:\Program Files (x86)\cw
```

10. Click **OK** until you're back to the Control Panel.

11. Restart your command prompt if you have it open.

8. Use PSCP to upload the key. In your Windows command prompt, run the foll

```
pscp -scp C:\Users\user\.ssh\id_rsa.pub user@production_s
```

9. On your *production_server*, run this command to append your new key to th

```
echo `cat ~/.ssh/uploaded_key.pub` >> ~/.ssh/authorized_k
```

10. Create a directory on your Windows machine where you will store your backu

```
mkdir %HOMEPATH%\backups
```

11. Create one backup manually, stored in C:\Users\user\backups\public_orig
future backups will be checked. From your Windows machine, run:

```
rsync -hrtvz --chmod u+rw user@production_server:~/publi
```

Note that these commands use Linux-style paths even for Windows: C:\User becomes /cygdrive/c/Users/user/backups/public_orig/.

This time, you will be prompted to enter your *production_server*'s password.
message like this:

```
sent 100 bytes  received 2.76K bytes  1.90K bytes/sec
total size is 20.73K  speedup is 7.26
```

You can `dir` the contents of %HOMEPATH%\backups\public_orig\ to verify tha

12. Add the final version of the command to your `cwrsync.cmd` file and run it on
working before adding the automation.

1. From the Start menu, under All Programs, open the cwRsync folder.

2. Right-click **1.Batch example** and choose **Run as administrator**.

3. This will open up the `cwrsync.cmd` file for editing.

4. Do NOT delete any of the default contents



11. Do not delete any of the default contents.

5. At the bottom, add this line:

```
rsync -hrtvz --chmod u+rwX --delete --link-dest=/cygdr
```

Note

For a deeper explanation of the `rsync` command's options and arguments, please see the [Understand the Rsync Command](#) section of this guide.

6. Save the file.

7. Run the file with the following line for your command prompt:

```
"C:\Program Files (x86)\cwRsync\cwrsync.cmd"
```

This will create today's backup and create the correct environment for a p

You should see output similar to the output from Step 11.

13. Finally, add `cwrsync.cmd` as a daily task in Task Scheduler.

1. From the Start menu, go to > All Programs > Accessories > System Tools >
2. Click **Create Basic Task....** The Task Wizard will pop up.
3. Fill in a name and description; "rsync backups," for example.
4. Choose **Daily** from the radio button list.
5. Set a start date (today) and time (when your server won't be busy, like 3 a.m. or 3 p.m.). It should recur every day.
6. Choose **Start a program.**
7. In the **Program/script** field, enter:

```
"C:\Program Files (x86)\cwRsync\cwrsync.cmd"
```

8. Click **Finish.**

Keep in mind that these backups use your allotted transfer, so running them very often can incur charges.

You have now configured daily automatic snapshot-style backups. If something goes wrong, you'll be able to choose a restoration point from any day from here on forward.



Restore Your Rsync Backup

Restore Your Rsync Backup

If you followed the instructions listed in one of the sections above, your Linode is another server or a desktop computer. But what if something happens to your Linode? You can restore your backup files to another computer? This section will show how to use rsync to restore your backup files to another computer.

1. Navigate to your backups directory on your *backup_server* or desktop.
2. Locate the folder with the right date.
3. Choose whether you want to restore the entire backup (`public/` in our example) or just a subset of files.
4. Upload your chosen files to the *production_server* with `scp`, `SFTP`, `rsync`, etc.
5. *Windows only*: Restore the correct Linux ownership and file permissions.

Maintain Your Backups

Even with automatic backups successfully configured, it is important to monitor your backups and keep the backup process efficient.

Backups to a remote server or desktop (via `rsync` or some other tool) count against your Linode's storage. Keep an eye on your usage to avoid overage charges.

To set a different email notification address for a cron job, add this to your cron job:

```
MAILTO="user@example.com"
```

To disable email notifications for your cron jobs, add this instead:

```
MAILTO=""
```

Make sure your backup server doesn't run out of disk space. You may need to delete old backups. If you're using the `rsync` backup presented in this article, the server will fill up frequently. You can automate backup deletion if desired.

If you're using the automatic `rsync` backup presented here, you may want to update your cron command to a newer backup folder if you've made a lot of changes since the last backup and disk space is low.

Understand the Rsync Command

`Rsync` is a powerful tool, but the half-dozen options in the example commands you saw above are just the beginning. If you need to customize the command, or encounter errors, it helps to have a deeper understanding of the command. This section will walk through the options and arguments used in the basic command.

```
rsync -ahvz user@production_server:/path/to/source/content /path/to/destination
```

rsync



Note

For a basic overview of rsync, [check out the manual page](#).

A basic rsync command takes this form:

```
rsync copyfrom copyto
```

The file or directory you want to back up is `copyfrom`, and `copyto` is the place you want to back it up. `copyfrom` and `copyto` are arguments of the rsync command and are required. A basic rsync command with `copyfrom` and `copyto` arguments would look like this:

```
rsync user@production_server:~/public ~/backups/mybackup
```

```
|---| |-----| |-----|
  ^           ^           ^
  |           |           |
rsync      copyfrom    copyto
```

Rsync can also run with additional options, which are included in the command like this:

```
rsync --options copyfrom copyto
```

-ahvz

Here are some standard options for rsync:

```
-ahvz
```

These are four rsync options that have been combined into a single directive. You can also use them individually like this:

```
-a -h -v -z
```

These options have the following effects:

- a or --archive: Preserves our file permissions and ownership, copies recursively
- h or --human-readable: Number outputs are human readable
- v or --verbose: Displays more output
- z or --compress: Compress file data during transfer

You can add or remove any of the rsync options. For example, if you don't need to preserve permissions, you can run:



```
-ahz
```

When creating backups, the essential option is `-a` or `--archive`.

Source Location

The `copyfrom` location is the path to what you want to back up on your *production* server. You put the file path to your content on the server.

```
user@production_server:~/public
|-----| |-----|
      ^           ^
      |           |
    SSH login   path
```

Since you're trying to copy from a remote server (the *production_server*), you should use `ssh://` first. Then use a colon (`:`), followed by an absolute file path to the folder you want to back up.

In this example, you're backing up the `~/public` directory, which is where your content is stored. You followed the [Hosting a Website](#) guide. `~` is a shortcut for `/home/user/`. The trailing slash is important because you want to include the `public` folder itself in the backup, not just its contents.

If you want to do a full-server backup from root, you should use `/*` as your path. However, `/run` and `/mnt` do not contain permanent data, and `/mnt` is the mount point for other file systems. You can use the `--exclude` option at the very end of the `rsync` command, after everything else.

```
--exclude={"/dev/*,/proc/*,/sys/*,/tmp/*,/run/*,/mnt/*}
```

You will also need to use either `root` or a sudo-capable user for the backup, if you're backing up a high-level directory. If you use a sudo user, you will need to either disable the need for a password, or send the password to the server. The [crashingdaily blog](#) has a good discussion on this.

Target Location

The `copyto` location is the path to where you want to store your backup on your local machine.

```
~/backups/mybackup
```

In the command for automatic backups (see below), a date variable is appended to the target location.

```
~/backups/public_$(date +%Y-%m-%d)
|-----| <- date variable
|-----|
```



This is the local file path on the *backup_server* where you want to store the backup. The `date` built-in function adds the current date to the end of the file path. This makes it easy to find each backup, and also makes individual backups easy to find.

Cron

The following command extends the previous example to enable automatic back

```
0 3 * * * rsync -ahvz --delete --link-dest=~/backu
```

The series of numbers and asterisks specifies when the cron task should be run (to the `crontab` file [earlier in this guide](#)).

0	3	*	*	*	Command
^	^	^	^	^	^
Minute	Hour	Day of Month	Month	Weekday	Shell command

For each of the five time categories you can specify either a specific number or * hour clock for hours. The example above specifies that the command should run every day (3 am). Anything you add after the fifth number or asterisk is considered run just as if you had typed it in your shell. You can [read more about cron here](#).

For testing purposes, you can set the task to run at * * * * *, which will create backups like this may use your allotted transfer, so running a new one every mini

-delete

--delete is another rsync option.

```
--delete
```

With `--delete`, if a file was removed from your `copyfrom` location, it will not be backup, even if it was in earlier backups. It will NOT remove the file from earlier backups. It is easy to navigate.



-link-dest

This is the option that makes our archive of old rsync backups so efficient:

This is the option that makes our archive of old rsync backups so efficient.

```
--link-dest=~/backups/public_orig
```

`--link-dest` is another rsync option and very important to our incremental backups. It lets us store multiple full backups in different folder names for different backups. It also lets us store multiple full backups without using too much disk space.

`--link-dest` has its own required argument, `comparison_backup_folder`. In its simplest form, it looks like this:

```
--link-dest=comparison_backup_folder
```

You can change the `comparison_backup_folder` whenever you want. The more specific the folder name, the more efficient rsync will be.

The trailing `/` is omitted to match the `copyto` path.

Different Server Locations

This guide specifies a remote *production_server* and a local *backup_server*. However, you can also specify a local *production_server* and a remote *backup_server*, with local backups to a different server with two remote servers. Any remote server requires an SSH login before the file transfer.

Running the rsync command from the backup server is a “pulled” backup, while running it from the production server is a “pushed” backup.

Local folders don’t need an SSH login, while remote folders need the SSH login. Here are some more valid rsync command examples:

rsync	copyfrom	copyto
rsync	/local1	/local2/
rsync	/local	user@remote:/remote/
rsync	user@remote:/remote	/local/
rsync	user@remote1:/remote	user@remote2:/remote/

All servers involved must have rsync installed, and any remote server must be reachable via SSH.

More Information

You may wish to consult the following resources for additional information on this topic. In the hope that they will be useful, please note that we cannot vouch for the accuracy, timeliness, or completeness of this information.

[rsync Man Page](#)



WebGnuru's rsync Tutorial

This page was originally published on Thursday, April 4, 2013.

SECURITY

Your Feedback Is Important

Let us know if this guide was helpful to you

[Provide Feedback](#)

Join the conversation.

Read other comments or post your own below. Comments must be respectful, cc the guide. Do not post external links or advertisements. Before posting, consider addressed by contacting our [Support team](#) or asking on our [Community Site](#).



© 2003-2023 Linode LLC.
All rights reserved.



[Site Map](#)

[Press Center](#)

[Support](#)

[Legal Center](#)

[Partners](#)

[System Status](#)



Careers

