

User Platform Client usage

Software Quality Team

ABSTRACT

This usage guide document will briefly introduce the usage of TMP Client for software verification, this document will include following areas:

- a) Client preparations
- b) Client install
- c) Client initial setting
- d) Client run and result check

REVISION HISTORY

REVISION	RELEASE DATE	COMMENTS
V1.0	9/10/2016	Initial draft
V1.1	4/11/2017	Jason Wang

CONTENTS

1	Preparation for TMP Client	5
1.1	What is TMP Client.....	5
1.2	System requirements	5
1.2.1	Operation System requirements.....	5
1.2.2	Hard Ware suggestion	5
1.3	System setting (Linux only).....	5
1.3	Dependence software and version	5
1.3.1	Java.....	5
1.3.2	Python	5
1.3.3	Subversion	6
2	Install TMP Client.....	6
2.1	Export TMP Client build	6
2.2	Install TMP Client build	6
2.2.1	Install with wizard	6
2.2.2	Manually install.....	9
3	Launch TMP Client	9
3.1	TMP Client initial setting (console mode)	9
3.1.1	Software setting section.....	9
3.1.2	Machine setting section	9
3.1.3	Preference setting section.....	9
3.2	launch from Start Menu (Windows)	10
3.3	launch from command line	10
3.4	TMP Client initial setting (GUI mode)	10
3.4.1	Welcome setting	10
3.4.2	Client setting.....	11
3.4.3	Software setting.....	11
3.4.4	Preference setting.....	12
4	TMP Client usage	12
4.1	Main window introduction.....	12
4.1.1	Overview.....	12
4.1.2	Menu bar	13
4.1.3	Rejected queue panel.....	15
4.1.4	Captured queue panel.....	15

4.1.5 Watching task panel.....	16
4.1.6 Status bar.....	16
4.2 Launch a local test suite	17
4.3 Launch remote test suite	17
4.4 Report output	17
5 Appendix	17

1 Preparation for TMP Client

1.1 What is TMP Client

TMP (Test Management Platform) Client is used to receive and run test case from TMP server, on the meanwhile client also support test suite run locally.

1.2 System requirements

1.2.1 Operation System requirements

The following are tested OS and we are not guarantee OS not list here

Window:

Win 7 or later.

Linux:

RedHat 6 or later

CentOS 7 or later

OpenSUSE 42 or later

Unbuntu 16 or later

1.2.2 Hard Ware suggestion

CPU core number: 4

Physical memory: 8G

1.3 System setting (Linux only)

TMP Client will launch many test cases concurrently (Depends on user setting in Menu → Setting → Preference → Max Threads) which will exceed the default user open files limitation (1024).

To avoid this limitation we need to add following two lines into file `/etc/security/limits.conf`.

```
* soft    nofile    32768
```

```
* hard    nofile    65536
```

To verify this modification you can type: `ulimit -a`

1.3 Dependence software and version

1.3.1 Java

TMP Client was built with Java 8 build121 32 bits. Although we have patched the whole JRE in the software build but we still suggest you install the JRE on your operation system (Especially on Linux platform).

Minimum Java version 1.8 is required, you can check Java version by type following command in console:

```
java -version
```

See appendix for java software.

1.3.2 Python

TMP Client will invoke core script to launch every detail test case. Core script was built by Python software, so we need Python ready on your machine.

Python version 2.7.x in 32 bits is required, you can check Python version by type following command in console:

```
Python -version
```

TMP client use a python package “psutil” to run system check, so we also need to install this package.

Python psutil version 5.0.0 in 32 bits is required.

See appendix for Python software.

1.3.3 Subversion

In most case our core script and user case were stored in subversion. So TMP client need subversion ready on your machine.

Subversion version large than 1.6 is required, you can check your version by type following command in console:

```
svn --version
```

See appendix for Subversion software.

2 Install TMP Client

2.1 Export TMP Client build

TMP Client build will follow the name rules as:

Tmp_client_a.bb_installer_ccc_ddd.dd

a: Public release version

b: Internal release version

ccc: bin/src, binary package or source package

ddd.dd: install platform which can be:

- 1) linux.run: package for Linux with install wizard.
- 2) windows.exe: package for windows with install wizard.
- 3) all.tar.gz: package for all platform with manually install.

For example:

- 1) tmp_client_2.06_installer_bin_linux.run:
Build version 2.06 for Linux (RedHat, Ubuntu, SUSE) install with wizard available.
- 2) tmp_client_2.06_installer_bin_windows.exe:
Build version 2.06 for Windows (win7 or later) install with wizard available.
- 3) tmp_client_2.06_installer_src_all.tar.gz:
Build version 2.06 for all platform install without install wizard (manually install).

Please export the build according your requirements:

See appendix for build location

2.2 Install TMP Client build

2.2.1 Install with wizard

TMP Client package offer general GUI setup, so you can simply following with the wizard to install it.

Step 1: Double click install package.

Step 2: Confirm install build and click "Next"




Figure1: Confirm install build

Step 3: Select install type



Figure2: Select install type

Step 4: Select install folder

The default install path will be <User home>/TestRail_Client. You can select another path with “Browse” button.




Figure3: Select install folder

Step 5: Select install components

Please select install components, the core component “TMP core component” is the must item to install.




Figure4: Install components select

Step 6 License agreement

Please accept the license before next step.




Figure5: Accept the license

Step 7 Create Start Menu shortcuts (Windows)

On Windows platform, setup wizard will create shortcuts in "Start Menu" for your future launch.




Figure6: Start Menu shortcut create

Step 8 install

Click "install" button to install software.




Figure7: Install software

2.2.2 Manually install

If you download a source package like: tmp_client_2.05_installer_src_all.tar.gz

You can use 7zip extract the source code on windows or tar command line (tar -xv -f tmp_client_2.05_installer_src_all.tar.gz) on Linux.

Place the source folder as you want.

3 Launch TMP Client

3.1 TMP Client initial setting (console mode)

This section is for TMP Client run in console mode only. For GUI mode initial setting will be launched after GUI start.

We can find the initial setting file from: <client_install_path>/conf/default.ini.

The default.ini file contains two kinds of sections:

- a) Section without "tmp_" : Client software setting section
- b) Section with "tmp_" : Client setting section.

3.1.1 Software setting section

Please use software name as the section name.

max_insts : used to define the maximum instance number this software can be launched.

scan_dir : Client will automatically scan this path to add new software build path.

version and path pair: user specify the software version and the path manually.

You can specify as much version path pair as you like.

3.1.2 Machine setting section

Group: setting the client group name

Private: value can be "0" or "1", the default name is "1" if not present.

"0" : public client will run assign and match task.

"1" : private client will run assign task only.

Terminal: client name setting, client will scan machine name if not present.

Unattended Mode: The value can be "0" or "1". The default value is "0" if option not present.

"0": Attended Mode. SW will do some special work (i.e. SW update) under user's operation.

"1": Unattended Mode. SW will do some special work (i.e. SW update) automatically.

3.1.3 Preference setting section

Link_mode: value can be “both”, “remote” and “local”. Client linked server select.

Max_threads: Maximum threads (test case) can be launched.

Task_mode: auto, serial and parallel.

Auto: client will take top priority level tasks and run it.

Serial: client will run task one by one according the task priority

Parallel: client will run tasks in parallel mode

Work_path: client work space, client will download and run case in this folder.

Save_path: client result save path. If not present client will skip copy case runtime result.

3.2 launch from Start Menu (Windows)

On Windows platform we can launch TMP client from start menu.

Please click “Start Menu” → “All Programs” → “TestRail Client” → “client”




Figure8: Launch from start menu

3.3 launch from command line

Please use following command line to launch client:

- 1) Java -jar <client_install_path>/bin/client.jar -c (console mode)
- 2) Java -jar <client_install_path>/bin/client.jar (GUI mode)

3.4 TMP Client initial setting (GUI mode)

3.4.1 Welcome setting

You will be prompt a welcome setting dialog like following:




Figure9: Welcome setting

You can specify 'work space' and 'save path' and click 'Apply' button to finish the setting. Also you can click the "Don't show welcome setting next time" check box to disable this dialog prompt next time.

3.4.2 Client setting

Click "Setting" → "Client..."

Run client setting in GUI way. Please refer [3.1.2](#) for details



Figure10: Client Setting

3.4.3 Software setting

Click "Setting" → "Software..."

Run software setting in GUI way. Please refer [3.1.1](#) for details




Figure11: Software Setting

3.4.4 Preference setting

Click "Setting" → "Preference..."

Run Preference setting in GUI way. Please refer [3.1.3](#) for details




Figure12: Preference Setting

4 TMP Client usage

4.1 Main window introduction

4.1.1 Overview

Client main view constructed by 5 sections:

- 1) Menu bar
- 2) Rejected queue panel
- 3) Captured queue panel
- 4) Watching task panel
- 5) Status bar

File View Run Tools Setting Help										1									
Rejected Queue2 Reason										4									
ID Suite Design										Status Reason Time									
011@run 1023... Machine,Softwa										m2 1 ... silicon 0... primitive/01 FD1P3XZ SB DFFE Passed NA 14:56:45 05/16									
011@run 1023... Machine,Softwa										m2 2 ... silicon 0... primitive/02 FD1P3XZ SB DFFES Failed NA 14:56:45 05/16									
011@run 1022... Machine,Softwa										m2 3 ... silicon 0... primitive/03 FD1P3XZ SB DFFER Failed NA 14:57:28 05/16									
011@run 960 ... Machine,Softwa										m2 4 ... silicon 0... primitive/04 FD1P3XZ SB DFFESR Passed NA 14:57:28 05/16									
011@run 960 ... Machine,Softwa										m2 5 ... silicon 0... primitive/05 FD1P3XZ SB DFFESS Failed NA 14:58:12 05/16									
011@run 952 ... Machine,Softwa										m2 6 ... silicon 0... primitive/06 FD1P3XZ SB DFF Passed NA 14:58:12 05/16									
011@run 951 ... Machine,Softwa										m2 7 ... silicon 0... primitive/07 FD1P3XZ SB DFFS Failed NA 14:58:55 05/16									
011@run 950 ... Machine,Softwa										m2 8 ... silicon 0... primitive/08 FD1P3XZ SB DFFR Failed NA 14:58:55 05/16									
011@run 950 ... Machine,Softwa										m2 9 ... silicon 0... primitive/09 FD1P3XZ SB DFFSR Passed NA 14:59:39 05/16									
011@run 948 ... Machine,Softwa										m2 10... silicon 0... primitive/10 FD1P3XZ SB DFFSS Failed NA 14:59:39 05/16									
011@run 606 ... Machine,Softwa										m2 11... silicon 0... primitive/11 FD1P3XZ CK INV Passed NA 15:00:23 05/16									
111@run 954 ... Machine,Softwa										m2 12... silicon 0... primitive/21 LUT4 1111 Failed NA 15:00:23 05/16									
111@run 954 ... Machine,Softwa										m2 13... silicon 0... primitive/22 LUT4 3333 Failed NA 15:01:06 05/16									
111@run 954 ... Machine,Softwa										m2 14... silicon 0... primitive/23 LUT4 7777 Failed NA 15:01:06 05/16									
111@run 954 ... Machine,Softwa										m2 15... silicon 0... primitive/24 LUT4 FF00 Failed NA 15:01:50 05/16									
111@run 954 ... Machine,Softwa										m2 16... silicon 0... primitive/25 VHI Failed NA 15:01:50 05/16									
111@run 954 ... Machine,Softwa										m2 17... silicon 0... primitive/26 VLO Failed NA 15:02:04 05/16									
111@run 954 ... Machine,Softwa										m2 18... silicon 0... primitive/27 INV Passed NA 16:42:44 05/16									
111@run 954 ... Machine,Softwa										m2 19... silicon 0... primitive/28 BUF Passed NA 16:42:44 05/16									
111@run 954 ... Machine,Softwa										m2 20... silicon 0... primitive/31 CCU2F 2bit Passed NA 16:43:38 05/16									
111@run 954 ... Machine,Softwa										m2 21... silicon 0... primitive/31 CCU2F 2bit COUT D Passed NA 16:43:38 05/16									
111@run 954 ... Machine,Softwa										m2 22... silicon 0... primitive/31 CCU2F 8bit Passed NA 16:44:35 05/16									
111@run 954 ... Machine,Softwa										m2 23... silicon 0... primitive/32 CCU2E 2bit Passed NA 16:44:22 05/16									
111@run 954 ... Machine,Softwa										m2 24... silicon 0... primitive/32 CCU2E 8bit Passed NA 16:45:17 05/16									
111@run 954 ... Machine,Softwa										m2 25... silicon 0... primitive/33 CCU2F initial 0 Passed NA 16:45:17 05/16									
111@run 954 ... Machine,Softwa										m2 26... silicon 0... primitive/34 CCU2F initial 1 Passed NA 16:46:12 05/16									
111@run 954 ... Machine,Softwa										m2 27... silicon 0... primitive/40 BB 1 Passed NA 16:46:12 05/16									
111@run 954 ... Machine,Softwa										m2 28... silicon 0... primitive/40 BB T 0 Passed NA 16:46:46 05/16									
111@run 954 ... Machine,Softwa										m2 29... silicon 0... primitive/40 BB T 1 Passed NA 16:46:46 05/16									
111@run 954 ... Machine,Softwa										m2 30... silicon 0... primitive/41 NONE REG NO Passed NA 16:47:43 05/16									
111@run 954 ... Machine,Softwa										m2 31... silicon 0... primitive/42 NONE DDR NO Passed NA 16:47:31 05/16									
111@run 954 ... Machine,Softwa										m2 32... silicon 0... primitive/43 LATCH REG NO Failed NA 15:08:02 05/16									
111@run 954 ... Machine,Softwa										m2 33... silicon 0... primitive/44 LATCH BYPASS NO Failed NA 15:08:02 05/16									
111@run 954 ... Machine,Softwa										m2 34... silicon 0... primitive/45 NONE REG DDROUT Failed NA 15:08:55 05/16									
111@run 954 ... Machine,Softwa										m2 35... silicon 0... primitive/46 NONE DDR DDROUT Failed NA 15:08:55 05/16									
111@run 954 ... Machine,Softwa										m2 36... silicon 0... primitive/47 LATCH REG DDRO... Failed NA 15:09:49 05/16									
111@run 954 ... Machine,Softwa										m2 37... silicon 0... primitive/48 LATCH BYASS DD... Failed NA 15:09:49 05/16									
111@run 954 ... Machine,Softwa										m2 38... silicon 0... primitive/60 FILTERA Passed NA 15:10:32 05/16									
111@run 954 ... Machine,Softwa										m2 39... silicon 0... primitive/61 WARMBOOTA Passed NA 15:10:32 05/16									
111@run 954 ... Machine,Softwa										m2 40... silicon 0... RGB/RGBDRVA Failed NA 15:11:16 05/16									
111@run 954 ... Machine,Softwa										m2 41... silicon 0... RGB/01 RGBPWMA FR250Hz Failed NA 15:17:48 05/16									
111@run 954 ... Machine,Softwa										m2 42... silicon 0... RGB/02 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 43... silicon 0... RGB/03 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 44... silicon 0... RGB/04 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 45... silicon 0... RGB/05 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 46... silicon 0... RGB/06 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 47... silicon 0... RGB/07 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 48... silicon 0... RGB/08 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 49... silicon 0... RGB/09 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 50... silicon 0... RGB/10 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 51... silicon 0... RGB/11 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 52... silicon 0... RGB/12 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 53... silicon 0... RGB/13 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 54... silicon 0... RGB/14 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 55... silicon 0... RGB/15 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 56... silicon 0... RGB/16 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 57... silicon 0... RGB/17 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 58... silicon 0... RGB/18 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 59... silicon 0... RGB/19 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 60... silicon 0... RGB/20 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 61... silicon 0... RGB/21 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 62... silicon 0... RGB/22 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 63... silicon 0... RGB/23 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 64... silicon 0... RGB/24 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 65... silicon 0... RGB/25 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 66... silicon 0... RGB/26 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 67... silicon 0... RGB/27 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 68... silicon 0... RGB/28 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 69... silicon 0... RGB/29 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 70... silicon 0... RGB/30 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 71... silicon 0... RGB/31 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 72... silicon 0... RGB/32 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 73... silicon 0... RGB/33 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 74... silicon 0... RGB/34 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 75... silicon 0... RGB/35 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 76... silicon 0... RGB/36 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 77... silicon 0... RGB/37 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 78... silicon 0... RGB/38 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 79... silicon 0... RGB/39 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 80... silicon 0... RGB/40 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 81... silicon 0... RGB/41 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 82... silicon 0... RGB/42 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 83... silicon 0... RGB/43 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 84... silicon 0... RGB/44 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 85... silicon 0... RGB/45 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 86... silicon 0... RGB/46 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 87... silicon 0... RGB/47 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 88... silicon 0... RGB/48 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 89... silicon 0... RGB/49 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 90... silicon 0... RGB/50 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 91... silicon 0... RGB/51 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 92... silicon 0... RGB/52 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 93... silicon 0... RGB/53 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 94... silicon 0... RGB/54 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 95... silicon 0... RGB/55 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 96... silicon 0... RGB/56 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 97... silicon 0... RGB/57 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 98... silicon 0... RGB/58 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 99... silicon 0... RGB/59 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 100... silicon 0... RGB/60 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 101... silicon 0... RGB/61 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 102... silicon 0... RGB/62 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 103... silicon 0... RGB/63 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 104... silicon 0... RGB/64 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 105... silicon 0... RGB/65 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 106... silicon 0... RGB/66 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 107... silicon 0... RGB/67 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 108... silicon 0... RGB/68 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 109... silicon 0... RGB/69 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 110... silicon 0... RGB/70 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 111... silicon 0... RGB/71 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 112... silicon 0... RGB/72 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 113... silicon 0... RGB/73 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 114... silicon 0... RGB/74 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 115... silicon 0... RGB/75 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 116... silicon 0... RGB/76 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 117... silicon 0... RGB/77 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 118... silicon 0... RGB/78 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 119... silicon 0... RGB/79 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 120... silicon 0... RGB/80 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 121... silicon 0... RGB/81 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 122... silicon 0... RGB/82 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 123... silicon 0... RGB/83 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 124... silicon 0... RGB/84 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 125... silicon 0... RGB/85 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 126... silicon 0... RGB/86 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 127... silicon 0... RGB/87 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 128... silicon 0... RGB/88 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 129... silicon 0... RGB/89 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 130... silicon 0... RGB/90 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 131... silicon 0... RGB/91 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 132... silicon 0... RGB/92 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 133... silicon 0... RGB/93 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 134... silicon 0... RGB/94 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 135... silicon 0... RGB/95 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 136... silicon 0... RGB/96 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 137... silicon 0... RGB/97 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 138... silicon 0... RGB/98 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 139... silicon 0... RGB/99 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 140... silicon 0... RGB/100 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 141... silicon 0... RGB/101 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 142... silicon 0... RGB/102 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 143... silicon 0... RGB/103 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 144... silicon 0... RGB/104 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 145... silicon 0... RGB/105 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 146... silicon 0... RGB/106 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 147... silicon 0... RGB/107 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 148... silicon 0... RGB/108 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 149... silicon 0... RGB/109 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 150... silicon 0... RGB/110 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 151... silicon 0... RGB/111 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 152... silicon 0... RGB/112 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 153... silicon 0... RGB/113 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 154... silicon 0... RGB/114 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 155... silicon 0... RGB/115 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 156... silicon 0... RGB/116 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 157... silicon 0... RGB/117 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 158... silicon 0... RGB/118 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 159... silicon 0... RGB/119 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 160... silicon 0... RGB/120 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 161... silicon 0... RGB/121 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 162... silicon 0... RGB/122 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 163... silicon 0... RGB/123 RGBPWMA FR125Hz Failed NA 15:18:20 05/16									
111@run 954 ... Machine,Softwa										m2 164... silicon 0... RGB/124 RGBPWMA FR125Hz Failed NA 15:18									

Figure13: Client main view

4.1.2 Menu bar

4.1.2.1 File menu

"Import...": Allow you import and run a standard test suite(suite Excel file)

"Export...": Export test report, not ready now.

"Exit": Exit/Close software. (If you just click close button on the main view, client will just close the window and hide. You can re-open the client window from system tray.)

4.1.2.2 View menu

Actions for "watching task panel (4)":

"All": Show all task cases in this task.

"Waiting": Show waiting task cases in this task.

"Processing": Show processing task cases in this task.

"Failed": Show failed task cases in this task.

"Passed": Show passed task cases in this task.

"TBD": Show TBD task cases in this task.

"Timeout": Show timeout task cases in this task.

4.1.2.3 Run menu

Actions for “Captured queue panel (3)” and “watching task panel (4)”

“Play”: action for “Captured queue panel (3)”, when there is a captured task selected, “Play” will restart this task.

“Pause”: action for “Captured queue panel (3)”, when there is a captured task selected, “Pause” will pause this task.

“Stop”: action for “Captured queue panel (3)”, when there is a captured task selected, “Stop” will stop this task.

“Retest” action for “watching task panel (4)”. Retest the test case in watching task according with the condition selected.

4.1.2.4 Tools menu

4.1.2.4.1 Upload

Integration tool allow you to update standard test suite to TMP server.




Figure14: Suite upload dialog

Please input your user name and pass word given by TMP admin.

Use “Select” button to select test suite you want to upload to server.

Click “Upload” button to start upload.

All output lines will be shown in “Upload Console Outputs” window.

4.1.2.4.2 Keygen

Integration tool allow you generate encryption code for your account and password which will be show on TMP website (auth_key = xxx)



Figure15: Key generate

4.1.2.5 Setting menu

Client setting, refer to [3.4](#) section

4.1.2.6 Help menu

“Usage”: show this help document.

“Contact”: create email and send to Client developer.

“About”: show client version information

4.1.3 Rejected queue panel

All rejected task will be shown here with queue name and rejected reason.

You can select one queue and make a right click to popup a “popup menu”, click “Details” to show details information:

Detail info for 511@run_961_040717_170101:		
Item	Request Value	Available Value
Software.diamond	3.9	d38_p1,d39_p2,3.9.0.48
Machine.terminal	D50523,D27409	D27639
Machine.group	test_sp1	rna_regression_group

*: Client work in Private Mode: Only 'Assigned' task will be run.

Figure16: Detail rejects view

You will be shown request values and current client value.

4.1.4 Captured queue panel

All captured task will be shown here with queue name and current status.

You can select one queue and make a right click to popup a “popup menu” like following:

Captured Queue	Status
501@run 864...	Finished
501@run 864...	Finished
501@run 864...	Show
501@run 864...	Run... ▶ Play
501@run 864...	Pause
501@run 864...	Stop
501@run 826...	Finished

Figure17: Captured panel popup menu

“Show”: click this button will show detail run case info in “watching task panel (4)”

“Run → Play”: same function as 4.1.2.3 Run menu, make the select captured queue re-start

“Run → Pause”: same function as 4.1.2.3 Run menu, make the select captured queue pause

“Run → Stop”: same function as 4.1.2.3 Run menu, make the select captured queue stop

4.1.5 Watching task panel

Watching task panel will show task queue data.

You can select one task case and make a right click to popup a “popup menu” like following:

ID	Suite	Design	Status	Reason	Ti...
1521529	53	Conversion Branch/sapphire/AE suite/AVID C125026 Swi...	Passed	NA	1...
1521530	53	Conversion Branch/sapphire/AE suite/AVID C125026 Swi...	Passed	NA	1...
1521531	53	Conversion Branch/sapphire/AE suite/BR2 markus sap	Passed	NA	1...
1521532	53	Conversion Branch/sapphire/AE suite/BR2 markus sap	Passed	NA	1...
1521533	53	Conversion Branch/sapphire/AE suite/Broadcom 10G NIF...	Passed	NA	1...
1521534	53	Conversion Branch/sapphire/AE suite/Broadcom 10G NIF...	Passed	NA	1...
1521535	53	Conversion Branch/sapphire/AE suite/ccpu02 ei3 sap	Passed	NA	1...
1521536	53	Conversion Branch/sapphire/AE suite/ccpu02 ei3 sap	Passed	NA	1...
1521537	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521538	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521539	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521540	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521541	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521542	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521543	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521544	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521545	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521546	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521547	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521548	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521549	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521550	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521551	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521552	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	NA	1...
1521553	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	ERROR - par...	1...
1521554	53	Conversion Branch/sapphire/AE suite/diag if dsp sap	Passed	ERROR - par...	1...

Figure18: Task panel popup menu

“Retest”: will retest this case.

“View”: same function as 4.1.2.2 view menu.

“Results”: open the task case result folder.

4.1.6 Status bar

Status bar will show you current running threads number and current system info like MEM and CPU.

4.2 Launch a local test suite

Step 1: make sure your client not running in remote mode (Setting → Preference → link server)

Step 2: click File → import...

Step 3: select your test suite file

4.3 Launch remote test suite

Make sure your client not running in local mode (Setting → Preference → link server).

4.4 Report output

Report export is not ready now.

Workaround: Manually copy task case status in “Watching task panel (4)”

5 Appendix

Software address: \\lsh-smb01\sw\qa\qa_store\TMP_tools\client\client_software

TMP client build: Software QA SVN: /release/tmp_client/
