

tf.contrib.rnn.BidirectionalGridLSTMCell

Contents

Class `BidirectionalGridLSTMCell`

Properties

`activity_regularizer`

`dtype`

Class `BidirectionalGridLSTMCell`

Inherits From: `GridLSTMCell`

Defined in `tensorflow/contrib/rnn/python/ops/rnn_cell.py`.

Bidirectional GridLstm cell.

The bidirection connection is only used in the frequency direction, which hence doesn't affect the time direction's real-time processing that is required for online recognition systems. The current implementation uses different weights for the two directions.

Properties

`activity_regularizer`

Optional regularizer function for the output of this layer.

`dtype`

`graph`

`input`

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

- `AttributeError`: if the layer is connected to more than one incoming layers.

Raises:

- `RuntimeError` : If called in Eager mode.
- `AttributeError` : If no inbound nodes are found.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- `AttributeError` : if the layer has no defined `input_shape`.
- `RuntimeError` : if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Returns:

Output tensor or list of output tensors.

Raises:

- `AttributeError` : if the layer is connected to more than one incoming layers.
- `RuntimeError` : if called in Eager mode.

output_shape

Retrieves the output shape(s) of a layer.

Only applicable if the layer has one output, or if all outputs have the same shape.

Returns:

Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).

Raises:

- `AttributeError` : if the layer has no defined output shape.
- `RuntimeError` : if called in Eager mode.

output_size

scope_name

state_size

state_tuple_type

trainable_variables

trainable_weights

updates

variables

Returns the list of all layer variables/weights.

Returns:

A list of variables.

weights

Returns the list of all layer variables/weights.

Returns:

A list of variables.

Methods

`__init__`

```

__init__(
    num_units,
    use_peepholes=False,
    share_time_frequency_weights=False,
    cell_clip=None,
    initializer=None,
    num_unit_shards=1,
    forget_bias=1.0,
    feature_size=None,
    frequency_skip=None,
    num_frequency_blocks=None,
    start_freqindex_list=None,
    end_freqindex_list=None,
    couple_input_forget_gates=False,
    backward_slice_offset=0,
    reuse=None
)

```

Initialize the parameters for an LSTM cell.

Args:

- `num_units` : int, The number of units in the LSTM cell
- `use_peepholes` : (optional) bool, default False. Set True to enable diagonal/peephole connections.
- `share_time_frequency_weights` : (optional) bool, default False. Set True to enable shared cell weights between time and frequency LSTMs.
- `cell_clip` : (optional) A float value, default None, if provided the cell state is clipped by this value prior to the cell output activation.
- `initializer` : (optional) The initializer to use for the weight and projection matrices, default None.
- `num_unit_shards` : (optional) int, default 1, How to split the weight matrix. If > 1, the weight matrix is stored across `num_unit_shards`.
- `forget_bias` : (optional) float, default 1.0, The initial bias of the forget gates, used to reduce the scale of forgetting at the beginning of the training.
- `feature_size` : (optional) int, default None, The size of the input feature the LSTM spans over.
- `frequency_skip` : (optional) int, default None, The amount the LSTM filter is shifted by in frequency.
- `num_frequency_blocks` : [required] A list of frequency blocks needed to cover the whole input feature splitting defined by `start_freqindex_list` and `end_freqindex_list`.
- `start_freqindex_list` : [optional], list of ints, default None, The starting frequency index for each frequency block.
- `end_freqindex_list` : [optional], list of ints, default None. The ending frequency index for each frequency block.
- `couple_input_forget_gates` : (optional) bool, default False, Whether to couple the input and forget gates, i.e. `f_gate = 1.0 - i_gate`, to reduce model parameters and computation cost.
- `backward_slice_offset` : (optional) int32, default 0, the starting offset to slice the feature for backward processing.
- `reuse` : (optional) Python boolean describing whether to reuse variables in an existing scope. If not `True`, and the existing scope already has the given variables, an error is raised.

`__call__`

```
__call__(
    inputs,
    state,
    scope=None
)
```

Run this RNN cell on inputs, starting from the given state.

Args:

- `inputs`: 2-D tensor with shape `[batch_size x input_size]`.
- `state`: if `self.state_size` is an integer, this should be a 2-D Tensor with shape `[batch_size x self.state_size]`. Otherwise, if `self.state_size` is a tuple of integers, this should be a tuple with shapes `[batch_size x s] for s in self.state_size`.
- `scope`: VariableScope for the created subgraph; defaults to class name.

Returns:

A pair containing:

- Output: A 2-D tensor with shape `[batch_size x self.output_size]`.
- New state: Either a single 2-D tensor, or a tuple of tensors matching the arity and shapes of `state`.

__deepcopy__

```
__deepcopy__(memo)
```

add_loss

```
add_loss(
    losses,
    inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs `a` and `b`, some entries in `layer.losses` may be dependent on `a` and some on `b`. This method automatically keeps track of dependencies.

The `get_losses_for` method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- `losses`: Loss tensor, or list/tuple of tensors.
- `inputs`: Optional input tensor(s) that the loss(es) depend on. Must match the `inputs` argument passed to the `__call__` method at the time the losses are created. If `None` is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

- `RuntimeError`: If called in Eager mode.

add_update

```
add_update(  
    updates,  
    inputs=None  
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The **get_updates_for** method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- **updates** : Update op, or list/tuple of update ops.
- **inputs** : Optional input tensor(s) that the update(s) depend on. Must match the **inputs** argument passed to the **__call__** method at the time the updates are created. If **None** is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(  
    name,  
    shape,  
    dtype=None,  
    initializer=None,  
    regularizer=None,  
    trainable=True,  
    constraint=None  
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- **name** : variable name.
- **shape** : variable shape.
- **dtype** : The type of the variable. Defaults to **self.dtype** or **float32**.
- **initializer** : initializer instance (callable).
- **regularizer** : regularizer instance (callable).
- **trainable** : whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- **constraint** : constraint instance (callable).

Returns:

The created variable.

Raises:

- `RuntimeError` : If called in Eager mode with regularizers.

apply

```
apply(  
    inputs,  
    *args,  
    **kwargs  
)
```

Apply the layer on a input.

This simply wraps `self.__call__` .

Arguments:

- `inputs` : Input tensor(s).
- `*args` : additional positional arguments to be passed to `self.call` .
- `**kwargs` : additional keyword arguments to be passed to `self.call` .

Returns:

Output tensor(s).

build

```
build(_)
```

call

```
call(  
    inputs,  
    state  
)
```

Run one step of LSTM.

Args:

- `inputs` : input Tensor, 2D, [batch, num_units].
- `state` : tuple of Tensors, 2D, [batch, state_size].

Returns:

A tuple containing: - A 2D, [batch, output_dim], Tensor representing the output of the LSTM after reading "inputs" when previous state was "state". Here output_dim is num_units. - A 2D, [batch, state_size], Tensor representing the new state of LSTM after reading "inputs" when previous state was "state".

Raises:

- `ValueError` : if an `input_size` was specified and the provided inputs have a different dimension.

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

- `ValueError` : if the layer isn't yet built (in which case its weights aren't yet defined).

get_input_at

```
get_input_at(node_index)
```

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_losses_for

```
get_losses_for(inputs)
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

- `inputs` : Input tensor or list/tuple of input tensors. Must match the `inputs` argument passed to the `__call__` method at the time the losses were created. If you pass `inputs=None`, unconditional losses are returned, such as weight regularization losses.

Returns:

List of loss tensors of the layer that depend on `inputs`.

Raises:

- `RuntimeError` : If called in Eager mode.

get_output_at

```
get_output_at(node_index)
```

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

- `inputs` : Input tensor or list/tuple of input tensors. Must match the `inputs` argument passed to the `__call__` method at the time the updates were created. If you pass `inputs=None`, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on `inputs`.

Raises:

- `RuntimeError` : If called in Eager mode.

zero_state

```
zero_state(
    batch_size,
    dtype
)
```

Return zero-filled state tensor(s).

Args:

- `batch_size` : int, float, or unit Tensor representing the batch size.
- `dtype` : the data type to use for the state.

Returns:

If `state_size` is an int or TensorShape, then the return value is a **N-D** tensor of shape `[batch_size x state_size]` filled with zeros.

If `state_size` is a nested list or tuple, then the return value is a nested list or tuple (of the same structure) of **2-D** tensors with the shapes `[batch_size x s]` for each s in `state_size`.

Except as otherwise noted, the content of this page is licensed under the [Creative Commons Attribution 3.0 License](#), and code samples are licensed under the [Apache 2.0 License](#). For details, see our [Site Policies](#). Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

Stay Connected

[Blog](#)

[GitHub](#)

[Twitter](#)

Support

[Issue Tracker](#)

[Release Notes](#)

[Stack Overflow](#)

English

[Terms](#) | [Privacy](#)