

NAME

resize – set environment and terminal settings to current *xterm* window size

SYNOPSIS

resize [**-v** | **-u** | **-c**] [**-s** [*row col*]]

DESCRIPTION

Resize prints a shell command for setting the appropriate environment variables to indicate the current size of *xterm* window from which the command is run.

Resize determines the command through several steps:

- first, it finds the name of the user's shell program. It uses the **SHELL** variable if set, otherwise it uses the user's data from */etc/passwd*.
- then it decides whether to use Bourne shell syntax or C-Shell syntax. It uses a built-in table of known shells, which can be overridden by the **-u** and **-c** options.
- then *resize* asks the operating system for the terminal settings. This is the same information which can be manipulated using *stty*.
- then *resize* asks the terminal for its size in characters. Depending on whether the **-s** option is given, *resize* uses a different escape sequence to ask for this information.
- at this point, *resize* attempts to update the terminal settings to reflect the terminal window's size in pixels:
 - if the **-s** option is used, *resize* then asks the terminal for its size in pixels.
 - otherwise, *resize* asks the operating system for the information and updates that after ensuring that the window's dimensions are a multiple of the character height and width.
 - in either case, the updated terminal settings are done using a different system call than used for *stty*.
- then *resize* updates the terminal settings to reflect any altered values such as its size in rows or columns. This affects the values shown by *stty*.
- finally, *resize* generates shell commands for setting the environment variables, and writes that to the standard output.

OPTIONS

The following options may be used with *resize*:

-c This option indicates that C shell commands should be generated even if the user's current shell does not appear to use C shell syntax.

-s [*rows columns*]

This option indicates that Sun console escape sequences will be used instead of the VT100-style *xterm* escape codes. If *rows* and *columns* are given, *resize* will ask the *xterm* to resize itself using those values.

Both of the escape sequences used for this option (first to obtain the window size and second to modify it) are subject to *xterm*'s **allowWindowOps** resource setting. The window manager may also choose to disallow the change.

The VT100-style escape sequence used to determine the screen size always works for VT100-compatible terminals. VT100s have no corresponding way to modify the screensize.

-u This option indicates that Bourne shell commands should be generated even if the user's current shell does not appear to use Bourne shell syntax.

-v This causes *resize* to print a version number to the standard output, and then exit.

Note that the Sun console escape sequences are recognized by XFree86 *xterm* and by *dterm*. The *resize* program may be installed as *sunsize*, which causes it to assume the **-s** option.

The *rows* and *columns* arguments must appear last; though they are normally associated with the **-s** option, they are parsed separately.

ENVIRONMENT

SHELL	<p>Unless overridden by the -c option, <i>resize</i> determines the user's current shell by</p> <ul style="list-style-type: none"> • first checking if \$SHELL is set, and using that, • otherwise <i>resize</i> looks in the password file (<i>/etc/passwd</i>). <p>Generally Bourne-shell variants (including <i>ksh</i>) do not modify \$SHELL, so it is possible for <i>resize</i> to be confused if one runs <i>resize</i> from a Bourne shell spawned from a C shell.</p> <p>After determining the user's shell, <i>resize</i> checks the shell's name against a table of known shell names. If it does not find the name in its table, <i>resize</i> will use C shell syntax for the generated commands to set environment variables.</p>
TERM	<i>Resize</i> 's generated shell command sets this to "xterm-new" if not already set.
TERMCAP	<i>Resize</i> 's generated shell command sets this variable on systems using termcap, e.g., when <i>resize</i> is linked with the <i>termcap</i> library rather than a <i>terminfo</i> library. The latter does not provide the complete text for a termcap entry.
COLUMNS, LINES	
	<i>Resize</i> 's generated shell command sets these variables on systems using terminfo. Many applications (including the curses library) use those variables when set to override their screensize.

FILES

<i>/etc/termcap</i>	for the base termcap entry to modify.
<i>~/.cshrc</i>	user's alias for the command.

EXAMPLES

For *resize*'s output to take effect, *resize* must either be evaluated as part of the command line (usually done with a shell alias or function) or else redirected to a file which can then be read in. From the C shell (usually known as */bin/csh*), the following alias could be defined in the user's *.cshrc*:

```
% alias rs 'set noglob; eval `resize`'
```

After resizing the window, the user would type:

```
% rs
```

Users of versions of the Bourne shell (usually known as */bin/sh*) that don't have command functions will need to send the output to a temporary file and then read it back in with the "." command:

```
$ resize > /tmp/out
$ . /tmp/out
```

AUTHORS

Mark Vandevoorde (MIT-Athena), Edward Moy (Berkeley)
 Thomas Dickey (invisible-island.net).
 Copyright (c) 1984, 1985 by X Consortium
 See *X(7)* for a complete copyright notice.

SEE ALSO

use_env(3x)
csh(1), *stty(1)*, *tset(1)*
xterm(1)