

Oracle® Communications Network Charging and Control

NP Provisioning Interface Commands

Release 6.0.1

April 2017

Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

| | |
|--|-----------|
| About This Document | v |
| Document Conventions | vi |
| Chapter 1 | |
| PI Commands Overview | 1 |
| Overview | 1 |
| Command List | 1 |
| Parameter Formats..... | 2 |
| Chapter 2 | |
| PI Number Portability Package | 3 |
| Overview | 3 |
| Add a Ported Number Range | 3 |
| Modify a Ported Number Range | 6 |
| Delete a Ported Number Range | 10 |
| Query an Active Ported Number Range | 11 |
| Add a Ported Number Prefix | 12 |
| Change a Ported Number Prefix | 14 |
| Query a Ported Number Prefix | 16 |
| Delete a Ported Number Prefix | 17 |
| Add New LCR Rule Set | 17 |
| Modify LCR Rule Set | 18 |
| Delete LCR Rule Set | 19 |
| Add New LCR Rule | 20 |
| Modify LCR Rule | 23 |
| Delete LCR Rule..... | 25 |
| Add Home Routing Entry | 26 |
| Modify Home Routing Entry | 28 |
| Delete Home Routing Entry | 30 |
| Query Home Routing Entry | 31 |
| Chapter 3 | |
| Error Code Lists | 33 |
| Overview | 33 |
| PI Chassis Errors | 33 |
| PI Command Errors | 34 |
| Glossary of Terms..... | 37 |
| Index | 39 |

About This Document

Scope

The scope of this document includes all the information required to configure the NP Service Pack PI commands.

Audience

The audience for this document includes system administrators responsible for the monitoring, maintenance, and configuration of the Oracle Communications Network Charging and Control IN applications.

Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

Related Documents

The following documents are related to this document:

- *Provisioning Interface User's and Technical Guide*
- *Virtual Private Network User's Guide*

Document Conventions

Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

| Formatting Convention | Type of Information |
|--------------------------------|--|
| Special Bold | Items you must select, such as names of tabs. Names of database tables and fields. |
| <i>Italics</i> | Name of a document, chapter, topic or other publication. Emphasis within text. |
| Button | The name of a button to click or a key to press. Example: To close the window, either click Close , or press Esc . |
| Key+Key | Key combinations for which the user must press and hold down one key and then press another. Example: Ctrl+P or Alt+F4 . |
| Monospace | Examples of code or standard output. |
| Monospace Bold | Text that you must enter. |
| <i>variable</i> | Used to indicate variables or text that should be replaced with an actual value. |
| menu option > menu option > | Used to indicate the cascading menu option to be selected. Example: Operator Functions > Report Functions |
| hypertext link | Used to indicate a hypertext link. |

Specialized terms and acronyms are defined in the glossary at the end of this guide.

PI Commands Overview

Overview

Introduction

The provisioning interface (PI) uses TCP/IP-based UNIX sockets to receive provisioning commands and parameters. These are translated into SQL commands that update prepaid application tables of the SMF and E2BE Oracle databases. This chapter defines the rules and packages required to translate the provisioning commands into SQL commands.

In this chapter

This chapter contains the following topics.

| | |
|------------------------|---|
| Command List | 1 |
| Parameter Formats..... | 2 |

Command List

Command list

The following table lists the Number Portability (NP) PI functions and their corresponding commands. To use the NP PI commands the npPISms package must be installed on your system in addition to the standard piSms package.

| Function | npPISms |
|--------------------------------------|-----------|
| Add a ported number range. | NPDS1=ADD |
| Modify a ported number range. | NPDS1=CHG |
| Delete a ported number range. | NPDS1=DEL |
| Query an active ported number range. | NPDS1=QRY |
| Add a ported number prefix. | NPYZ1=ADD |
| Query a ported number prefix. | NPYZ1=QRY |
| Change a ported number prefix. | NPYZ1=CHG |
| Delete a ported number prefix. | NPYZ1=DEL |
| Add new LCR rule set. | NPLC1=ADD |
| Modify an LCR rule set. | NPLC1=CHG |
| Delete an LCR rule set. | NPLC1=DEL |
| Add a new LCR rule. | NPLC2=ADD |
| Modify an LCR rule. | NPLC2=CHG |
| Delete an LCR rule. | NPLC2=DEL |
| Add a new home routing entry. | NPHR1=ADD |
| Modify a home routing entry. | NPHR1=CHG |

| Function | npPISms |
|------------------------------|-----------|
| Delete a home routing entry. | NPHR1=DEL |
| Query a home routing entry. | NPHR1=QRY |

Parameter Formats

Number Portability PI Parameter Formats

This table describes the format of each Number Portability PI parameter.

| Parameter | Format |
|---|--|
| ACTIVATION_DATE | YYYYMMDDHHMMSS (24 hour clock) |
| ADDITIONAL_RN_ID | One to 8 digit hexadecimal number |
| CARRIER _{<i>n</i>} (<i>n</i> =1 to 8) | One to 30 character string |
| CASCADE | Y N |
| DESCRIPTION | String of up to 64 characters. |
| DN | Four to 18 digit number. |
| DN_END | Four to 18 digit number, must be the same length as the associated DN_START value. |
| DN_START | Four to 18 digit number. |
| DN_TYPE | H S |
| DONOR_ID | One to 8 digit hexadecimal number |
| ENTRY_TYPE | O S |
| NEW_NAME | String of up to 30 characters. |
| NUMBER_TYPE | F M Null |
| PORT_ID | One to 8 digit hexadecimal number |
| PQYZ | String of up to 18 characters. |
| ROUTING_DESTINATION | String of up to 64 characters. |
| ROUTING_NUMBER | String of up to eight characters. |
| RULE_SET | String of up to 30 characters. |
| URI | String of up to 50 characters. |

PI Number Portability Package

Overview

Introduction

This chapter describes the available PI commands for provisioning number portability information on the SMS.

These commands are added by the `npPISms` package that is installed when you install NCC. For more information about the PI, and the PI packages, see *PI User's and Technical Guide*. For more information about Number Portability, see the *NP Service Pack Technical Guide* and *NP Service Pack User's Guide*.

In this chapter

This chapter contains the following topics.

| | |
|---|----|
| Add a Ported Number Range | 3 |
| Modify a Ported Number Range | 6 |
| Delete a Ported Number Range | 10 |
| Query an Active Ported Number Range | 11 |
| Add a Ported Number Prefix | 12 |
| Change a Ported Number Prefix | 14 |
| Query a Ported Number Prefix | 16 |
| Delete a Ported Number Prefix | 17 |
| Add New LCR Rule Set | 17 |
| Modify LCR Rule Set | 18 |
| Delete LCR Rule Set | 19 |
| Add New LCR Rule | 20 |
| Modify LCR Rule | 23 |
| Delete LCR Rule | 25 |
| Add Home Routing Entry | 26 |
| Modify Home Routing Entry | 28 |
| Delete Home Routing Entry | 30 |
| Query Home Routing Entry | 31 |

Add a Ported Number Range

Description

Use the `NPDS1=ADD` PI command to add a new entry to the `NP_DN_RANGE` table.

Required parameters

This command requires the following parameters.

`DN_START`

Syntax: `DN_START=integer`

Description: The start of the DN number range.

Type: Integer
Optionality: Required
Allowed: The specified number must have four to 18 digits.
Default: None
Notes:
Example: DN_START=1230

DN_END

Syntax: DN_END=*integer*
Description: The end of the DN number range.
Type: Integer
Optionality: Required
Allowed: The specified number must have four to 18 digits.
Default: None
Notes: DN_END and DN_START must be the same length.
Example: DN_END=1250

ACTIVATION_DATE

Syntax: ACTIVATION_DATE=*date*
Description: The date the range will become active.
Type: Date String
Optionality: Required
Allowed: A valid date using this format: YYYYMMDDHHMMSS
Default: None
Notes:
Example: ACTIVATION_DATE=20080714000000

ENTRY_TYPE

Syntax: ENTRY_TYPE=O|S
Description: The entry type to use.
Type: String
Optionality: Required when adding a ported number range
Allowed: Either:

- O – For an operator entry type
- S – For a subscriber entry type

Default: None
Notes:
Example: ENTRY_TYPE=S

ROUTING_NUMBER

Syntax: ROUTING_NUMBER=*number*
Description: The routing number.
Type: Integer
Optionality: Required

Allowed: A hexadecimal number between 1 and 8 digits long.
Default: None
Notes:
Example: ROUTING_NUMBER=ABC123

Optional parameters

This command accepts the following optional parameters.

NUMBER_TYPE

Syntax: NUMBER_TYPE=F|M|D|Null value
Description: The number type of the DN range.
Type: String
Optionality: Optional (default used if not set)
Allowed: One of the following:

- Null value
- F - fixed
- M - mobile
- D - delete (see *Logic and constraints* (on page 9))

Default: Null
Notes:
Example: NUMBER_TYPE=F

ADDITIONAL_RN_ID

Syntax: ADDITIONAL_RN_ID=*integer*
Description: The additional routing number for the DN range.
Type: Integer
Optionality: Optional
Allowed: A hexadecimal number, 1 to 8 digits long.
Default: None
Notes:
Example: ADDITIONAL_RN_ID=001

DONOR_ID

Syntax: DONOR_ID=*integer*
Description: The donor ID number for the DN range.
Type: Integer
Optionality: Optional
Allowed: A hexadecimal number, 1 to 8 digits long. Must be a defined routing number.
Default: None
Notes:
Example: DONOR_ID=0011

PORT_ID

| | |
|---------------------|---|
| Syntax: | <code>PORT_ID=<i>integer</i></code> |
| Description: | The port ID number for the DN range. |
| Type: | Integer |
| Optionality: | Optional |
| Allowed: | A hexadecimal number, 1 to 8 digits long. Must be a defined routing number. |
| Default: | None |
| Notes: | |
| Example: | <code>PORT_ID=001</code> |

URI

| | |
|---------------------|---|
| Syntax: | <code>URI=<i>string</i></code> |
| Description: | The uri for the DN range. |
| Type: | String |
| Optionality: | Optional |
| Allowed: | Textual string, 1 to 50 characters long |
| Default: | None |
| Notes: | |
| Example: | <code>URI=Uri.com</code> |

Logic and constraints

The following rules apply when using the NPDS1=ADD command:

- The range defined by DN_START and DN_END must not overlap an existing entry of the same entry type in the NP_DN_RANGE table, except if DN_START and DN_END exactly match a defined range and ACTIVATION_DATE is different.
- Overlapping ranges of different entry types but the same DN_START and DN_END must have a different ACTIVATION_DATE.
- DN_START and DN_END must be the same length, with DN_END being of equal or higher value.
- ROUTING_NUMBER must be an existing routing number defined in the NP_ROUTING_NUMBER table.
- ADDITIONAL_RN_ID must be an existing routing number defined in the NP_ROUTING_NUMBER table. The ADDITIONAL_RN_ID routing number's associated RD_ID value must equal the ROUTING_NUMBER's associated RD_ID value.
- DONOR_ID must be a routing number defined in the NP_ROUTING_NUMBER table.
- If the maximum number of activation dates per number range is exceeded, then an error is returned: too many routing numbers for this range.
- If **eserv.config** contains the item `pi.NP.checkRN = "x"`, and the ROUTING_NUMBER matches this value "x", then the ADDITIONAL_RN_ID field must have a non-NULL value.
- If **eserv.config** contains the item `pi.localTZ = "x"`, then the data specified for ACTIVATION_DATE will be converted from the local time zone "x" to GMT before being stored in the database.

Modify a Ported Number Range

Changes the entry in the NP_DN_RANGE table that matches the supplied DN_START, DN_END, ACTIVATION_DATE and ROUTING NUMBER parameters.

Description

Use the NPDS1=CHG PI command to modify the entry to the NP_DN_RANGE table for the specified DN_START, DN_END and ACTION_DATE parameters.

Required parameters

This command requires the following parameters.

DN_START

| | |
|---------------------|---|
| Syntax: | DN_START= <i>integer</i> |
| Description: | The start of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | |
| Example: | DN_START=1230 |

DN_END

| | |
|---------------------|---|
| Syntax: | DN_END= <i>integer</i> |
| Description: | The end of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | DN_END and DN_START must be the same length. |
| Example: | DN_END=1250 |

ACTION_DATE

| | |
|---------------------|--|
| Syntax: | ACTION_DATE= <i>date</i> |
| Description: | The date the range will become active. |
| Type: | Date String |
| Optionality: | Required |
| Allowed: | A valid date using this format: YYYYMMDDHHMMSS |
| Default: | None |
| Notes: | |
| Example: | ACTION_DATE=20080714000000 |

Optional parameters

This command accepts the following optional parameters.

ENTRY_TYPE

| | |
|---------------------|------------------------|
| Syntax: | ENTRY_TYPE=O S |
| Description: | The entry type to use. |

Type: String
Optionality: Required when adding a ported number range
Allowed: Either:

- O – For an operator entry type
- S – For a subscriber entry type

Default: None

Notes:

Example: ENTRY_TYPE=S

NUMBER_TYPE

Syntax: NUMBER_TYPE=F|M|D|Null value

Description: The number type of the DN range.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

- Null value
- F - fixed
- M - mobile
- D - delete (see *Logic and constraints* (on page 9))

Default: Null

Notes:

Example: NUMBER_TYPE=F

ADDITIONAL_RN_ID

Syntax: ADDITIONAL_RN_ID=*integer*

Description: The additional routing number for the DN range.

Type: Integer

Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long.

Default: None

Notes:

Example: ADDITIONAL_RN_ID=001

DONOR_ID

Syntax: DONOR_ID=*integer*

Description: The donor ID number for the DN range.

Type: Integer

Optionality: Optional

Allowed: A hexadecimal number, 1 to 8 digits long. Must be a defined routing number.

Default: None

Notes:

Example: DONOR_ID=0011

PORT_ID

| | |
|---------------------|---|
| Syntax: | <code>PORT_ID=<i>integer</i></code> |
| Description: | The port ID number for the DN range. |
| Type: | Integer |
| Optionality: | Optional |
| Allowed: | A hexadecimal number, 1 to 8 digits long. Must be a defined routing number. |
| Default: | None |
| Notes: | |
| Example: | <code>PORT_ID=001</code> |

ROUTING_NUMBER

| | |
|---------------------|---|
| Syntax: | <code>ROUTING_NUMBER=<i>number</i></code> |
| Description: | The routing number. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | A hexadecimal number between 1 and 8 digits long. |
| Default: | None |
| Notes: | |
| Example: | <code>ROUTING_NUMBER=ABC123</code> |

URI

| | |
|---------------------|---|
| Syntax: | <code>URI=<i>string</i></code> |
| Description: | The uri for the DN range. |
| Type: | String |
| Optionality: | Optional |
| Allowed: | Textual string, 1 to 50 characters long |
| Default: | None |
| Notes: | |
| Example: | <code>URI=Uri.com</code> |

Logic and constraints

The following rules apply when using the NPDS1=CHG command:

- The range defined by DN_START and DN_END must be an existing entry in the NP_DN_RANGE table.
- The ROUTING_NUMBER must be an existing routing number defined in the NP_ROUTING_NUMBER table.
- ADDITIONAL_RN_ID must be an existing routing number defined in the NP_ROUTING_NUMBER table. The ADDITIONAL_RN_ID routing number's associated RD_ID value must equal the ROUTING_NUMBER's associated RD_ID value.
- DONOR_ID must be a routing number defined in the NP_ROUTING_NUMBER table.
- If an optional parameter needs to be removed or blanked, set the value to "null" or "NULL". The exceptions are ROUTING_NUMBER and ENTRY_TYPE, which
- must have a value.
- If changing a DN range to ENTRY_TYPE=O, set DONOR_ID=null if a DONOR_ID is already set.

- If **eserv.config** contains the item `pi.NP.checkRN = "x"`, and the `ROUTING_NUMBER` matches this value "x", the `ADDITIONAL_RN_ID` field must have a non-NULL value.
- If **eserv.config** contains the item `pi.localTZ = "x"`, the data specified for `ACTIVATION_DATE` will be converted from the local time zone "x" to GMT before being stored in the database.
- If an entry needs to be removed, set the value for the `ROUTING_NUMBER` to "null" or "NULL" and the `NUMBER_TYPE` parameter value to D or d.

Delete a Ported Number Range

Description

Use the `NPDS1=DEL PI` command to delete the entry in the `NP_DN_RANGE` table for the specified parameters.

Required parameters

This command requires the following parameters.

DN_START

| | |
|---------------------|---|
| Syntax: | <code>DN_START=<i>integer</i></code> |
| Description: | The start of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | |
| Example: | <code>DN_START=1230</code> |

DN_END

| | |
|---------------------|--|
| Syntax: | <code>DN_END=<i>integer</i></code> |
| Description: | The end of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | <code>DN_END</code> and <code>DN_START</code> must be the same length. |
| Example: | <code>DN_END=1250</code> |

Optional parameters

This command accepts the following optional parameters.

ENTRY_TYPE

| | |
|---------------------|--|
| Syntax: | <code>ENTRY_TYPE=O S</code> |
| Description: | The entry type to use. |
| Type: | String |
| Optionality: | Required when adding a ported number range |
| Allowed: | Either: |

- O – For an operator entry type
- S – For a subscriber entry type

Default: None

Notes:

Example: ENTRY_TYPE=S

ACTIVATION_DATE

Syntax: ACTIVATION_DATE=*date*

Description: The date the range will become active.

Type: Date String

Optionality: Required

Allowed: A valid date using this format: YYYYMMDDHHMMSS

Default: None

Notes:

Example: ACTIVATION_DATE=20080714000000

Logic and constraints

The following rules apply when using the NPDS1=ADD command:

- The range defined by DN_START and DN_END must be an existing entry in the NP_DN_RANGE table.
- If `eserv.config` contains the item `pi.localTZ = "x"`, then the data specified for ACTIVATION_DATE will be converted from the local time zone "x" to GMT before being used to look up the row in the database.

Query an Active Ported Number Range

Description

Use the command NPDS1 and action QRY to query an entry in the NP_DN_RANGE table for the Active Ported Number Range (APNR) of a number.

Required parameters

This command requires the following parameters.

DN

Syntax: DN=*integer*

Description: The destination number to query. The DN must be within the required DN range.

Type: Integer

Optionality: Required

Allowed: Number, 4 to 18 digits long

Default: None

Notes:

Example: DN=4124

Optional parameters

This command accepts the following optional parameters.

ENTRY_TYPE

| | |
|---------------------|--|
| Syntax: | ENTRY_TYPE=O S |
| Description: | The entry type to use. |
| Type: | String |
| Optionality: | Optional (default used if not set) |
| Allowed: | Either: <ul style="list-style-type: none"> • O – For an operator entry type. • S – For a subscriber entry type. |
| Default: | S |
| Notes: | If the DN is provisioned in both an Operator and Subscriber DN range that overlap each other, ENTRY_TYPE=O must be used to show the Operator DN range. |
| Example: | ENTRY_TYPE=S |

Logic and constraints

The following rules apply to the NPDS1=QRY command:

- The subscriber or operator name as defined by NAME must not be blank, and must not match an existing subscriber or operator.
- The range defined by DN_START and DN_END must not overlap an already defined range which has the same ENTRY_TYPE.
- DN_END must be the same length as DN_START.
- ENTRY_TYPE must be either 'S' for subscriber, or 'O' for operator.

Add a Ported Number Prefix

About Adding Ported Number Prefixes by Using PI

Use the NPYZ1=ADD PI command to add a ported number prefix definition to the NP database. To successfully add a ported number prefix definition, you must specify either the ROUTING_NUMBER or the ROUTING_DESTINATION parameter in the command. If you specify:

- Only the ROUTING_NUMBER parameter, then ROUTING_DESTINATION is automatically set to the routing destination that matches the specific routing number.
- Only the ROUTING_DESTINATION parameter, then a routing number is not associated with the prefix in the PQYZ parameter and a prefix is not added to the number if it is matched during porting.
- Both the ROUTING_DESTINATION and the ROUTING_NUMBER parameters, then the routing destination must correspond to the value configured for the specified routing number in the database.

For example, the following PI command adds the 441473 ported number prefix:

```
NPYZ1=ADD:PQYZ=441473,ROUTING_NUMBER=123,ROUTING_DESTINATION=Destination1,NUMBER_TYP
E=F,URI=uri.com,DESCRIPTION=Any text
```

After successfully adding ported number prefixes to the NP database, the PI returns this message:

```
NPYZ1=ADD:ACK;
```

If unsuccessful, then the PI may return any of the following error codes: 68, 69, 1002, 1008 or 1020.

Required Parameter

This command requires the following parameter.

PQYZ

| | |
|---------------------|---|
| Syntax: | <code>PQYZ=string</code> |
| Description: | The prefix number to use to match ported numbers. |
| Type: | String |
| Optionality: | Required |
| Allowed: | A string of up to 18 characters. |
| Example: | <code>PQYZ=441473</code> |

Optional parameters

This command accepts the following optional parameters.

ROUTING_NUMBER

| | |
|---------------------|--|
| Syntax: | <code>ROUTING_NUMBER=string</code> |
| Description: | The routing number to prepend to numbers that match the prefix in PQYZ during a ported number check. |
| Type: | String |
| Optionality: | Optional |
| Allowed: | Specify a string of up to eight characters. |
| Example: | <code>ROUTING_NUMBER=123</code> |

ROUTING_DESTINATION

| | |
|---------------------|---|
| Syntax: | <code>ROUTING_DESTINATION=string</code> |
| Description: | The routing destination. |
| Type: | String |
| Optionality: | Optional |
| Allowed: | A string of up to 64 characters. |
| Example: | <code>ROUTING_DESTINATION=Vodafone</code> |

NUMBER_TYPE

| | |
|---------------------|---|
| Syntax: | <code>NUMBER_TYPE=F M Blank or empty value</code> |
| Description: | Sets the type of ported number. |

Note: You unset the ported number type for an existing prefix definition by using the `NPYZ1=CHG` command to specify a blank or empty value for `NUMBER_TYPE`.

| | |
|---------------------|--|
| Type: | String |
| Optionality: | Optional (default used if not set) |
| Allowed: | One of the following: <ul style="list-style-type: none"> • F – For fixed number • M –For mobile number • Blank or empty value. The ported number type is not set. |
| Default: | Blank or empty value |

Example: NUMBER_TYPE=F

URI

Syntax: URI=*string*

Description: Defines the associated URI.

Type: String

Optionality: Optional

Allowed: A string of up to 50 characters.

Example: URI=uri.com

DESCRIPTION

Syntax: DESCRIPTION=*string*

Description: The description for the ported number.

Type: String

Optionality: Optional

Allowed: A string of up to 50 characters.

Example: DESCRIPTION=Any text

Change a Ported Number Prefix

About Changing Ported Number Prefixes by Using PI

Use the NPYZ1=CHG PI command to change a ported number prefix definition in the NP database. For example, the following PI command changes the definition for the 441473 ported number prefix:

```
NPYZ1=CHG:PQYZ=441473,ROUTING_NUMBER=321,ROUTING_DESTINATION=Destination2,NUMBER_TY  
PE=F,URI=uri.com,DESCRIPTION=Any text
```

If unsuccessful, then the PI may return any of the following error codes: 68, 69, 1002, 1008, 1021.

Required Parameter

This command requires the following parameter.

PQYZ

Syntax: PQYZ=*string*

Description: The prefix number, on which ported numbers are matched, that you want to change.

Type: String

Optionality: Required

Allowed: An existing PQYZ prefix string of up to 18 characters.

Example: PQYZ=441473

Optional parameters

This command accepts the following optional parameters.

ROUTING_NUMBER

Syntax: ROUTING_NUMBER=*string*

Description: The routing number to prepend to numbers that match the prefix in PQYZ during

a ported number check.

Type: String

Optionality: Optional

Allowed: Specify a string of up to eight characters.

Example: ROUTING_NUMBER=123

ROUTING_DESTINATION

Syntax: ROUTING_DESTINATION=*string*

Description: The routing destination.

Type: String

Optionality: Optional

Allowed: A string of up to 64 characters.

Example: ROUTING_DESTINATION=Vodafone

NUMBER_TYPE

Syntax: NUMBER_TYPE=F|M|Blank or empty value

Description: Sets the type of ported number.

Note: You unset the ported number type for an existing prefix definition by using the NPYZ1=CHG command to specify a blank or empty value for NUMBER_TYPE.

Type: String

Optionality: Optional (default used if not set)

Allowed: One of the following:

- F – For fixed number
- M –For mobile number
- Blank or empty value. The ported number type is not set.

Default: Blank or empty value

Example: NUMBER_TYPE=F

URI

Syntax: URI=*string*

Description: Defines the associated URI.

Type: String

Optionality: Optional

Allowed: A string of up to 50 characters.

Example: URI=uri.com

DESCRIPTION

Syntax: DESCRIPTION=*string*

Description: The description for the ported number.

Type: String

Optionality: Optional

Allowed: A string of up to 50 characters.

Example: DESCRIPTION=Any text

Query a Ported Number Prefix

About Querying Ported Number Prefixes by Using PI

Use the NPYZ1=QRY PI command to query the NP database for PQYZ entries. A PQYZ entry maps a ported number prefix to a routing destination. You can query the NP database for multiple PQYZ entries by appending the % wild card character to the DN string parameter. The query returns all the PQYZ entries that match the specified network address. For example, the following PI command returns all the number prefixes for destination addresses that start with 44147328990:

```
NPYZ1=QRY:DN=44147328990%;
```

If you do not append the % character to the PQYZ string in the query, then the query returns the longest matching PQYZ entry.

By default, the maximum number of records returned when you query the NP database is 1500. You can specify a different maximum by configuring the `pqyzMaxRecords` parameter in the `pi, NP` section of the `eserv.config` configuration file. The PI outputs an error if the query finds more records than the configured maximum. For more information about configuring the PI, see *PI User's and Technical Guide*.

After successfully performing a prefix query, the PI returns this message:

```
NPYZ1=QRY:ACK:
  PQYZ=prefix,ROUTING_NUMBER=r_number,NUMBER_TYPE=F|M,URI=uri,[DESCRIPTION=description]
  [PQYZ=...]
```

Where:

- *prefix* is a matching PQYZ prefix.
- *r_number* is the routing number for the prefix.
- *uri* is the URI associated with the prefix.
- *description* is the optional description for the prefix.

If no matching prefix is found, then the PI may return the following error codes: 69, 1004, or 1022.

Required Parameter

This command requires the following parameter.

DN

Syntax: DN=*string*

Description: A network address that is checked against PQYZ entries in the NP database. The longest matching entry is returned by default. To query the NP database for multiple PQYZ entries, enter % as the last character in the DN query string.

Type: String

Optionality: Required.

Allowed: A string of up to 18 characters.

Example: DN=44147328990%

Delete a Ported Number Prefix

About Deleting Ported Number Prefixes by Using PI

Use the NPYZ1=DEL PI command to delete ported number prefixes from the NP database. You can delete multiple ported number prefixes by appending the % wild card character to the end of the PQYZ prefix string parameter. For example, the following PI command deletes all the prefix numbers that start with the digits 4414:

```
NPYZ1=DEL:PQYZ=4414%
```

If unsuccessful, then the PI may return the following the error codes: 69, 1021, or 1022.

Required Parameter

This command requires the following parameter.

PQYZ

| | |
|---------------------|---|
| Syntax: | <code>PQYZ=string</code> |
| Description: | The prefix number, on which ported numbers are matched, that you want to delete. To delete multiple PQYZ prefix strings, specify the initial characters of the group of prefixes that you want to delete and then append it with the % wild card character. |
| Type: | String |
| Optionality: | Required |
| Allowed: | An existing PQYZ prefix string of up to 18 characters. |
| Example: | <code>PQYZ=441473</code> |

Add New LCR Rule Set

Description

Use the NPLC1=ADD PI command to add a new rule set to the NP_RULE_SET table.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | <code>RULE_SET=string</code> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | <code>RULE_SET=Rule Set 1</code> |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

There are no optional parameters for this command.

Logic and constraints

The following rule applies to the NPLC1=ADD command:

- The rule set name must not exist already.

Modify LCR Rule Set

Description

Use the NPLC1=CHG PI command to change the name of a rule set in the NP_RULE_SET table.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | <code>RULE_SET=string</code> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | <code>RULE_SET=Rule Set 1</code> |

NEW_NAME

| | |
|---------------------|--|
| Syntax: | <code>NEW_NAME=string</code> |
| Description: | The new name for the rule set specified in RULE_SET. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string of up to 30 characters. |
| Default: | None. |
| Notes: | |
| Example: | <code>NEW_NAME=Rule Set 2</code> |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

There are no optional parameters for this command.

Logic and constraints

The following rules apply to the NPLC1=CHG command:

- This rule set name must exist already.
- The new name for the rule set must be unique.

Delete LCR Rule Set

Description

Use the NPLC1=DEL PI command to delete a rule set from the NP_RULE_SET table. You can also delete any associated rules defined for the rule set.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | RULE_SET= <i>string</i> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | RULE_SET=Rule Set 1 |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

This command accepts the following optional parameters.

CASCADE

| | |
|---------------------|--|
| Syntax: | CASCADE=Y N |
| Description: | Flag to determine whether or not rules based on this rule set should also be deleted. |
| Type: | Boolean |
| Optionality: | Optional (default used if not set). |
| Allowed: | Either: Y – Cascade deletion into the NP_RULE table. N – Do not delete rules from the NP_RULE table. |
| Default: | N |
| Notes: | |
| Example: | CASCADE=Y |

Logic and constraints

The following rules apply to the NPLC1=DEL command:

- This rule set must exist in the NP_RULE_SET table.
- If CASCADE is 'N' or not specified, the rule set must not have any associated rules in the NP_RULE table.
- If CASCADE is 'Y', all rules from this set will be deleted from the NP_RULE table.

Add New LCR Rule

Description

Use the command NPLC2 and action ADD to add a new rule to the NP_RULE table for the specified rule set.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | <code>RULE_SET=string</code> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | <code>RULE_SET=Rule Set 1</code> |

ROUTING_DESTINATION

| | |
|---------------------|--|
| Syntax: | <code>ROUTING_DESTINATION=string</code> |
| Description: | The routing destination operator name. |
| Type: | String |
| Optionality: | Required when adding, modifying or deleting LCR rules. |
| Allowed: | A text string, up to 64 characters long. |
| Default: | None |
| Notes: | |
| Example: | <code>ROUTING_DESTINATION=Vodafone</code> |

CARRIER1

| | |
|---------------------|---------------------------------------|
| Syntax: | <code>CARRIER1=string</code> |
| Description: | The name of the carrier. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |

Example: `CARRIER1=Carrier 1`

Constraint required parameters

This command accepts the following constraint required parameters.

CARRIER2

Syntax: `CARRIER2=string`
Description: The name of the second carrier.
Type: String
Optionality: Must be specified if subsequent carriers are to be specified.
Allowed: A text string of up to 30 characters.
Default: None
Notes:
Example: `CARRIER2=Carrier 2`

CARRIER3

Syntax: `CARRIER3=string`
Description: The name of the third carrier.
Type: String
Optionality: Must be specified if subsequent carriers are to be specified.
Allowed: A text string of up to 30 characters.
Default: None
Notes:
Example: `CARRIER3=Carrier 3`

CARRIER4

Syntax: `CARRIER4=string`
Description: The name of the fourth carrier.
Type: String
Optionality: Must be specified if subsequent carriers are to be specified.
Allowed: A text string of up to 30 characters.
Default: None
Notes:
Example: `CARRIER4=Carrier 4`

CARRIER5

Syntax: `CARRIER5=string`
Description: The name of the fifth carrier.
Type: String
Optionality: Must be specified if subsequent carriers are to be specified.
Allowed: A text string of up to 30 characters.
Default: None
Notes:
Example: `CARRIER5=Carrier 5`

CARRIER6

| | |
|---------------------|---|
| Syntax: | <code>CARRIER6=string</code> |
| Description: | The name of the sixth carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER6=Carrier 6</code> |

CARRIER7

| | |
|---------------------|---|
| Syntax: | <code>CARRIER7=string</code> |
| Description: | The name of the 7th carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER7=Carrier 7</code> |

Optional parameters

This command accepts the following optional parameters.

CARRIER8

| | |
|---------------------|---|
| Syntax: | <code>CARRIER8=string</code> |
| Description: | The name of the 8th carrier. |
| Type: | String |
| Optionality: | Optional. May only be specified if carriers 1 to 7 are specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER8=Carrier 8</code> |

Logic and constraints

The following rules apply to the NPLC2=ADD command:

- This rule set must exist in the NP_RULE_SET table.
- The routing destination must be defined in the NP_ROUTING_DESTINATION table.
- The combined rule set and routing destination must not already be defined in the NP_RULE table.
- The carrier names must exist in the NP_CARRIER table.
- Carriers must be specified sequentially.

Modify LCR Rule

Description

Use the command NPLC2 and action CHG to change a rule in the NP_RULE table for the specified rule set.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | <code>RULE_SET=string</code> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | <code>RULE_SET=Rule Set 1</code> |

ROUTING_DESTINATION

| | |
|---------------------|--|
| Syntax: | <code>ROUTING_DESTINATION=string</code> |
| Description: | The routing destination operator name. |
| Type: | String |
| Optionality: | Required when adding, modifying or deleting LCR rules. |
| Allowed: | A text string, up to 64 characters long. |
| Default: | None |
| Notes: | |
| Example: | <code>ROUTING_DESTINATION=Vodafone</code> |

CARRIER1

| | |
|---------------------|---------------------------------------|
| Syntax: | <code>CARRIER1=string</code> |
| Description: | The name of the carrier. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER1=Carrier 1</code> |

Constraint required parameters

This command accepts the following constraint required parameters.

Chapter 2

CARRIER2

| | |
|---------------------|---|
| Syntax: | <code>CARRIER2=string</code> |
| Description: | The name of the second carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER2=Carrier 2</code> |

CARRIER3

| | |
|---------------------|---|
| Syntax: | <code>CARRIER3=string</code> |
| Description: | The name of the third carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER3=Carrier 3</code> |

CARRIER4

| | |
|---------------------|---|
| Syntax: | <code>CARRIER4=string</code> |
| Description: | The name of the fourth carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER4=Carrier 4</code> |

CARRIER5

| | |
|---------------------|---|
| Syntax: | <code>CARRIER5=string</code> |
| Description: | The name of the fifth carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |
| Allowed: | A text string of up to 30 characters. |
| Default: | None |
| Notes: | |
| Example: | <code>CARRIER5=Carrier 5</code> |

CARRIER6

| | |
|---------------------|---|
| Syntax: | <code>CARRIER6=string</code> |
| Description: | The name of the sixth carrier. |
| Type: | String |
| Optionality: | Must be specified if subsequent carriers are to be specified. |

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: `CARRIER6=Carrier 6`

`CARRIER7`

Syntax: `CARRIER7=string`

Description: The name of the 7th carrier.

Type: String

Optionality: Must be specified if subsequent carriers are to be specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: `CARRIER7=Carrier 7`

Optional parameters

This command accepts the following optional parameters.

`CARRIER8`

Syntax: `CARRIER8=string`

Description: The name of the 8th carrier.

Type: String

Optionality: Optional. May only be specified if carriers 1 to 7 are specified.

Allowed: A text string of up to 30 characters.

Default: None

Notes:

Example: `CARRIER8=Carrier 8`

Logic and constraints

The following rules apply to the `NPLC2=CHG` command:

- This rule set must exist in the `NP_RULE_SET` table.
- The routing destination must be defined in the `NP_ROUTING_DESTINATION` table.
- The combined rule set and routing destination must exist in the `NP_RULE` table.
- The carrier names must exist in the `NP_CARRIER` table.
- Carriers must be specified sequentially.
- All carriers (carriers 1 to 8) will be updated, therefore you must specify a value for each of the required carriers. Carriers for which you do not specify a value will be set to null.

Delete LCR Rule

Description

Use the `NPLC2=DEL` PI command to delete a rule from the `NP_RULE` table for the specified rule set and routing destination.

Required parameters

This command requires the following parameters.

RULE_SET

| | |
|---------------------|--|
| Syntax: | <code>RULE_SET=<i>string</i></code> |
| Description: | The name of a the rule set you want to add, change, or delete. |
| Type: | String |
| Optionality: | Required. |
| Allowed: | Textual string, 1 to 30 characters long. |
| Default: | None. |
| Notes: | |
| Example: | <code>RULE_SET=Rule Set 1</code> |

ROUTING_DESTINATION

| | |
|---------------------|--|
| Syntax: | <code>ROUTING_DESTINATION=<i>string</i></code> |
| Description: | The routing destination operator name. |
| Type: | String |
| Optionality: | Required when adding, modifying or deleting LCR rules. |
| Allowed: | A text string, up to 64 characters long. |
| Default: | None |
| Notes: | |
| Example: | <code>ROUTING_DESTINATION=Vodafone</code> |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

There are no optional parameters for this command.

Logic and constraints

The following rules apply to the NPLC2=DEL command:

- This rule set must exist in the NP_RULE_SET table.
- The routing destination must be defined in the NP_ROUTING_DESTINATION table.
- The combination of rule set and routing destination must exist in the NP_RULE table.

Add Home Routing Entry

Description

Use the NPHR1=ADD PI command to add a new home routing entry in the NP_HOME_ROUTING table.

Required parameters

This command requires the following parameters.

DN_START

Syntax: `DN_START=integer`
Description: The start of the DN number range.
Type: Integer
Optionality: Required
Allowed: The specified number must have four to 18 digits.
Default: None
Notes:
Example: `DN_START=1230`

DN_END

Syntax: `DN_END=integer`
Description: The end of the DN number range.
Type: Integer
Optionality: Required
Allowed: The specified number must have four to 18 digits.
Default: None
Notes: DN_END and DN_START must be the same length.
Example: `DN_END=1250`

Constraint required parameters

This command accepts the following constraint required parameters.

DN_TYPE

Syntax: `DN_TYPE=H|S`
Description: The type of DN.
Type: String
Optionality: Optional (default used if not set).
Allowed: Either:

- H - home
- S - special

Default: S
Notes: If the ROUTING_DESTINATION field is not specified, DN_TYPE must be set to S.
Example: `DN_TYPE=H`

Optional parameters

This command accepts the following optional parameters.

ROUTING_DESTINATION

Syntax: `ROUTING_DESTINATION=string`
Description: The routing destination operator name.
Type: String

| | |
|---------------------|--|
| Optionality: | Required when adding, modifying or deleting LCR rules. |
| Allowed: | A text string, up to 64 characters long. |
| Default: | None |
| Notes: | |
| Example: | ROUTING_DESTINATION=Vodafone |

Logic and constraints

The following rules apply to the NPHR1=ADD command:

- The range defined by DN_START and DN_END must not overlap an already defined range.
- DN_END must be the same length as DN_START.
- If specified, ROUTING_DESTINATION must be a routing destination defined in the np_routing_destination table.
- The DN_LENGTH field in the NP_HOME_ROUTING table is populated by a database trigger.
- If ROUTING_DESTINATION is specified, DN_TYPE must be 'H' or 'S'.
- If ROUTING_DESTINATION is not specified, DN_TYPE must be 'S'.
- DN_TYPE will default to 'S' if the ROUTING_DESTINATION is not specified and DN_TYPE is not specified.

Modify Home Routing Entry

Description

Use the NPHR1=CHG PI command to modify an existing entry in the NP_HOME_ROUTING table.

Required parameters

This command requires the following parameters.

DN_START

| | |
|---------------------|---|
| Syntax: | DN_START= <i>integer</i> |
| Description: | The start of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | |
| Example: | DN_START=1230 |

DN_END

| | |
|---------------------|---|
| Syntax: | DN_END= <i>integer</i> |
| Description: | The end of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | DN_END and DN_START must be the same length. |

Example: `DN_END=1250`

Constraint required parameters

This command accepts the following constraint required parameters.

DN_TYPE

Syntax: `DN_TYPE=H|S`

Description: The type of DN.

Type: String

Optionality: Optional (default used if not set).

Allowed: Either:

- H - home
- S - special

Default: S

Notes: If the ROUTING_DESTINATION field is not specified, DN_TYPE must be set to S.

Example: `DN_TYPE=H`

Optional parameters

This command accepts the following optional parameters.

ROUTING_DESTINATION

Syntax: `ROUTING_DESTINATION=string`

Description: The routing destination operator name.

Type: String

Optionality: Required when adding, modifying or deleting LCR rules.

Allowed: A text string, up to 64 characters long.

Default: None

Notes:

Example: `ROUTING_DESTINATION=Vodafone`

Logic and constraints

The following rules apply to the NPHR1=CHG command:

- The range defined by DN_START and DN_END must exist already in the NP_HOME_ROUTING table.
- If specified, ROUTING_DESTINATION must be a routing destination defined in the NP_ROUTING_DESTINATION table.
- If ROUTING_DESTINATION is specified, DN_TYPE must be 'H' or 'S'.
- If ROUTING_DESTINATION is not specified, DN_TYPE must be 'S'. An existing set ROUTING_DESTINATION will be made null.
- DN_TYPE will default to 'S' if the ROUTING_DESTINATION is not specified and DN_TYPE is not specified.

Delete Home Routing Entry

Description

Use the NPHR1=DEL PI command to delete an existing entry from the NP_HOME_ROUTING table.

Required parameters

This command requires the following parameters.

DN_START

| | |
|---------------------|---|
| Syntax: | <code>DN_START=<i>integer</i></code> |
| Description: | The start of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | |
| Example: | <code>DN_START=1230</code> |

DN_END

| | |
|---------------------|---|
| Syntax: | <code>DN_END=<i>integer</i></code> |
| Description: | The end of the DN number range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | The specified number must have four to 18 digits. |
| Default: | None |
| Notes: | DN_END and DN_START must be the same length. |
| Example: | <code>DN_END=1250</code> |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

There are no optional parameters for this command.

Logic and constraints

The following rule applies to the NPHR1=DEL command:

- The range defined by DN_START and DN_END must exist already in the NP_HOME_ROUTING table.

Query Home Routing Entry

Description

Use the NPHR1=QRY PI command to query an entry in the NP_HOME_ROUTING table for the following information:

- DN range
- Routing destination
- DN type

Required parameters

This command requires the following parameters.

DN

| | |
|---------------------|---|
| Syntax: | <code>DN=<i>integer</i></code> |
| Description: | The destination number to query. The DN must be within the required DN range. |
| Type: | Integer |
| Optionality: | Required |
| Allowed: | Number, 4 to 18 digits long |
| Default: | None |
| Notes: | |
| Example: | <code>DN=4124</code> |

Constraint required parameters

There are no constraint required parameters for this command.

Optional parameters

There are no optional parameters for this command.

Logic and constraints

The following rules apply to the NPHR1=QRY command:

- The DN must be within the DN range you want to query, that is, the DN must be \geq DN_START and \leq DN_END.
- The DN must be formatted correctly. It must be a number between 4 and 18 digits long.

Error Code Lists

Overview

Introduction

This chapter explains the error codes for NP PI commands.

In this chapter

This chapter contains the following topics.

| | |
|------------------------|----|
| PI Chassis Errors..... | 33 |
| PI Command Errors..... | 34 |

PI Chassis Errors

Error List

This table describes the PI Chassis error codes.

| Code | Message | Description |
|------|---|---|
| 70 | TOO MANY SESSIONS | All PI sessions are in use. |
| 71 | LOGON SYNTAX ERROR | The login string was incorrectly formatted. |
| 72 | INVALID LOGON - username, password | Invalid username and/or password |
| 73 | INVALID LOGON - user not allowed on this port | The user attempted to log in to the wrong PI port. |
| 74 | INVALID LOGON - host | The PI client is unknown. |
| 75 | UNKNOWN COMMAND | Client sent an unknown command. |
| 76 | USER DOES NOT HAVE SUFFICIENT SECURITY | The user's security level is less than the command's security level. |
| 77 | SYNSTAMP NOT FOUND | Synstamps are turned on, but the client did not send one. |
| 78 | SYNSTAMP NOT VALID | Synstamps are turned on, but the synstamp sent by the client is invalid. |
| 79 | INVALID OR MISSING CHECKSUM | Checksums are turned on, but the client is one of the following: <ul style="list-style-type: none"> • Did not send one • It was invalid |
| 80 | UNKNOWN PARAMETER FOR COMMAND | A parameter was sent that was not valid for this command. |
| 81 | MISSING PARAMETERS FROM COMMAND | A required parameter is missing. |

| Code | Message | Description |
|------|-------------------------|---|
| 82 | | Undefined |
| 83 | DUPLICATE PARAMETER | The client sent two identically named parameters. |
| 84 | ERROR RUNNING PROCEDURE | An internal error occurred running the command. |
| 85 | USER SESSION TERMINATED | The user's session has been terminated by an administrator. |
| 86 | COMMAND TOO BIG | The command sent is too long. Indicates an incorrectly formatted command. |
| 87 | COMMAND SYNTAX ERROR | The command sent is incorrectly formatted. |
| 88 | PARAMETER NAME TOO BIG | A parameter name is too long. Indicates the command was incorrectly formatted. |
| 89 | PARAMETER VALUE TOO BIG | A parameter value is too long. Indicates the command was incorrectly formatted. |
| 90 | SYNSTAMP OUT OF PLACE | The synstamp is not at the end of the command, but before the checksum. |
| 91 | TIMEOUT | The command took too long to run. |

PI Command Errors

Number Portability PI Error Codes

This table lists the error codes and error messages for the Number Portability PI commands.

| Code | Error Message | Commands |
|------|---|---|
| 68 | Badly formatted parameter <i>name</i> . Where <i>name</i> is an invalid parameter name. | All commands. |
| 69 | This error indicates that an error without a specific error code has occurred for a NP PI command. Details about the error are included in the error text. | All commands. |
| 1000 | The specified range <i>start</i> to <i>end</i> [with activation date <i>date</i>] overlaps an already defined range of the same entry type Where: <ul style="list-style-type: none"> <i>start</i> is the start of the DN range <i>end</i> is the end of the DN range <i>date</i> is DN range activation date | NPDS1=ADD (includes text in square brackets) NPHR1=ADD NPDS1=CHG (includes text in square brackets) |
| 1001 | The end of range <i>end</i> is a different length to the start of range <i>start</i> Where: <ul style="list-style-type: none"> <i>end</i> is the end of the DN range <i>start</i> is the start of the DN range | NPDS1=ADD NPDHR1=ADD |
| 1002 | This error displays one of the following error messages: <ul style="list-style-type: none"> The routing number <i>number</i> is not defined in the routing number table. The number type <i>string</i> is not defined | NPDS1=ADD NPDS1=CHG NPYZ1=ADD NPYZ1=CHG |

| Code | Error Message | Commands |
|------|--|---|
| | <p>in the number type.</p> <ul style="list-style-type: none"> The given URI is too long. <p>Where:</p> <ul style="list-style-type: none"> <i>number</i> is the undefined routing number. <i>string</i> is the undefined number type. | |
| 1003 | <p>The specified range <i>start</i> to <i>end</i> [with activation date <i>date</i>] is not defined</p> <p>Where:</p> <ul style="list-style-type: none"> <i>start</i> is the start of the DN range specified in the PI command. <i>end</i> is the end of the DN range specified in the PI command. <i>date</i> is DN range activation date specified in the PI command. | <p>NPDS1=CHG (includes text in square brackets)</p> <p>NPDS1=DEL (includes text in square brackets)</p> <p>NPHR1=CHG</p> <p>NPHR1=DEL</p> |
| 1004 | <p>The DN <i>number</i> was not matched.</p> <p>Where <i>number</i> is the value specified for DN in the PI command.</p> | <p>NPDS1=QRY</p> <p>NPHR1=QRY</p> <p>NPYZ1=QRY</p> |
| 1005 | <p>A rule set with name <i>name</i> is already defined</p> <p>Where <i>name</i> is the rule set name specified in RULE_SET in the PI command.</p> | <p>NPLC1=ADD</p> <p>NPLC1=CHG</p> |
| 1006 | <p>A rule set with name <i>name</i> is not defined</p> <p>Where <i>name</i> is the rule set name specified in RULE_SET in the PI command.</p> | <p>NPLC1=CHG</p> <p>NPLC1=DEL</p> <p>NPLC2=ADD</p> <p>NPLC2=CHG</p> <p>NPLC2=DEL</p> |
| 1007 | <p>The rule set <i>name</i> has associated rules</p> <p>Where <i>name</i> is the rule set name specified in RULE_SET in the PI command.</p> | <p>NPLC1=DEL</p> |
| 1008 | <p>The routing destination <i>string</i> is not defined in the routing destination table.</p> <p>Where <i>string</i> is the value specified for ROUTING_DESTINATION in the PI command.</p> | <p>NPLC2=ADD</p> <p>NPLC2=CHG</p> <p>NPLC2=DEL</p> <p>NPHR1=ADD</p> <p>NPHR1=CHG</p> <p>NPYZ1=ADD</p> <p>NPYZ1=CHG</p> |
| 1009 | <p>The rule set <i>name</i> and routing destination <i>string</i> are already defined in the rules table</p> <p>Where:</p> <ul style="list-style-type: none"> <i>name</i> is the rule set name specified in RULE_SET in the PI command. <i>string</i> is the value specified for ROUTING_DESTINATION in the PI command.. | <p>NPLC2=ADD</p> |

| Code | Error Message | Commands |
|------|---|---|
| 1010 | <p>CARRIERn must be defined if CARRIERm, where m is greater than n, is defined</p> <p>Where:</p> <ul style="list-style-type: none"> n is the carrier number before CARRIERm. m is the carrier number after CARRIERn. <p>Note: Carriers must be defined in order.</p> | <p>NPLC2=ADD</p> <p>NPLC2=CHG</p> |
| 1011 | <p>The rule set <i>name</i> and routing destination <i>string</i> are not defined in the rules table</p> <p>Where:</p> <ul style="list-style-type: none"> <i>name</i> is the rule set name specified in RULE_SET in the PI command. <i>string</i> is the value specified for ROUTING_DESTINATION in the PI command. | <p>NPLC2=CHG</p> <p>NPLC2=DEL</p> |
| 1012 | <p>The DN_TYPE <i>type</i> is not a known type</p> <p>Where <i>type</i> is the DN type specified in DN_TYPE in the PI command.</p> | <p>NPHR1=ADD</p> <p>NPHR1=CHG</p> |
| 1013 | <p>The CARRIERn <i>name</i> is not a known carrier</p> <p>Where:</p> <ul style="list-style-type: none"> n is the carrier number specified in the PI command. The <i>name</i> specified in CARRIERn is not an existing carrier name for that carrier number. | <p>NPLC2=ADD</p> <p>NPLC2=CHG</p> |
| 1014 | <p>The start of range <i>start</i> is after the end of range <i>end</i></p> <p>Where:</p> <ul style="list-style-type: none"> <i>start</i> is the value specified for the start of the DN range in the PI command. <i>end</i> is the value specified for the end of the DN range in the PI command. | <p>NPDS1=ADD</p> <p>NPDS1=CHG</p> <p>NPDS1=DEL</p> <p>NPHR1=ADD</p> <p>NPHR1=CHG</p> <p>NPHR1=DEL</p> |
| 1015 | <p>DN_TYPE not specified when ROUTING_DESTINATION is specified</p> | <p>NPHR1=ADD</p> <p>NPHR1=CHG</p> |
| 1020 | <p>The specified PQYZ <i>number</i> is already defined.</p> <p>Where <i>number</i> is the PQYZ number specified in the PI command.</p> | <p>NPYZ1=ADD</p> |
| 1021 | <p>The specified PQYZ <i>number</i> is not present.</p> <p>Where <i>number</i> is the PQYZ number specified in the PI command.</p> | <p>NPYZ1=CHG</p> <p>NPYZ1=DEL</p> |
| 1022 | <p>Max query results exceeded. Try a smaller range.</p> <p>To reduce the number of records found when you use the NPYZ1=QRY PI command, enter an additional character in the query string before you append the % wild card character.</p> | <p>NPYZ1=QRY</p> |

Glossary of Terms

DTMF

Dual Tone Multi-Frequency - system used by touch tone telephones where one high and one low frequency, or tone, is assigned to each touch tone button on the phone.

GUI

Graphical User Interface

IN

Intelligent Network

IP

1) Internet Protocol

2) Intelligent Peripheral - This is a node in an Intelligent Network containing a Specialized Resource Function (SRF).

NP

Number Portability

PI

Provisioning Interface - used for bulk database updates/configuration instead of GUI based configuration.

SLC

Service Logic Controller (formerly UAS).

SMS

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform
- NCC Service Management System application

SQL

Structured Query Language is a database query language.

SRF

Specialized Resource Function – This is a node on an IN which can connect to both the SSP and the SLC and delivers additional special resources into the call, mostly related to voice data, for example play voice announcements or collect DTMF tones from the user. Can be present on an SSP or an Intelligent Peripheral (IP).

SSP

Service Switching Point

TCP

Transmission Control Protocol. This is a reliable octet streaming protocol used by the majority of applications on the Internet. It provides a connection-oriented, full-duplex, point to point service between hosts.

URI

Uniform Resource Identifier.

Index

A

About Adding Ported Number Prefixes by Using PI • 12
About Changing Ported Number Prefixes by Using PI • 14
About Deleting Ported Number Prefixes by Using PI • 17
About Querying Ported Number Prefixes by Using PI • 16
About This Document • v
ACTIVATION_DATE • 4, 7, 11
Add a Ported Number Prefix • 12
Add a Ported Number Range • 3
Add Home Routing Entry • 26
Add New LCR Rule • 20
Add New LCR Rule Set • 17
ADDITIONAL_RN_ID • 5, 8
Audience • v

C

CARRIER1 • 20, 23
CARRIER2 • 21, 24
CARRIER3 • 21, 24
CARRIER4 • 21, 24
CARRIER5 • 21, 24
CARRIER6 • 22, 24
CARRIER7 • 22, 25
CARRIER8 • 22, 25
CASCADE • 19
Change a Ported Number Prefix • 14
Command list • 1
Command List • 1
Constraint required parameters • 17, 18, 19, 21, 23, 26, 27, 29, 30, 31
Copyright • ii

D

Delete a Ported Number Prefix • 17
Delete a Ported Number Range • 10
Delete Home Routing Entry • 30
Delete LCR Rule • 25
Delete LCR Rule Set • 19
Description • 3, 7, 10, 11, 17, 18, 19, 20, 23, 25, 26, 28, 30, 31
DESCRIPTION • 14, 15
DN • 11, 16, 31
DN_END • 4, 7, 10, 27, 28, 30
DN_START • 3, 7, 10, 27, 28, 30
DN_TYPE • 27, 29
Document Conventions • vi
DONOR_ID • 5, 8
DTMF • 37

E

ENTRY_TYPE • 4, 7, 10, 12
Error Code Lists • 33
Error List • 33

G

GUI • 37

I

IN • 37
IP • 37

L

Logic and constraints • 5, 6, 8, 9, 11, 12, 18, 19, 20, 22, 25, 26, 28, 29, 30, 31

M

Modify a Ported Number Range • 6
Modify Home Routing Entry • 28
Modify LCR Rule • 23
Modify LCR Rule Set • 18

N

NEW_NAME • 18
NP • 37
Number Portability PI Error Codes • 34
Number Portability PI Parameter Formats • 2
NUMBER_TYPE • 5, 8, 13, 15

O

Optional parameters • 5, 7, 10, 12, 13, 14, 18, 19, 22, 25, 26, 27, 29, 30, 31
Overview • 1, 3, 33

P

Parameter Formats • 2
PI • 37
PI Chassis Errors • 33
PI Command Errors • 34
PI Commands Overview • 1
PI Number Portability Package • 3
PORT_ID • 6, 9
PQYZ • 13, 14, 17
Prerequisites • v

Q

Query a Ported Number Prefix • 16
Query an Active Ported Number Range • 11
Query Home Routing Entry • 31

R

Related Documents • v
Required Parameter • 13, 14, 16, 17
Required parameters • 3, 7, 10, 11, 17, 18, 19, 20, 23, 26, 28, 30, 31

ROUTING_DESTINATION • 13, 15, 20, 23, 26,
27, 29
ROUTING_NUMBER • 4, 9, 13, 14
RULE_SET • 17, 18, 19, 20, 23, 26

S

Scope • v
SLC • 37
SMS • 37
SQL • 37
SRF • 37
SSP • 38

T

TCP • 38
Typographical Conventions • vi

U

URI • 6, 9, 14, 15, 38