

# **Oracle® Communications Network Charging and Control**

EDR Control Agent Technical Guide

Release 6.0.1

April 2017

# Copyright

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

About This Document .....	v
Document Conventions .....	vi
<b>Chapter 1</b>	
<b>System Overview .....</b>	<b>1</b>
Overview .....	1
Introduction to EDR Control Agent .....	1
Statistics and Reports .....	4
<b>Chapter 2</b>	
<b>Configuration .....</b>	<b>7</b>
Overview .....	7
Configuration Overview .....	7
eserv.config Configuration .....	7
<b>Chapter 3</b>	
<b>Background Processes .....</b>	<b>11</b>
Overview .....	11
edrControlAgent .....	11
<b>Chapter 4</b>	
<b>Troubleshooting .....</b>	<b>23</b>
Overview .....	23
Possible Problems .....	23
<b>Chapter 5</b>	
<b>About Installation and Removal .....</b>	<b>25</b>
Overview .....	25
Installation and Removal Overview .....	25
Checking the Installation .....	25
Post-installation Configuration .....	26
<b>Glossary of Terms .....</b>	<b>27</b>
<b>Index .....</b>	<b>31</b>



# About This Document

## Scope

The scope of this document includes all the information required to install, configure, and administer the Oracle Communications Network Charging and Control EDR Control Agent.

## Audience

This guide was written primarily for system administrators and persons installing, configuring, and administering the EDR Control Agent application. However, sections of the document may be useful to anyone requiring an introduction to the application.

## Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential pre-requisite for safely using the information contained in this technical guide. Attempting to install, remove, configure, or otherwise alter the described system without the appropriate background skills, could cause damage to the system; including temporary or permanent incorrect operation, loss of service, and may render your system beyond recovery.

Although it is not a pre-requisite to using this guide, familiarity with the target platform would be an advantage.

This manual describes system tasks that should only be carried out by suitably trained operators.

## Related Documents

The following documents are related to this document:

- *Service Logic Execution Environment Technical Guide*
- *Advanced Control Services Technical Guide*
- *Service Management System User's Guide*
- *Service Management System Technical Guide*

# Document Conventions

## Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

Formatting Convention	Type of Information
<b>Special Bold</b>	Items you must select, such as names of tabs. Names of database tables and fields.
<i>Italics</i>	Name of a document, chapter, topic or other publication. Emphasis within text.
<b>Button</b>	The name of a button to click or a key to press. <b>Example:</b> To close the window, either click <b>Close</b> , or press <b>Esc</b> .
<b>Key+Key</b>	Key combinations for which the user must press and hold down one key and then press another. Example: <b>Ctrl+P</b> or <b>Alt+F4</b> .
Monospace	Examples of code or standard output.
<b>Monospace Bold</b>	Text that you must enter.
<i>variable</i>	Used to indicate variables or text that should be replaced with an actual value.
menu option > menu option >	Used to indicate the cascading menu option to be selected. Example: <b>Operator Functions &gt; Report Functions</b>
<a href="#">hypertext link</a>	Used to indicate a hypertext link.

Specialized terms and acronyms are defined in the glossary at the end of this guide.

# System Overview

## Overview

### Introduction

This chapter provides a high-level overview of the application. It explains the basic functionality of the system and lists the main components.

It is not intended to advise on any specific Oracle Communications Network Charging and Control (NCC) network or service implications of the product.

### In this Chapter

---

This chapter contains the following topics.

Introduction to EDR Control Agent .....	1
Statistics and Reports.....	4

## Introduction to EDR Control Agent

### Purpose

The Oracle Communications Network Charging and Control EDR Control Agent (ECA) is a SLEE interface that takes EDRs and translates them into InitialDPs (IDPs). These IDPs can be used to trigger control plans on an SLC. This enables a user to use additional functionality provided by call processing (such as control plans) to process information collected in EDRs from switches or other sources.


### Example solution

One possible use of the ECA is to check if a subscriber is using his or her SIM card with its original handset. This can be achieved by sending the IMEI to an ACS control plan.

ECA reads the IMEI from the EDR and sends it to `slee_acs` in an InitialDP in the `tbcdExtensionstring` field. The control plan then uses a Profile Field Comparison node to compare the relevant extension call context value with a profile field holding the subscriber's original IMEI. If it matches, a discount or a bonus can be applied to the account.

## Component diagram

This diagram shows the ECA components.



## Component descriptions

This table describes the main components involved in the ECA application.


Component	Description	Further Information
edrControlAgent	Main ECA executable, responsible for all EDR processing. Opens and parses EDRs in the input directory and moves EDRs into success or failed directories depending on plug-in processing. Uses plug-in libraries to process specific EDR types.	<i>edrControlAgent</i> (on page 11)
edrSimplePlugin.so	Basic plug-in for edrControlAgent.	<i>edrSimplePlugin.so</i> (on page 15)
SLEE	The SLEE routes calls between applications and interfaces.	<i>Service Logic Execution Environment Technical Guide</i>
SLEE.cfg	Main configuration file for SLEE. Provides some startup configuration for ECA, including number of instances.	<i>Service Logic Execution Environment Technical Guide</i>
IN Applications	This could be any call processing component, but is usually <code>slee_acs</code> .	<i>Advanced Control Services Technical Guide</i>
Switch	One of many possible sources of EDRs.	
eserv.config	Main configuration file for ECA.	<b>eserv.config</b>



Component	Description	Further Information
		Configuration (on page 7)

## EDR processing diagram

This diagram shows ECA processing.



## EDR processing

This table describes the stages involved in processing EDRs.

**Note:** This process uses `slee_acs`. However, other compatible call processing software could be used.

Step	Action
1	EDR files arrive in the input directory.
2	<code>edrControlAgent</code> moves the EDRs from the input directory to the processing directory.
3	<code>edrControlAgent</code> passes the EDR file to its plug-in. The plug-in parses EDRs from the EDR file.
4	For each EDR in the EDR file, the <code>edrControlAgent</code> plug-in generates a TCAP BEGIN containing an InitialDP and call duration that the <code>edrControlAgent</code> sends to <code>slee_acs</code> across the SLEE. The plug-in populates the InitialDP using specific configuration (such as <i>idpParameters</i> (on page 16)). For more information about: <ul style="list-style-type: none"> <li>SLEE configuration, see <i>NCC Service Logic Execution Environment Technical Guide</i></li> <li><code>slee_acs</code>, see <i>Advanced Control Services Technical Guide</i></li> </ul>
5	<code>slee_acs</code> runs the relevant control plan. This may involve further TCAP operations being passed between <code>slee_acs</code> and <code>edrControlAgent</code> .
6	When the call is over (due to an appropriate TCAP operation or a timeout), the <code>edrControlAgent</code> 's plug-in closes the file. If the EDRs were successful, it moves the file to

Step	Action
	the success directory. Any EDRs that could not be parsed are written to a separate file in the failed directory.

## Supported InitialDP operations

edrControlAgent uses CAP 3 INAP in messages to slee\_acs. These INAP operations are supported:

- InitialDP
- ApplyChargingReport
- EventReportBCSM
- RequestReportBCSMEvent
- ApplyCharging
- Connect
- Continue
- ReleaseCall

## Unsupported InitialDP parameters

All other INAP operations are not supported, including:

- ConnectToResouce
- EstablishTemporaryConnection
- PlayAnnouncement
- PromptAndCollectUserInformation
- DisconnectLeg
- CallInformationRequest

**Warning:** You must set up the control plans, the **acs.conf** file, and **eserv.config** file so that these and other unsupported operations are not received by edrControlAgent in EDRs.

# Statistics and Reports

## Introduction

edrControlAgent logs statistics to the Service Management System statistics subsystem if configured to do so in **eserv.config**. edrControlAgent uses Application ID ECA.

For more information about the SMS statistics subsystem, see *Service Management System Technical Guide* and *Service Management System User's Guide*.

## Statistics

This table describes the statistics that can be logged by edrControlAgent.

Statistic	Description
INITIALDPS_SENT	Number of InitialDP operations sent.
CALL_PROCESSING_FAILED	Number of InitialDPs for which processing failed.
APPLY_CHARGING_CONNECT_SUCCESSFUL	Number of calls where AC-Connect received.
APPLY_CHARGING_CONTINUE_SUCCESSFUL	Number of calls where AC-Continue received.
APPLY_CHARGING_CONNECT_INSUFFICIENT	Number of calls where (AC-Connect) duration is

Statistic	Description
T_FUNDS	greater than granted time.
APPLY_CHARGING_CONTINUE_INSUFFICIENT_FUNDS	Number of calls where (AC-Continue) duration is greater than granted time.
RELEASE_CALL	Number of calls where a (ReleaseCall) was received. Detail = cause.
CONNECT	Number of calls where Connect received.
CONTINUE	Number of calls where Continue received.
TIMED_OUT	Number of calls for which the tssf timer expired. For more information about the tssf timer, see <i>tssf</i> (on page 15).

## Reports

ECA does not install any specific reports. However, you can report on any statistics that are recorded using the SMS Application report on the Service Management System Report Functions screen.

For more information about running SMS reports, see *Service Management System User's Guide*.

## Report example

This text shows an example of the SMS Application report run for ECA for the previous 24 hours showing Total counts for each statistic.

```
Application Statistics Listing
=====
Hours since: 24
Application: ECA
Report Type: Totals
```

```
08 January 2008, 02:27:35
```

Node Name	Statistics ID	Totals
-----	-----	-----
prodscpl	CONNECT	0
prodscpl	CONTINUE	106
prodscpl	TIMED_OUT	1200
prodscpl	RELEASE_CALL	1209
prodscpl	INITIALDPS_SENT	6102
prodscpl	CALL_PROCESSING_FAILED	91
prodscpl	APPLY_CHARGING_CONNECT_SUCCESSFUL	3192
prodscpl	APPLY_CHARGING_CONTINUE_SUCCESSFUL	0
prodscpl	APPLY_CHARGING_CONNECT_INSUFFICIENT_FUNDS	79
prodscpl	APPLY_CHARGING_CONTINUE_INSUFFICIENT_FUNDS	0

```
10 rows selected.
```

```
Completed
```



# Configuration

## Overview

### Introduction

This chapter explains how to configure the Oracle Communications Network Charging and Control (NCC) application.

### In this chapter

---

This chapter contains the following topics.

Configuration Overview .....	7
eserv.config Configuration .....	7

## Configuration Overview

### Introduction

This topic provides a high-level overview of how you configure EDR Control Agent.

### Configuration components

You configure ECA by using the following components:

Component	Locations	Description	Further Information
<b>eserv.config</b>	SLCs	The most important configuration file. It configures most NCC applications, including ECA processes.  Use the ECA section of <b>eserv.config</b> to configure ECA.	<b>eserv.config Configuration</b> (on page 7).
<b>SLEE.cfg</b>	SLCs	Sets details about how the ECA runs, including number of instances.	<i>Service Logic Execution Environment Technical Guide</i>

## eserv.config Configuration

### Introduction

The **eserv.config** file is a shared configuration file, from which many Oracle Communications Network Charging and Control (NCC) applications read their configuration. Each NCC machine (SMS, SLC, and VWS) has its own version of this configuration file, containing configuration relevant to that machine. The **eserv.config** file contains different sections; each application reads the sections of the file that contains data relevant to it.

The **eserv.config** file is located in the **/IN/service\_packages/** directory.

The **eserv.config** file format uses hierarchical groupings, and most applications make use of this to divide the options into logical groupings.

### Configuration File Format

To organize the configuration data within the **eserv.config** file, some sections are nested within other sections. Configuration details are opened and closed using either **{ }** or **[ ]**.

- Groups of parameters are enclosed with curly brackets – **{ }**
- An array of parameters is enclosed in square brackets – **[ ]**
- Comments are prefaced with a **#** at the beginning of the line

To list things within a group or an array, elements must be separated by at least one comma or at least one line break. Any of the following formats can be used, as in this example:

```
{ name="route6", id = 3, prefixes = [ "00000148", "0000473" ] }
{ name="route7", id = 4, prefixes = [ "000001049" ] }
```

or

```
{ name="route6"
  id = 3
  prefixes = [
    "00000148"
    "0000473"
  ]
}
{ name="route7"
  id = 4
  prefixes = [
    "000001049"
  ]
}
```

or

```
{ name="route6"
  id = 3
  prefixes = [ "00000148", "0000473" ]
}
{ name="route7", id = 4
  prefixes = [ "000001049" ]
}
```

### ECA **eserv.config** example section

ECA adds a cut-down **ECA** section to **eserv.config** file. It is not a full list of all parameters that are available.

The **ECA** section contains initial values that you may need to amend to suit a specific installation. After amended, **ECA** runs with no further changes to Oracle. Where additional implementation changes need to be made to Oracle, refer to the *Background Processes* (on page 11) chapters for full descriptions of all process parameters.

### Editing the File

Open the configuration file on your system using a standard text editor. Do not use text editors, such as Microsoft Word, that attach control characters. These can be, for example, Microsoft DOS or Windows line termination characters (for example, ^M), which are not visible to the user, at the end of each row. This causes file errors when the application tries to read the configuration file.

Always keep a backup of your file before making any changes to it. This ensures you have a working copy to which you can return.

## Loading eserv.config Changes

If you change the configuration file, you must restart the appropriate parts of the service to enable the new options to take effect.





# Background Processes

## Overview

### Introduction

This chapter explains the processes that are started automatically by Service Logic Execution Environment (SLEE).

**Note:** This chapter also includes some plug-ins to background processes which do not run independently.

### In this chapter

---

This chapter contains the following topics.

edrControlAgent ..... 11

## edrControlAgent

### Purpose

edrControlAgent processes InitialDPs and sends them to an application across the SLEE. The edrControlAgent uses separate plugins to process different types of EDRs. It can only run one plugin per instance.

For more information about the SLEE, see *Service Logic Execution Environment Technical Guide*.

### Startup

This task is started by the SLEE, by the following line in the **SLEE.cfg** configuration file:

```
INTERFACE=edrControlAgent eca.sh /IN/service_packages/ECA/bin 1 EVENT
```

**Note:** The above are defaults and may vary.

### Configuration

To load and operate, the edrControlAgent reads the ECA section of the **eserv.config** file. The high-level structure of the ECA section is shown below.

```
ECA = [
{
    sleeInterfaceName = "uniqueID"
    inputDirectory = "dir"
    processingDirectory = "dir"
    badFileDirectory = "dir"
    fileNamePattern = "pattern"
    sleeServiceKey = key
    maxIdpsPerSecond = seconds
    statisticsEnabled = true|false
    tssf = seconds
    pluginLibrary = "lib"
```

```

    PluginSpecificConfig = {
        inapServiceKey = key
        commentChar = "str"
        separatorChar = "str"
        idpParameters = [
            "str"
            ...
        ]
        NumberRules = [
            { [remove=int][, replace=str] }
            ...
        ]
        successDirectory = "dir"
        failedDirectory = "dir"
    }
}
{
    additional_ECA_instances
}
...
]

```

## Parameters

Parameters of the `edrControlAgent` are listed below.

### `badFileDirectory`

**Syntax:** `badFileDirectory = "dir"`

**Description:** `edrControlAgent` moves EDR files that it cannot open for processing to this directory.

**Type:** String

**Optionality:** Required

**Default:** `/IN/service_packages/ECA/failed`

**Example:** `badFileDirectory = "/IN/service_packages/ECA/failed"`

### `fileNamePattern`

**Syntax:** `fileNamePattern = "pattern"`

**Description:** The pattern that the `edrControlAgent` uses to identify EDR files in the input directory.

**Type:** String

**Optionality:** Required

**Default:** `fileNamePattern = "*.edr"`

**Notes:** Use the parameter to:

- Ensure only EDR files are processed (while other files, such as README files, are left alone)
- Enable a specific `edrControlAgent` instance to select specific EDR files from a common input directory

**Example:** `fileNamePattern = "*.edr"`

### `inputDirectory`

**Syntax:** `inputDirectory = "dir"`

**Description:** The full path of the directory that holds EDRs to be processed by `edrControlAgent`.

**Type:** String

**Optionality:** Mandatory  
**Default:** /IN/service\_packages/ECA/input  
**Example:** inputDirectory = "/IN/service\_packages/ECA/input"

#### maxIdpsPerSecond

**Syntax:** maxIdpsPerSecond = *num*  
**Description:** The maximum number of IDPs that edrControlAgent sends across the SLEE within one second.  
**Type:** Integer  
**Optionality:** Optional, default used if not set  
**Allowed:** Positive integers.  
 If set to 0 (zero), no throttling is performed.  
**Default:** 0  
**Example:** maxIdpsPerSecond = 250

#### pluginLibrary

**Syntax:** pluginLibrary = "*lib*"  
**Description:** The ECA plug-in that processes EDRs of a specific type.  
**Type:** String  
**Optionality:** Optional, default used if not set  
**Default:** ECASimplePlugin.so  
**Notes:** You can only have one plug-in per instance. To run two plug-ins, you must have two edrControlAgents configured in the ECA section of **eserv.config**.  
**Example:** pluginLibrary = "ECASimplePlugin.so"

#### PluginSpecificConfig

**Syntax:** PluginSpecificConfig = { *config* }  
**Description:** Configuration for the library specified in pluginLibrary (on page 13).  
**Type:** Array  
**Optionality:** Required  
**Notes:** The detail of this array depends on the plug-in.  
**Example:**

```

PluginSpecificConfig = {
  inapServiceKey = 900
  commentChar = "#"
  separatorChar = "|"
  idpParameters = [
    "calledPartyNumber"
    "skip"
    "callingPartyNumber"
    "locationNumber"
    "tbcdExtension 1234"
    "asn1Extension 1234"
    "callDurationDeciseconds"
  ]
  NumberRules = [
    { prefix = "6449", min = 5, remove = 2,
      prepend = "0", resultNoa = 2 }
  ]
  successDirectory =

```

```

        "/IN/service_packages/ECA/success"
        failedDirectory =
        "/In/service_packages/ECA/failed"
    }

```

#### processingDirectory

**Syntax:** `processingDirectory = "dir"`

**Description:** Before processing the EDR files, `edrControlAgent` moves the files to the specified directory.

**Type:** String

**Optionality:** Required

**Default:** `/IN/service_packages/ECA/processing`

**Notes:** You can use this parameter to enable different instances of `edrControlAgent` to run on the same machine, while using the same input directory.

**Example:** `processingDirectory = "/IN/service_packages/ECA/processing"`

#### sleeInterfaceName

**Syntax:** `sleeInterfaceName = "name"`

**Description:** The unique identifier of this instance of the `edrControlAgent` interface in **SLEE.cfg**.

**Type:** Integer

**Optionality:** Required

**Default:** `edrControlAgent`

**Notes:** Must match the unique identifier of `edrControlAgent` in the **SLEE.cfg** file.  
For more information about **SLEE.cfg**, see *Service Logic Execution Environment Technical Guide*.

**Example:** `sleeInterfaceName = "edrControlAgent"`

#### sleeServiceKey

**Syntax:** `sleeServiceKey = skey`

**Description:** The service key to use in outgoing InitialDPs.

**Type:** Integer

**Optionality:** Required

**Default:** 900

**Notes:** Must match the SERVICEKEY entry for the `edrControlAgent` (`slee_acs` on install) in **SLEE.cfg**. For more information about **SLEE.cfg**, see *Service Logic Execution Environment Technical Guide*.  
Set to 900 at installation.

**Example:** `sleeServiceKey = 900`

#### statisticsEnabled

**Syntax:** `statisticsEnabled = true|false`

**Description:** Defines whether `edrControlAgent` logs statistics about its processing to the SMS statistics sub-system.

**Type:** Integer

**Optionality:** Optional, default used if not set.

**Allowed:** true, false

**Default:** true

**Notes:**

**Example:** `statisticsEnabled = false`

`tssf`

**Syntax:** `tssf = seconds`

**Description:** The number of seconds `edrControlAgent` waits for a response before abandoning the IDP and closing the dialog.

**Type:** Integer

**Optionality:** Optional, default used if not set.

**Allowed:**

**Default:** 30

**Notes:** If the plug-in requires it, `edrControlAgent` increments a statistic count when a message times out.

**Example:** `tssf = 10`

## edrSimplePlugin.so

The `PluginSpecificConfig` section of the ECA `eserv.config` configuration supports these parameters for `edrSimplePlugin.so`.

```
PluginSpecificConfig = {
    inapServiceKey = key
    commentChar = "str"
    separatorChar = "str"
    idpParameters = [
        "str"
        ...
    ]
    NumberRules = [
        { [prefix="str", ][min=int, ][max=int, ] remove=int[, replace=str][,
        prepend="str"][, resultNoa=int] }
        ...
    ]
    successDirectory = "dir"
    failedDirectory = "dir"
}
```

The parameters are described in detail below.

`commentChar`

**Syntax:** `commentChar = "char"`

**Description:** The character that signifies comments, which are not processed.

**Type:** String

**Optionality:** Optional, default will be used if not set.

**Allowed:** ASCII characters

**Default:** `"#"`

**Notes:**

**Example:** `commentChar = "#"`

`failedDirectory`

**Syntax:** `failedDirectory = "dir"`

**Description:** When an EDR fails parsing, `edrControlAgent` writes the EDR to the specified directory.

**Type:** String  
**Optionality:** Mandatory  
**Allowed:**  
**Default:** None  
**Notes:** edrControlAgent writes EDRs that are parsed successfully to the directory specified by the *successDirectory* (on page 17) parameter.  
**Example:** `failedDirectory = "/var/edr/failed"`

#### idpParameters

**Syntax:** `idpParameters = ["parameters"]`  
**Description:** The order of fields in the EDR.  
**Type:** Array of strings  
**Optionality:** Mandatory  
**Allowed:** For information about the fields you can use, see *idpParameter details* (on page 16). If fields other than those specified are used, edrControlAgent does not startup.  
**Default:** None  
**Notes:** The separator in the EDR file is specified by the *separatorChar* (on page 17) parameter.  
**Example:**

```
idpParameters = [
    "calledPartyNumber"
    "skip"
    "callingPartyNumber"
    "locationNumber"
    "tbcdExtension 1234"
    "callDurationSeconds"
]
```

This configuration correctly parses the following EDR:  
123456789|skip|987654321|123456|490154203237518|123

#### idpParameter details

You can specify the following strings for *idpParameters*:

String	Description
skip	The field in this position is irrelevant. Skip it.
callDurationSeconds	Call duration in seconds
callDurationDeciseconds	Call duration in deciseconds
tbcdExtension(<int extension type>)	An IDP extension with the given type, as an octet string. The octet string contains a coded up MAP TBCD-STRING.
calledPartyNumber	IDP.calledPartyNumber
callingPartyNumber	IDP.callingPartyNumber
callingPartysCategory	IDP.callingPartysCategory
locationNumber	IDP.locationNumber
additionalCallingPartyNumber	IDP.additionalCallingPartyNumber
redirectingPartyID	IDP.redirectingPartyID
iMSI	IDP.iMSI
mscAddress	IDP.mscAddress
calledPartyBCDNumber	IDP.calledPartyBCDNumber

**inapServiceKey**

<b>Syntax:</b>	<code>inapServiceKey = <i>skey</i></code>
<b>Description:</b>	The service key for all IDPs generated by this plug-in.
<b>Type:</b>	Integer
<b>Optionality:</b>	Mandatory
<b>Allowed:</b>	Valid IDPs as specified in the relevant standard.
<b>Default:</b>	None
<b>Notes:</b>	To run some EDRs on a different service key, you must run more than one instance of <code>edrControlAgent</code> and split the EDRs for each process.
<b>Example:</b>	<code>inapServiceKey = 111</code>

**separatorChar**

<b>Syntax:</b>	<code>separatorChar = "<i>char</i>"</code>
<b>Description:</b>	The character that separates the fields in the EDR.
<b>Type:</b>	String
<b>Optionality:</b>	Optional, default will be used if not set.
<b>Allowed:</b>	ASCII
<b>Default:</b>	
<b>Notes:</b>	
<b>Example:</b>	<code>separatorChar = " "</code>

**successDirectory**

<b>Syntax:</b>	<code>successDirectory = "<i>dir</i>"</code>
<b>Description:</b>	<code>edrControlAgent</code> moves EDRs that are processed successfully to the specified directory.
<b>Type:</b>	String
<b>Optionality:</b>	Mandatory
<b>Allowed:</b>	
<b>Default:</b>	None
<b>Notes:</b>	
<b>Example:</b>	<code>successDirectory = "/var/edr/success"</code>

**NumberRules**

The `NumberRules` subsection of the ECA `eserv.config` configuration supports these parameters. If the `NumberRules` section is not present, all numbers are assumed to be in international format. This section applies to denormalization only.

```
NumberRules = [
    { [prefix="str", ][min=int, ][max=int, ][remove=int[, replace=str][,
      prepend="str"][, resultNoa=int] }
    ...
]
```

The parameters are described in detail below.

**max**

<b>Syntax:</b>	<code>max = <i>maxNoLength</i></code>
<b>Description:</b>	The maximum number of digits that a number can contain. If the number contains

digits less than or equal to this value, the max part of the number rule is met.

Type:

Integer

Optionality:

Optional, (if not set, default it used).

Allowed:

Default:

999

Notes:

This parameter is an element of the `NumberRules` parameter array.

Example:

`max = 9`

`min`

Syntax:

`min = minNoLength`

Description:

The minimum number of digits that a number can contain. If the number contains digits that is greater than or equal to this value, the min part of the number rule is met.

Type:

Integer

Optionality:

Optional, if not set default is used.

Allowed:

$0 \leq minNoLength$

Default:

0

Notes:

- The `remove` parameter affects the `min` parameter. If `remove` is equal to `noOfRemovedDigits` and `noOfRemovedDigits` is greater than 0, then `minNoLength` must be set so `minNoLength` is greater than or equal to `noOfRemovedDigits`.
- This parameter is an element of the `NumberRules` parameter array.

Example:

`min = 5`

`prefix`

Syntax:

`prefix = "prefix"`

Description:

Contains a digit or digits. Rule attempts to match the first digit or digits of a number with this value. If the digit or digits match, the prefix part of the number rule is met.

Type:

String

Optionality:

Optional

Allowed:

One or more decimal digits.

Default:

Notes:

This parameter is an element of the `NumberRules` parameter array.

Example:

`prefix = "25"`

`prepend`

Syntax:

`prepend = "firstDigits"`

Description:

Digits added to the beginning of a number.

Type:

String

Optionality:

Optional

Allowed:

Can be:

- Any combination of decimal digits
- A null string ("" )

Default:

Notes:

- If the `remove` and `prepend` parameters are both used in the same number rule, `firstDigits` is added to the beginning of the number



after the number has been modified by the `remove` parameter.

- This parameter is an element of the `NumberRules` parameter array.

**Example:** `prepend = "0"`

`remove`

**Syntax:** `remove = noOfRemovedDigits`

**Description:** The number of digits stripped from the beginning of a number.

**Type:** Integer

**Optionality:** Mandatory

**Allowed:**

**Default:**

- Notes:**
- The `remove` parameter affects the `min` parameter. If `min` is equal to `minNoLength` and if `noOfRemovedDigits` is greater than 0, then `minNoLength` must be set to `minNoLength` is greater than or equal to `noOfRemovedDigits`. See *min* (on page 18).
  - The `remove` parameter is an element of the `NumberRules` parameter array.

**Example:** `remove = 2`

`replace`

**Syntax:** `replace = "str"`

**Description:** Characters that the number rule substitutes for a number.

**Type:** String

**Optionality:** Optional

**Allowed:**

**Default:**

**Notes:** This parameter is an element of the `NumberRules` parameter array.

**Example:** `replace = "111"`

`resultNoa`

**Syntax:** `resultNoa = NOA`

**Description:** The nature of address (NOA) sent to the network after denormalization.

**Type:** Integer

**Optionality:** Optional

**Allowed:**

**Default:**

- Notes:**
- A value for `NOA` is typically specified in denormalization rules.
  - This parameter is an element of the `NumberRules` parameter array.

**Example:** `resultNoa = 4`

## Example number denormalisation

### Example 1

```
{ prefix="027", min=9, remove=1, resultNoa=3 }
```

This denormalization rule:

- Matches numbers that:
  - Start with the digits 027
  - Have a minimum of 9 digits
- Removes the first digit.
- Sets NOA = 3.

For example, the outgoing message 027nnnnnnnn is changed to 27nnnnnnnn.

### Example 2

```
{ prefix="00", min=5, remove=2, prepend="", resultNoa=4 }
```

This denormalization rule:

- Matches numbers that:
  - Start with the digits 00
  - Contain a minimum of 5 digits
- Removes the first two digits.
- Sets NOA = 4.

For example, the outgoing message 00nnnnnnnnnnnn is changed to nnnnnnnnnnn.

## Example configuration

An example of the ECA section of a **eserv.config** file is listed below. Comments have been removed.

```
ECA = [
{
    sleeInterfaceName = "EDRControlAgent"
    inputDirectory = "/var/edr/input"
    processingDirectory = "/var/edr/processing"
    badFileDirectory = "/var/edr/unprocessable"
    fileNamePattern = "*.cdr"
    sleeServiceKey = 300
    maxIdpsPerSecond = 250
    statisticsEnabled = true
    tssf = 10
    pluginLibrary = "ECASimplePlugin.so"
    PluginSpecificConfig = {
        inapServiceKey = 111
        commentChar = "#"
        separatorChar = "|"
        idpParameters = [
            "calledPartyNumber"
            "skip"
            "callingPartyNumber"
            "locationNumber"
            "tbcdExtension 1234"
            "callDurationSeconds"
        ]
        NumberRules = [
            { prefix = "6449", min = 5, remove = 2, prepend = "0", resultNoa = 2
            }
        ]
        successDirectory = "/var/edr/success"
        failedDirectory = "/var/edr/failed"
    }
}
]
```

## Failure

If `edrControlAgent` stops while processing an EDR file, it writes the following information to `ecaProgress.txt`:

- The names of all the files being processed
- The name of the EDR file currently being processed
- The number of IDPs sent for the current file
- If the plug-in requires it, the file names and EDR number for all the 'calls' in progress

When it restarts, `edrControlAgent` uses `ecaProgress.txt` to identify where to start again.

If `edrControlAgent` stops without writing to the `ecaProgress.txt` file, it uses the plug-in to move any files out of the progress directory to the success or failed directory.

## Input

`edrControlAgent` takes EDRs from the input directory configured by the `inputDirectory` (on page 12) parameter in `eserv.config`.

## Output

`edrControlAgent` moves processed EDRs to the success or failed directory depending on the result of the EDR processing. These directory locations are configurable in `eserv.config`.

`edrControlAgent` also writes error messages to the system messages file, and writes additional output to `/IN/service_packages/ECA/tmp/edrControlAgent.log`

**Note:** The above are defaults and may vary.



# Troubleshooting

## Overview

### Introduction

This chapter explains the important processes on each of the server components in NCC, and describes a number of example troubleshooting methods that can help aid the troubleshooting process before you raise a support ticket.

### In this chapter

---

This chapter contains the following topics.

Possible Problems..... 23

## Possible Problems

### Introduction

This topic lists common problems and actions you can take to investigate or solve them. This list enables you to check for alarms based on the overall behavior you are experiencing.

### Flooding

edrControlAgent may produce more IDPs than the processing applications can cope with. In this circumstance, edrControlAgent waits until the next second to re-send the IDP.

You can throttle the number of IDPs edrControlAgent sends by specifying one of the following:

- A lower *maxIdpsPerSecond* (on page 13)
- A lower MAX\_DIALOGS for the edrControlAgent INTERFACE entry in **SLEE.cfg**.



# About Installation and Removal

## Overview

### Introduction

This chapter provides information about the installed components for the NCC application described in this guide. It also lists the files installed by the application that you can check for, to ensure that the application installed successfully.

### In this Chapter

---

This chapter contains the following topics.

Installation and Removal Overview .....	25
Checking the Installation .....	25
Post-installation Configuration .....	26

## Installation and Removal Overview

### Introduction

For information about the following requirements and tasks, see *Installation Guide*:

- NCC system requirements
- Pre-installation tasks
- Installing and removing NCC packages

### ECA packages

An installation of Oracle Communications Network Charging and Control EDR Control Agent includes the following packages, on the:

- SMS:
  - ecaSms
- SLC:
  - ecaScp

## Checking the Installation

### Introduction

Refer to these checklists to ensure that ECA installed correctly.

## Checklist - SMS

Follow the steps in this checklist to ensure ECA installed correctly on an SMS machine.

Step	Action
1	Log in to SMS machine as root.
2	Check that the following directory structure exists, with subdirectories: <ul style="list-style-type: none"> <li>• <code>/IN/service_packages/ECA</code></li> </ul>
3	Check that directories contain subdirectories and that all are owned by: <code>smf_oper</code> user (group <code>esg</code> )

## Checklist - SLC

Follow the steps in this checklist to ensure that ACS installed correctly on an SLC machine.

Step	Action
1	Log in to SLC machine as root.
2	Check that the following directory structure exists, with subdirectories: <ul style="list-style-type: none"> <li>• <code>/IN/service_packages/ECA</code></li> </ul>
3	Check that the directory contains subdirectories and that all are owned by: <code>smf_oper</code> user (group <code>esg</code> )
4	Check that the processes listed in the process lists are running. For a list of the processes that should be running, see <i>Process list - SLC</i> (on page 26).

## Process list - SLC

If the application is running correctly, the following process should be running on each SLC:

- Started during SLEE startup:
  - `edrControlAgent`

# Post-installation Configuration

## Configuration process overview

This table describes the steps involved in configuring ECA for the first time.

Stage	Description
1	Uncomment (and if necessary update) the default SLEE configuration for the ECA in the <code>SLEE.cfg</code> file. For more information, see <i>Service Logic Execution Environment Technical Guide</i> .
2	The <code>eserv.config</code> file must be configured for ECA. The installation script adds an <code>ECA</code> section to <code>eserv.config</code> . Any required configuration should be updated. For more information, see <i>eserv.config Configuration</i> (on page 7).



# Glossary of Terms

## AC

Application Context. A parameter in a TCAP message which indicates what protocol is conveyed. May indicate, for example, MAP, CAMEL, or INAP. Also usually specifies the particular version of the conveyed protocol, for example, which CAMEL Phase.

## ACS

Advanced Control Services configuration platform.

## CAMEL

Customized Applications for Mobile network Enhanced Logic

This is a 3GPP (Third Generation Partnership Project) initiative to extend traditional IN services found in fixed networks into mobile networks. The architecture is similar to that of traditional IN, in that the control functions and switching functions are remote. Unlike the fixed IN environment, in mobile networks the subscriber may roam into another PLMN (Public Land Mobile Network), consequently the controlling function must interact with a switching function in a foreign network. CAMEL specifies the agreed information flows that may be passed between these networks.

## CAP

CAMEL Application Part

## DP

Detection Point

## GPRS

General Packet Radio Service - employed to connect mobile cellular users to PDN (Public Data Network- for example the Internet).

## HLR

The Home Location Register is a database within the HPLMN (Home Public Land Mobile Network). It provides routing information for MT calls and SMS. It is also responsible for the maintenance of user subscription information. This is distributed to the relevant VLR, or SGSN (Serving GPRS Support Node) through the attach process and mobility management procedures such as Location Area and Routing Area updates.

## HPLMN

Home PLMN

## IDP

INAP message: Initial DP (Initial Detection Point)

## IN

Intelligent Network

## **INAP**

Intelligent Network Application Part - a protocol offering real time communication between IN elements.

## **Initial DP**

Initial Detection Point - INAP Operation. This is the operation that is sent when the switch reaches a trigger detection point.

## **MAP**

Mobile Application Part - a protocol which enables real time communication between nodes in a mobile cellular network. A typical usage of the protocol would be for the transfer of location information from the VLR to the HLR.

## **MS**

Mobile Station

## **MT**

Mobile Terminated

## **NOA**

Nature Of Address - a classification to determine in what realm (Local, National or International) a given phone number resides, for the purposes of routing and billing.

## **PLMN**

Public Land Mobile Network

## **SGSN**

Serving GPRS Support Node

## **SIM**

Usually referred to as a SIM card, the Subscriber Identity Module is the user subscription to the mobile network. The SIM contains relevant information that enables access onto the subscribed operator's network.

## **SLC**

Service Logic Controller (formerly UAS).

## **SLEE**

Service Logic Execution Environment

## **SMS**

Depending on context, can be:

- Service Management System hardware platform
- Short Message Service
- Service Management System platform

- NCC Service Management System application

**SN**

Service Number

**TCAP**

Transaction Capabilities Application Part – layer in protocol stack, message protocol.

**VLR**

Visitor Location Register - contains all subscriber data required for call handling and mobility management for mobile subscribers currently located in the area controlled by the VLR.

**VWS**

Oracle Voucher and Wallet Server (formerly UBE).



# Index

## A

About Installation and Removal • 25  
About This Document • v  
AC • 27  
ACS • 27  
Audience • v

## B

Background Processes • 8, 11  
badFileDirectory • 12

## C

CAMEL • 27  
CAP • 27  
Checking the Installation • 25  
Checklist - SLC • 26  
Checklist - SMS • 26  
commentChar • 15  
Component descriptions • 2  
Component diagram • 2  
Configuration • 7, 11  
Configuration components • 7  
Configuration File Format • 8  
Configuration Overview • 7  
Configuration process overview • 26  
Copyright • ii

## D

Document Conventions • vi  
DP • 27

## E

ECA eserv.config example section • 8  
ECA packages • 25  
Editing the File • 8  
EDR processing • 3  
EDR processing diagram • 3  
edrControlAgent • 2, 11  
edrSimplePlugin.so • 2, 15  
eserv.config Configuration • 2, 7, 26  
Example configuration • 20  
Example number denormalisation • 19  
Example solution • 1

## F

failedDirectory • 15  
Failure • 21  
fileNamePattern • 12  
Flooding • 23

## G

GPRS • 27

## H

HLR • 27  
HPLMN • 27

## I

IDP • 27  
idpParameter details • 16  
idpParameters • 3, 16  
IN • 27  
INAP • 28  
inapServiceKey • 17  
Initial DP • 28  
Input • 21  
inputDirectory • 12, 21  
Installation and Removal Overview • 25  
Introduction • 4, 7, 23, 25  
Introduction to EDR Control Agent • 1

## L

Loading eserv.config Changes • 9

## M

MAP • 28  
max • 17  
maxIdpsPerSecond • 13, 23  
min • 18, 19  
MS • 28  
MT • 28

## N

NOA • 28  
NumberRules • 17

## O

Output • 21  
Overview • 1, 7, 11, 23, 25

## P

Parameters • 12  
PLMN • 28  
pluginLibrary • 13  
PluginSpecificConfig • 13  
Possible Problems • 23  
Post-installation Configuration • 26  
prefix • 18  
prepend • 18  
Prerequisites • v  
Process list - SLC • 26  
processingDirectory • 14  
Purpose • 1, 11

## R

Related Documents • v  
remove • 19  
replace • 19

Report example • 5  
Reports • 5  
resultNoa • 19

## **S**

Scope • v  
separatorChar • 16, 17  
SGSN • 28  
SIM • 28  
SLC • 28  
SLEE • 28  
sleeInterfaceName • 14  
sleeServiceKey • 14  
SMS • 28  
SN • 29  
Startup • 11  
Statistics • 4  
Statistics and Reports • 4  
statisticsEnabled • 14  
successDirectory • 16, 17  
Supported InitialDP operations • 4  
System Overview • 1

## **T**

TCAP • 29  
Troubleshooting • 23  
tssf • 5, 15  
Typographical Conventions • vi

## **U**

Unsupported InitialDP parameters • 4

## **V**

VLR • 29  
VWS • 29