

**Oracle® Communications  
Network Charging and Control**

Testing Utilities User's Guide

Release 6.0.1

**E85792-01**

April 2017

Copyright © 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

---

---

# Contents

<b>Preface</b> .....	vii
Audience .....	vii
Related Documents .....	vii
Conventions .....	vii
 <b>1 About the NCC Testing Utilities</b>	
<b>Overview of NCC Testing Utilities</b> .....	1-1
Overview of the slpit Utility .....	1-1
Overview of the mipt Utility .....	1-3
Overview of the smsc Test Tool .....	1-4
 <b>2 Testing Calls and Messages Using the slpit Utility</b>	
<b>About the slpit Utility</b> .....	2-1
<b>Running the slpit Utility</b> .....	2-1
Command Syntax .....	2-2
Command-Line Options .....	2-2
Output Options .....	2-4
Running slpit in a Separate SLEE .....	2-5
Exit Codes .....	2-5
<b>Managing Script File Processing</b> .....	2-5
Using Distributions .....	2-6
Using TCAP Primitives .....	2-7
Receiving Expected Operations .....	2-7
Managing Dialogs .....	2-8
Specifying a Particular Dialog .....	2-8
Ending a SLEE Dialog .....	2-8
Aborting a SLEE Dialog .....	2-9
Completing Calls .....	2-9
Cancelling slpit .....	2-9
Sending an Error .....	2-10
<b>Creating the slpit Script File</b> .....	2-10
Syntax .....	2-10
Commands .....	2-11
Call Definition Commands and Messages .....	2-12
The Call Sequence .....	2-12

About Expressions and Comparators .....	2-15
Call Messages.....	2-16
Send Message Operations.....	2-17
Receive Message Operations .....	2-41
Example Scripts .....	2-49
A Standard Call.....	2-49
A Call that Plays an Announcement.....	2-51

### 3 Testing IP Interactions with the mipt Utility

About the mipt Utility .....	3-1
Running the mipt Utility .....	3-1
Command Syntax.....	3-1
Command-Line Options .....	3-2
Logging Options .....	3-3
Creating the mipt Script File.....	3-4
Specifying the Test Sequence.....	3-4
Reserved keywords .....	3-5
Using mipt as an ASP or SMSC.....	3-5
Sending Multiple Messages.....	3-6
Rejecting Messages.....	3-6
Using Variables.....	3-7
Controlling the Message Flow.....	3-7
Providing an Alternate Flow .....	3-7
Controlling the Processing Sequence.....	3-7
Controlling Loops .....	3-8
Using the RADIUS Protocol .....	3-10
Using mipt as a Diameter Client or Server.....	3-11
Connecting as a Diameter Client .....	3-11
Accepting a Connection as a Diameter Server.....	3-12
Sending a Diameter Error Message.....	3-12

### 4 Testing Messaging with the SMSC Test Tool

About the smsc Test Tool .....	4-1
Running the smsc Test Tool.....	4-1
Configuring SLEE for smsc .....	4-2
Configuring the smsc Test Tool .....	4-2
Configuring General Parameters .....	4-3
Configuring for CAP3 GPRS .....	4-3
Configuring for MAP .....	4-5
Example MAP Configuration.....	4-9
Configuring for MAP as HLR .....	4-9
Example MAP as HLR Configuration .....	4-17
SMSC Sequence for MAP as HLR.....	4-17
Map SendUSSDNotification.....	4-18
XMS tcpInterfaceName .....	4-19
Configuring for IS-41 .....	4-19
Configuring for IS-41 as HLR .....	4-25

SMSC Sequence for MAP as IS-41 .....	4-29
Specifying AccessDeniedReason Values .....	4-30
tcapInterfaceServiceKey for XMS .....	4-30
SMS CauseCode Mapping .....	4-31

## **A About the SS7 Protocol Suite**

The INAP Protocol .....	A-1
The CAP Protocol .....	A-2
The MAP Protocol .....	A-2
The IS-41 Protocol .....	A-2
The TCAP Protocol.....	A-2
The SCCP Protocol.....	A-2
The M3UA Protocol .....	A-3
The SUA Protocol .....	A-3
The SCTP Protocol .....	A-3
The Internet Protocol .....	A-3

## **B Supported Protocol Fields for mipt**

Supported Fields for the Diameter Protocol .....	B-1
Base AVP Diameter Fields .....	B-11
Vendor-Specific Diameter Fields .....	B-14
Supported Fields for the EMI Protocol .....	B-28
Supported Fields of the M3UA Protocol.....	B-30
Supported Fields of the RADIUS Protocol .....	B-31
Supported Vendor-Specific Fields of the RADIUS Protocol.....	B-36
Supported Fields of the SMPP Protocol .....	B-38
Supported SMPP TLV Fields.....	B-40
Supported Fields of the SUA Protocol .....	B-40

## **Glossary**



---

---

# Preface

This guide describes how to use the Oracle Communications Network Charging and Control (NCC) testing utilities.

## Audience

This document is intended for NCC network operators, system administrators, and system integrators who do functional testing of applications, load testing, and external interface testing.

## Related Documents

For related information, see the following documents in the NCC documentation set:

- *Network Charging and Control System Administrator's Guide*
- *Network Charging and Control Configuration User's Guide*
- *Network Charging and Control Service Logic Execution Environment Technical Guide*

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.





---

## About the NCC Testing Utilities

This chapter provides an overview of the Oracle Communications Network Charging and Control (NCC) testing utilities.

### Overview of NCC Testing Utilities

NCC communicates internally using a language known as G8-Intelligent Network Application Protocol (G8-INAP), which is a subset of Capability Set 1 (CS1) INAP but also includes bits of CS2 INAP and CAMEL Application Part (CAP). Using this common language allows NCC components to perform functions without having to translate the low-level languages used by the telephony network.

NCC interfaces communicate with the physical network in whichever protocol the network demands. The interfaces translate the messages from the physical network into the G8-INAP messages. The passing of messages between NCC and the interfaces takes place in the NCC Service Logic Execution Environment (SLEE), where many interfaces can communicate concurrently. Because they are not tied to low-level network languages, NCC components can be portable and plug into any network as long as an effective interface exists.

The NCC testing utilities include:

- The Service Logic Program Instance Tester (**slpit**) utility  
The **slpit** utility allows you to test call processing by NCC applications without the need for a physical telephony network.
- The Messaging over Internet Protocol Tester (**mipt**) utility  
The **mipt** utility allows you to test the sending and receiving of messages over internet-based protocols.
- The short message service center (**smsc**) test tool  
The **smsc** test tool emulates various parts of the short message service (SMS) environment to enable testing of SMS messaging.

The distinction between the **smsc** test tool and the two utilities is that you initiate **smsc** through configuration parameters as part of NCC startup, whereas you run the two utilities independently from the command line.

### Overview of the **slpit** Utility

The **slpit** utility is a tool that you can use to do functional testing of NCC applications, high load testing, and external interface testing without concern for the protocol of a given network. From the perspective of the test application, the **slpit** utility emulates a real interface that converts the network messages to and from G8-INAP. It

communicates with the application by way of the SLEE, just like a regular interface.

---

**Note:** In this context, *application* or *NCC application* refers to the SLEE process to which the **slpit** utility is communicating. Usually, this process is either **slee\_acs**, which is the main ACS process, or **xmsTrigger**, which is the main XMS process. But it can also be **m3uaIf**, which is also a SLEE process. The **m3uaIf** process is further described in this section.

---

The **slpit** utility has the following characteristics:

- It allows you to effectively test Intelligent Network (IN) applications without requiring a physical telephony network or a low-level network-specific test tool.
- You can use it to do functional testing of NCC applications without concern for a particular network protocol. As long as the application provides the correct functionality in G8-INAP, it will perform the same way on a particular network with the appropriate interface.
- It acts as a normal TCAP interface to trigger IN platform service logic, emulating a service switching point (SSP) and specialized resource function (SRF) interactions.


The **slpit** utility supports the following IN protocols: CAP, MAP, SCCP, CAP3 GPRS and IS-41.

- It uses a script file in which you define the INAP operations that are sent and received for one or more types of calls. A single instance of **slpit** can run many call instances and many calls can be in-progress at once. The script initiates a call and you can specify different distributions and throughput rates. Multiple protocols are supported.
- You can use it to do moderate load testing and external interface testing, in addition to using it for functional testing of applications.
- You can run it in the same SLEE as the application being tested or in a separate SLEE using appropriate TCAP interfaces.

On a production NCC system, the **slee\_acs** process and the **xmsTrigger** process communicate with a process called **m3uaIf**, using a TCAP-like protocol. The **m3uaIf** process is also a SLEE process. The **m3uaIf** process turns the TCAP-like events into messages that are sent over the IP network in a protocol stack that consists of one of the following:


- MAP over TCAP over SCCP over M3UA over SCTP over IP
- CAP over TCAP over SCCP over M3UA over SCTP over IP

[Figure 1–1](#) shows **slpit** running in the same SLEE as the application being tested.

**Figure 1–1 *slpit Testing Application in the Same SLEE***

You can also use **slpit** to generate INAP, MAP, CAP3 GPRS or IS-41 over a specific set of protocols if you run it on a different machine than the one where the application is being tested.

Figure 1–2 shows **slpit** running in a SLEE on a separate machine from the one where the application is being tested.

**Figure 1–2 *slpit Testing Application in a Separate SLEE***

See "Testing Calls and Messages Using the **slpit** Utility" for more information.

## Overview of the **mipit** Utility

The **mipit** utility is a test tool that allows you to send and receive messages. Depending on the protocol, the **mipit** utility can act as:

- An application service provider (ASP) or a Short Message Service Center (SMSC) when the protocol is one of the following:

- Short Message Peer to Peer (SMPP)
- External Machine Interface (EMI)
- An ASP when the protocol is Media Transfer Protocol (MTP) level 3 User Adaptation layer (M3UA)
- A Diameter agent or a Diameter server for the Diameter protocol

You can run multiple instances of **mipt**, acting as ASPs or SMSCs, that communicate with each other on the same machine.

You can use the following protocols with **mipt**:

- Remote Authentication Dial-In User Service (RADIUS)  
RADIUS is a network protocol that is the predecessor to the Diameter protocol and, like Diameter, it is used for authentication, authorization, and accounting.
- Diameter  
Diameter is an authentication, authorization, and accounting protocol. You can also use the Diameter protocol for policy control and resource control.
- EMI  
EMI connects mobile telephones to SMSCs.
- M3UA  
The M3UA protocol enables the SS7 protocol User Part SCCP, as well as others, to run over the internet protocol instead of telephony equipment. It is generally transmitted by using the services of Stream Control Transmission Protocol (SCTP).
- SMPP  
SMPP transfers short message data between message centers and routing and messaging facilities. It is commonly used to transfer short messages and it allows service providers to submit messages in bulk.
- SUA  
The SUA protocol facilitates the transfer of SCCP user messages, such as TCAP, between the signalling gateway and the ASP.

See "[Supported Protocol Fields for mipt](#)" for a list of supported fields for each of the protocols that you can use.

To test messages using these protocols, you create a text file, called the *script file*, that contains the operations or messages that you want to test. The **mipt** utility accepts the script file as input and processes the operations that you have defined.

See "[Testing IP Interactions with the mipt Utility](#)" for more information.

## Overview of the smsc Test Tool

The **smsc** test tool is a multipurpose test tool that runs as a Service Logic Execution Environment (SLEE) interface.


The SMSC test tool emulates the following parts of a short message service (SMS) messaging environment:

- Visitor Mobile Switching Center (VMSC)  
A mobile switching center (MSC) is a telephone exchange in a GSM mobile network. The VMSC is the MSC that the destination phone is attached to, which could be distant from its home network, and, hence, is a visitor.

- Short Message Service Center (SMSC)
- Home Location Register (HLR)

Figure 1–3 illustrates how NCC applications connect to SMSC, HLR, or VMSC in a production environment.

**Figure 1–3 NCC Connecting to SMSC, HLR, or VMSC in a Production Environment**



The SMSC attaches to the SLEE as a Transaction Capabilities Application Part (TCAP) interface. The simulated SMSC handles both Mobile Application Part (MAP) and IS-41 (also known as ANSI-41) incoming short message requests. The **smc** test tool can simulate an SMSC, a Home Location Register (HLR), and a messaging service center (MSC) at MAP levels 1 through 3. It can also perform one CAP 3 GPRS operation, ActivitytestGPRS.


The **smc** test tool can handle the following operations for MAP and IS-41:

- MAP
  - FORWARD-SHORT\_MESSAGE
  - MT-FORWARD-SM
  - SEND-ROUTING-INFO-FOR-SM (HLR operation)
  - SEND-ROUTING-INFORMATION (HLR operation)
  - PROCESS-UNSTRUCTURED-SS-REQUEST
  - UNSTRUCTURED-SS-NOTIFY
- IS-41
  - SmsDeliveryPointToPoint (SMDPP)
  - SMSRequest (HLR operation)

- SMSNotification

Figure 1–4 illustrates how the **smsc** test tool replaces SMSC, HLR, or VMSC in a testing environment. The diagram illustrates the **smsc** test tool running on the same SLC (SLC1) that you are testing on, and running on a remote SLC (SLC2). The latter case is necessary to test the interaction between the application and the SIGTRAN interface.

**Figure 1–4 The smsc Test Tool Environment**



See "[Testing Messaging with the SMSC Test Tool](#)" for more information.

---

## Testing Calls and Messages Using the slpit Utility

This chapter describes how to use the Oracle Communications Network Charging and Control (NCC) **slpit** utility.

### About the slpit Utility

The **slpit** utility sends and receives Intelligent Network Application Part (INAP) operations and acts as an interface to the Transaction Capabilities Application Part (TCAP) protocol.

[Appendix A](#) gives a brief overview of the Signalling System 7 (SS7) protocol suite, of which INAP and TCAP are a part.

The **slpit** utility processes operations from an input text file rather than a real network. The input text file is called the *script file* and it is a file that you create. In the script file, you add commands and send and receive operations that define the call sequences that you want to test. See ["Creating the slpit Script File"](#) for more information.

The utility parses the responses from the test application and compares them to the responses that the script file expects.

There are two ways to run the **slpit** utility. In the first way, it replaces the **m3uaIf** process so that **slpit** communicates with **slee\_acs** and **xmsTrigger** but does not send anything over the IP network. This allows you to test the higher layers of a protocol but does not include any processing that would normally happen inside **m3uaIf**.

The second way to run the **slpit** utility allows you to test certain functions that happen in the **m3uaIf** process. To run the utility this way, you must configure two machines. For example, if you configure machines SLC1 and SLC2, you configure SLC1 exactly like a production SLC, with **slee\_acs** and **xmsTrigger** talking to **m3uaIf**. You configure SLC2 with only **m3uaIf** and the **slpit** utility on it. See ["Running slpit in a Separate SLEE"](#) for information about running the **slpit** utility in this configuration.

See ["About the NCC Testing Utilities"](#) for an overview of the **slpit** utility.

### Running the slpit Utility

The **slpit** utility is located in the following directory:

```
/IN/service_packages/TEST_TOOLS/bin
```

The basic command for running the **slpit** utility specifies a service and the name of the script input file. Additional command line options allow you to request validation of

the script file, define a global variable, specify the debug output, specify output options, and perform various other actions.

## Command Syntax

To run the **slpit** utility, use one of the following commands:

```
slpit -k [<option>...] [<script>]
slpit -V
slpit -h
```

The only command-line option that is typically required to run **slpit** is **-k**, which allows you to specify a service key other than the arbitrary default of 101. The following example shows the simplest command to run **slpit** with a script file:

```
slpit -k 1 <script file>
```

You can alternatively provide the script on the command line rather than in a file by using the following syntax where **<script>** is your script code:

```
slpit -k 1 < <script>
```

When you are trying to correct syntax errors in a script, the **-c** option is useful because it causes **slpit** to exit immediately after parsing, without running any calls:

```
slpit -c <script file>
```

## Command-Line Options

The **slpit** utility takes the following command-line options:

### **-A**

Constructs ANSI SCCP addresses rather than ITU addresses, which is the default.

### **-a**

Act as an application instead of the default interface. For more information, see ["Running slpit in a Separate SLEE"](#).

### **-c**

Validate the script file and exit.

### **-C <CSV\_file>**

Writes the following values to the specified comma-separated values (CSV) file every ten seconds: the time, calls per second (CPS), and outstanding call count.

### **-D <name>=<value>**

Predefines a global variable with the specified name and value, where **<name>** is the name of the variable and **<value>** can be an integer or a double quoted string. Defining a global variable could be useful for making a change to the script easier in the future. For example, you could define the destination phone number and then refer to it in the call definition using the variable. Then, in the future, when you want to define a new call with a different number, you would only need to change the number in one place.

### **-d <level>**

Sets the level of debug output. Valid levels are 0 to 5, with 0 indicating no output and 5 indicating the maximum output.



**-g**

Makes the utility more tolerant of errors, causing it to continue, if possible, rather than abort.

**-h**

Prints version and build information, like the **-V** option, plus a summary of the usage information.

**-i <interval>**

Report call summary information at the interval specified, which is a number of seconds.

**-l <name>**

Adds the value of <name> as a suffix to the interface name. This option is required if you run more than one instance of **slpit** simultaneously in the same SLEE.

**-k <key>**

Initiates calls with the specified service key value rather than 101, which is the default. The service key values are defined in the `/IN/service_packages/SLEE/etc/SLEE.cfg` file.

**-M <interval>**

Used with the **-m** option to write average timing information per primitive to the CSV file at the interval specified by <interval>. If the specified interval is 0, the average timing information will be written when the script completes. This parameter works only if the **slpit** script expects a response because the average durations cannot be calculated otherwise.

**-m <directory>**

Enables logging of timestamps per TCAP primitive for messages sent and received. The utility writes the information by call type to a comma-separated values (CSV) file in the specified directory.

**-N**

Instructs **slpit** not to add itself as an interface to the SLEE as the SLEE has added it already.

**-n**

Makes **slpit** ignore any received TCAP\_CANCEL messages.

**-O <flags>**

Enables the specified output flags. See ["Output Options"](#) for more information.

**-o <level>**

Sets the level of normal output. Valid levels are 0 to 5, with 0 indicating no output and 5 indicating the maximum level. The default is 3, which produces a reasonable amount of output that is not excessive.

**-p <protocol>**

Sets the preferred TCAP protocol to use when there is a conflict between the INAP/CAP and MAP tag values, as there is some overlap. Valid values are `map`, `is41`, and `inap`. The default is `inap`.

**-R**

Recreates the main dialog, if it no longer exists, using the last received originating reference as a correlation ID. This is required for the CAP3 GPRS message sequence. This option does not work if the **-a** option is also submitted.

**-T**

Enables the use of the SLEE Timer interface for delays between sending new requests, or between responses to inbound requests. Without this option, delays are handled by polling. Use of this option is not recommended. The Timer interface is not ideal for this purpose.

**-v**

Enables verbose output, setting the output level to the maximum. This is equivalent to setting the **-o** option to 5.

**-vv or -v -v**

Sets the debug output level to the maximum.

**-V**

Prints version and build information and then exits.

**Output Options**

In addition to the overall output level that is controlled by the **-o** option, you can enable the following more specific output features with the **-O** option. Most of these options are enabled automatically at various numeric output levels.

**calldfntrace**

Displays a brief summary of the call definition at each step in the call execution, including an indication of the current step. Automatically enabled at overall output level 4.

**callrate**

Displays the average call rate achieved before the **slpit** utility terminates. It calculates the call rate by dividing the total run time by the number of calls started.

**callsummary**

Prints a table summarizing the number of calls run, the number of successful calls, and the number of partially and totally failed calls. Call types that have at least one aborted call are marked with four asterisks (\*\*\*\*); call types with failed calls are marked with a single asterisk (\*).

**fullcallsummary**

Prints a more detailed call summary table than the one produced by the **callsummary** option. The information is the same as produced by the **callsummary** option, but the format of the table produced by **callsummary** is more concise.

**triptiming**

Records and displays round-trip message times for each call.

**sleecheck**

Checks for changes in the count of free resource objects in the SLEE at the end of the run. If there are any changes, displays a table of the free counts. The resources can be calls, dialogs, events, and application instances. The rows for resource types that showed a positive delta are marked with a single asterisk (\*); those with a negative delta, which indicates a potential memory leak, are marked with four asterisks (\*\*\*\*). A positive delta in free resource counts indicates that running one or more calls caused resources to be freed. This is not uncommon with Advanced Control Services (ACS), which is prompted to free a SLEE management event when the first call event arrives.

**parsedebug**

Enables the extremely verbose debug output for the GNU Bison parser. This option is not automatically enabled at any output level because it is useful primarily when debugging the parser.

## Running slpit in a Separate SLEE

When running the **slpit** utility in a separate SLEE, you must specify the **-a** and **-k** command-line options. The **-k** option must specify the SLEE service key that is assigned to the **m3uaIf** process in the **/IN/service\_packages/SLEE/etc/SLEE.cfg** file on the machine where the **m3uaIf** process is running.

## Exit Codes

[Table 2–1](#) describes the exit codes that the **slpit** utility uses to indicate whether the run was successful. The **slpit** utility writes the exit code to **stdout** (standard output), which you can redirect to a file if you wish.

```
slpit -k [<option>...] [<script>] > <outfile>
```

**Table 2–1** *slpit Exit Codes*

Exit Code	Description
0	Execution completed successfully
1	General or usage error, which usually indicates that the command-line options were not valid.
2	Script parsing error. Either <b>slpit</b> could not read the script file or it encountered a syntax error in the script. The utility displays diagnostics on <b>stderr</b> (standard error output).
4	The initial connection to the SLEE failed, most likely because no SLEE is running.
5	A SLEE entity that <b>slpit</b> required could not be contacted. This can occur when <b>slpit</b> is directed to use the Timer interface for running timers but the interface could not be found.
6	Call creation failed. From most likely to least likely, the possible reasons include: the service key for the call being created is not configured; a resource for a SLEE dialog or for call instances has been exhausted; the SLEE for the service configured on the service key never started or has been stopped.
10	At least one call instance failed. There were no errors that prevented <b>slpit</b> from running to completion, but at least one call instance ended in the FAILED state.
11	At least one call instance aborted. There were no errors that prevented <b>slpit</b> from running to completion, but at least one call instance ended in the ABORTED state.

## Managing Script File Processing

The script file is an input file in which you define the call instances that you want the **slpit** utility to process. Call instances are defined with a set of commands and INAP operations that you specify in sets of send and receive messages. The following example shows the beginning of a call instance definition:

```
define call assisting_ip_pa {
    SERVICE_NUMBER ?= "555801"
```

```
send {
    initialdp
    calledpartynumber SERVICE_NUMBER
    callingpartynumber "40002000"
    callingpartyscategory 10
    locationnumber "40002000"
    eventtypebcs analyzedinformation
}

receive {
    establishtemporaryconnection
    address "1234"
}
```

You start call processing by including a `startcall` command; for example:

```
startcall assisting_ip_pa using once
```

The **slpit** utility can reference the call types that you define in the script file only after the script file has been parsed. Starting a call creates a call distribution but the distribution does not start creating new call instances until script processing completes.

When you run the **slpit** utility, it processes all distributions and calls in the script file before stopping.

In general, each call that **slpit** executes produces one call instance and one or two dialogs in the SLEE. The first dialog is called the *main* dialog. The second dialog, which will exist only for parts of some calls, is referred to as the *assisting* dialog.

The first message sent for a call must be an `InitialDP` or an appropriate `TC_BEGIN` message. Alternatively, the first action in a call can be a receive message with a `cs1InitiateCallAttempt` or a `cap4InitiateCallAttempt` operation.

---

---

**Note:** Sending an `AssistRequestInstructions` message creates a second dialog on the same call instance to simulate the dialog between the intelligent peripheral and the service control point (SCP).

When **slpit** runs in the same SLEE as the application, the correlation ID for each dialog is not required to match. Normally, the TCAP interface would resolve the correlation ID to create the second dialog on the correct call instance.

---

---

---

---

**Note:** Receiving a `DisconnectForwardConnection` operation is not a special case. The shutdown of the assisting dialog must be explicitly stated.

---

---

The **slpit** utility does little validation to ensure valid call flow. It primarily ensures that the dialog is handled correctly. For example, you do not get a warning if you forget to send an `ApplyChargingReport` message at the end of a monitored call, but you do get a warning if you do not explicitly terminate a dialog.

## Using Distributions

The **slpit** utility creates a distribution with a list of call types and other parameters that control the launching of calls, which is known as the call rate, and the terminating

condition of the distribution, which is generally the number of calls launched. A distribution processes the call types in a round-robin fashion until the completion condition is met. The **slpit** utility allows you to create the following types of distributions:

- A uniform distribution has an interval and a total call count. The interval specifies the number of seconds that are to elapse before launching each call until the total number of calls is reached. The practical minimum interval is greater than a microsecond but less than a millisecond. The following `startcall` line, for example, would run the call every 0.5 seconds for a total of 10 times:

```
startcall using uniform 0.5 10
```

- A Poisson distribution has a lambda value and a total call count. The lambda value represents the average interval between calls rather than the exact interval.
- The once distribution launches one of each specified call type immediately.

A once distribution will run through the contents of the given call type once and report a result of SUCCESS, FAILED or ABORT.

The type of distribution is determined by the type of testing that you are performing. You specify the distribution type in the script file using the `startcall` command, for example:

```
startcall <id> using <distribution>
```

So for a script in which you wanted to run only one call that was started with `define call 982 {`, you would have to start the call with a line like the following:

```
startcall 982 using once
```

## Using TCAP Primitives

All TCAP messages are primitives although some primitives are not messages. That is, some primitives are transferred only inside the local machine. A TCAP primitive contains zero or more TCAP components and can be one of the types described in [Table 2-2](#).

**Table 2-2** *Types of TCAP Primitives*

Primitive Type	Description
Unidirectional	A single standalone instruction. It is both the start and end of a dialog.
Begin	Begins a dialog with other primitives coming after it.
Continue	A subsequent primitive sent on an existing dialog with other primitives coming after it.
End	The last primitive, which closes its dialog.
Abort	Closes the dialog, possibly due to an error.
Cancel	Closes the dialog when the invoke timer expires without receiving a response. This is an example of a primitive that is not a message.

## Receiving Expected Operations

Each received message corresponds to a single TCAP primitive and can contain one or more INAP operations.

The received message must contain the expected INAP operations in the order specified in the receive message section of the call definition. See ["Call Definition Commands and Messages"](#) for more information about defining calls.

---

**Note:** Operations can come in one primitive but also can sometimes come in separate primitives, depending on the application or the service.

---

If the received operation types do not match the expected operation types, the **slpit** utility aborts the call. If the parameters received for each operation do not match the expected parameters, **slpit** reports the result of the call as `FAILED` but continues to process the remaining operations in the call definition. See ["About Expressions and Comparators"](#) for more information about parameter values.

Receive operations can time out, which prevents **slpit** from waiting for call completion when the call has been lost. The global default for timeout is 15 seconds.

When a timeout occurs, you can execute a sequence of messages to finish the call. The default action is to abort the call, which closes any open dialogs. Aborting the call is not likely to be the most desirable behavior, however, because it does not cause a TCAP ABORT message to be sent to the application when it is running in the same SLEE. Therefore, if you expect a timeout, you should override the default with a more appropriate action.

## Managing Dialogs

The send message includes options that allow you to specify a particular dialog on which to send and also to end a SLEE dialog. You can also use the abort primitive to abort a dialog and use other messages to send an error to ACS.

### Specifying a Particular Dialog

To send operations specifically on either the main or assisting dialog, specify the dialog in the send primitive. For example, the following send primitive sends the operations on the assisting dialog:

```
send assisting {  
    <operations>  
}
```

To send on the main dialog, specify `main` instead of `assisting`. If you do not specify a dialog, the `main` dialog is assumed.

### Ending a SLEE Dialog

The easiest way to end a SLEE dialog is to include the **end** option in the last send message in the dialog, as shown in the following example:

```
send end {  
    ...  
}
```

When a call completes, whether it is successful or aborted, the **slpit** utility automatically closes any open dialogs. If the **slpit** utility runs in the same SLEE as the application, the application receives only an indication that the dialog is closed and might not handle it in the same way that it does the shutdown of a real TCAP dialog. Therefore, if a call ends with a status of Failed or Okay, and it has dialogs open, the

**slpit** utility displays a warning message. If a call was aborted, you can assume it might have an open dialog.

The **slpit** utility terminates a dialog when the application sends or receives a terminating event. When the **slpit** utility ends a dialog, it writes a line of output that indicates the number of messages that are still in the queue. Usually, you can ignore these messages because only internal SLEE messages will be left.

### Aborting a SLEE Dialog

You can also explicitly abort a dialog by using the `abort` message. Specify the **open** option to abort any open dialogs.

```
abort [main | assisting | open]
```

## Completing Calls

Each call instance finishes in one of the following states:

- **Aborted**  
Execution of the call was interrupted because something was sufficiently wrong that the call could not or should not continue. For example, an attempt was made to send an event when a dialog was no longer available, or a run-time error occurred.
- **Failed**  
The call was not completely successful but the errors were not sufficient to interrupt the call. The most likely cause is a discrepancy between the received and expected parameters for an operation. The call is failed but allowed to continue because the difference might not be significant.
- **Okay**  
The call completed without errors.

A call can finish for the following reasons:

- The call execution reaches the end of the call definition; the final call state will be either Failed, or Okay depending on whether there were errors in the run.
- A `finish call` command is executed: The call run is immediately finished either with its current state or the override state that is specified in the `finish call` command.
- The **slpit** utility encounters a serious error: The utility aborts the call immediately.

## Cancelling splpit

You can run multiple calls with **slpit**, either by specifically defining each call in the script input or by using the uniform or Poisson distribution models.

By default, the **slpit** utility does not stop generating calls if any call aborts or fails. You can change this behavior by using the `cancel after` command. You can place this command anywhere outside a call definition in a **slpit** script. The command has the following forms, each of which is self explanatory:

```
cancel after none
cancel after abort
cancel after failure
cancel after abort or failure
```

See ["The Call Sequence"](#) for more information about these commands.

You can also allow the **slpit** utility to continue after an abort or failure until a specified limit is reached.

You can use the following form of the cancel command to cancel a run after a specified number of failures or aborts occurs.

```
cancel after <number> [abort|failure]
```

If the number of specified aborts or failures occurs for the call, this command causes the **slpit** utility to stop call processing and exit. The program accepts either abort or failures. It also accepts either failure or failures.

The following command specifies a time limit, in seconds, on the number of failed or aborted calls that the **slpit** utility can receive before it cancels call processing and exits:

```
cancel after <number> [aborts|failures]in <number> seconds
```

The program accepts either second or seconds.

## Sending an Error

You can send an error to ACS or the application that you are testing by using either the `tcapReject` message or the error message. See ["tcapreject"](#) and ["error"](#) for more information.

## Creating the slpit Script File

The **slpit** utility processes a script file that consists of a few commands and a set of INAP send and receive operations, which define the progress of one or more call instances.

## Syntax

The following syntax conventions are used to describe the commands and operations that appear in the script file.

[ ]

Square brackets indicate that the enclosed items are optional. For example, the `correlationid` parameter in the following operation is optional.

```
establishtemporaryconnection
  address <digits>
  [correlationid <digits>]
```

|

A pipe separates one or more choices. For example, in the following `finish call` operation, you can optionally specify a final state of `aborted`, `failed`, or `okay`.

```
finish call [aborted|failed|okay]
```

...

An ellipsis indicates that an item can be repeated one or more times. In the following example, `part` must occur at least once but the ellipsis indicates that it can be repeated one or more times.

```
[variableparts <part> [<part>...]]
```



&lt;&gt;

Angle brackets indicate a placeholder that you replace with a specific value. The placeholder typically specifies the value's atomic token or basic data type such as <integer>, <string>, or <bcd>.

The **slpit** utility supports the following three styles of comments, which can appear anywhere in the script file:

- `//`

Two forward slashes indicate C++ style comments that can extend to the end of a line. The following line illustrates a full line comment:

```
//This is a full line comment
calledpartynumber "049393520" // This is an in-line comment
```

- `#`

A pound character indicates shell-style comments that can extend to the end of a line.

- `/*...*/`

Text enclosed by asterisks and then forward slashes indicate C-style comments that can extend multiple lines between the beginning and ending delimiters.

## Commands

You can include the following commands in the script file in addition to the messages and operations that define a call:

### **include <file>**

Includes the named file in the **slpit** script, enabling you to include a call sequence that is defined in a separate file. The value of <file> includes the directory path to the file's location.

### **define call <ID> { <call sequence> }**

Defines a set of call sequence messages and operations. The <ID> is an identifier you assign to the call and use to reference the call in other commands. See ["The Call Sequence"](#) for more information about <call sequence>.

### **startcall <ID> [ <ID>... ] using <distribution> [<seed>] maxconcurrent <limit> \ [after <wait\_seconds>]**

Defines the call types, the number of calls, and the call rate at which to start generating calls. You can start multiple call types and call rates by including multiple **startcall** commands in the script file.

For all distribution types, you can specify a random seed, which is a number that will be used to initialize the call rate. If not specified, the current clock time is used.

For all distribution types, you can also specify a maximum concurrent number of calls to hold open. This overrides any calls-per-second (CPS) rate and causes a lower CPS rate to be used. This is useful for specifying the maximum load that can be supported for the test system.

For all distribution types, you can specify that the block of calls are to be run after a wait time of a specified number of seconds. This is useful for specifying a stepped call rate, in which you define one **startcall** for each step, with each one timed to begin after the preceding one has finished.

After the keyword **using**, you can use the following forms of the command:

```
uniform <delay> <count>
```

```
once
poisson <delay> <count>
poisson <delay> <ramp> <count>
```

The <delay>, <count>, and <ramp> values must be defined as a number with a decimal point.

The <delay> parameter is the average interval between calls. You can alternatively express this value as calls per second and you can do so by using the `cps` keyword. For example `10.0 cps` is equivalent to a <delay> value of `0.1`.

The first form of the `poisson` command generates calls at random with the average interval between calls specified by the <delay> parameter.

The second form of the `poisson` command ramps up from zero calls per second to  $1/\text{<delay>}$  calls per second, taking about <ramp> seconds to reach the maximum call rate. It then flattens off at that rate.

## Call Definition Commands and Messages

The basic format of a call definition looks like this:

```
define call <ID> {
    <call sequence>
}
```

Each call type is identified by an ID that can be either a number or a name that starts with a letter and contains only letters, digits, and underscores.

The <call sequence> consists of a set of call definition messages that describe the progress of a call.

### The Call Sequence

The call sequence consists of one or more of the following call definition messages:

```
send [end] [assisting|main] { <message details> ... }
receive [assisting|main] { <reponse details> ... }
allow receive abort assisting
[send] abort [assisting|main|open]
wait <delay>
<ID> = <expression>
<ID> ?= <expression>
waitforcalls <delay> seconds|calls
finish call [aborted|failed|okay]
default timeout none
default timeout <expression> [ { <new call sequence> } ]
close [assisting|main|open]
cancel after [none|abort|fail] [or [abort|fail] ]
```

#### send

The **split** `send` message sends an event containing one or more operations, as determined by the message details, which you can modify through the use of various flags.

```
send [end] [assisting|main] { <message details> ... }
```

The `end` flag causes the messages to be sent as the final event on the dialog. You can use the `assisting` or `main` flag to override the dialog on which the message is sent. See ["Managing Script File Processing"](#) for more information.

**receive**

The **slpit** utility expects to receive an event containing one or more operations as determined by the response details in a receive message, including CS1InitiateAttempt and CAP4InitiateCallAttempt operations. You can use either the assisting or the main flag to override the dialog on which the message is expected to arrive.

```
receive [assisting|main] { <reponse details> ... }
```

See ["Managing Script File Processing"](#) for more information.

**allow receive abort**

An allow receive abort message indicates that the **slpit** utility should expect an abort to arrive from TCAP on the specified dialog at some time in the future. This is different from receive in that the **slpit** utility does not stop and wait for the abort, but continues processing.

```
allow receive abort assisting
```

**abort**

An abort message causes the **slpit** utility to send a TCAP abort on the specified dialog or dialogs (the default is the main dialog). Specifying open dialogs causes the **slpit** utility to abort any dialogs still open for the call.

```
[send] abort [assisting|main|open]
```

**wait**

The wait message causes the **slpit** utility to pause its processing of the call for a specified delay or until it is interrupted by a received event. You can specify the delay as an integer value representing microseconds or as a floating point value representing seconds. In other words, if the value contains a decimal point, the unit value is seconds. If it does not contain a decimal point, the unit value is microseconds. The following example illustrates the format of the message:

```
wait <delay>
```

**<ID> = <expression>**

The **slpit** utility uses the <ID> = <expression> definition to evaluate an expression and assign its value to a named variable. You can always assign an expression to ID using <ID> = <expression> but <ID> ?= <expression> only assigns an expression to ID if ID has not been already defined in the script.

```
<ID> = <expression>
<ID> ?= <expression>
```

**waitforcalls**

The waitforcallsmessage causes the **slpit** utility to pause its processing for a specified number of seconds or until the specified number of new calls started by TCAP\_BEGIN requests have finished. You specify the number of seconds to wait or the number of calls to process. The following example illustrates the format of the message:

```
wait <delay> seconds|calls
```

**finish call**

The `finish call` message finishes the call. You can specify a final state of `aborted`, `failed`, or `okay` to override the established state. For example, `finish call okay` causes a failed call to be recorded as successful.

```
finish call [aborted|failed|okay]
```

**default timeout**

The `default timeout` message specifies the default timeout that the **slpit** utility uses when waiting for a message. If you specify the {<new call sequence>} section, **slpit** will run the new call sequence when the timeout occurs rather than the lines that follow in the main call definition. If you specify `none`, it turns off the timeout altogether.

```
default timeout <expression> [ {<new call sequence>} ]  
default timeout none
```

**close**

The `close` message closes the SLEE dialog by way of a `DIALOG CLOSED` event on the given dialog. If you use the `open` option, the **slpit** utility closes all open dialogs.

```
close [assisting|main|open]
```

**cancel**

The `cancel after` message forces the **slpit** utility to exit any call immediately when the call fails or is aborted. This feature is most useful when running multiple calls in one **slpit** run, as when using the uniform and Poisson call distribution models.

This message has the following four formats:

- `cancel after none`  
This format prevents the **slpit** utility from exiting the run on the abort or failure of the call.
- `cancel after abort`  
This format causes the **slpit** utility to stop processing or generating calls and exit if the call aborts. You can substitute the word `aborts` for `abort`.
- `cancel after fail`  
This format causes the **slpit** utility to stop call processing and exit if the call fails. You can substitute the words `failure`, `failures`, and `fails` for `fail`.
- `cancel after abort or fail`  
This format causes the **slpit** utility to stop processing or generating calls and exit if the call aborts or fails. You can substitute words as described in the other formats of the `cancel` message.

You can use multiple `cancel` messages like this in the same call definition to handle calls that might not fail before a certain command, but could fail after another command.

You can also define a global cancellation strategy outside of a call definition. See ["Cancelling slpit"](#) for more information.

## About Expressions and Comparators

An expression generates a value that you can use, for example, as the parameter value for a `send` operation. The simplest form of an expression is a constant value. For example, "5551234" appearing in a **split** script is usually an expression that generates a digit string. More complex expressions are supported:

- Expressions that use the value of a variable by name.
- Expressions that use limited integer arithmetic: subtraction, addition, and multiplication. Integer arithmetic expressions may also contain parentheses for grouping.

For example:

```
callConnectedElapsedTime(talktime - 20) * 10
```

You can also specify ranges of numbers as an expression, including the Nature of Address of the generated numbers, which defaults to 3, if not specified. The syntax looks like this:

```
CLI = RANGE [ (<integer: NoA>) ] "<start of range>" "<end of range>"
SEQUENTIAL|RANDOM
```

For example,

```
CLI = RANGE(4) "49900010001" "49900020001" SEQUENTIAL
```

or

```
CLI = RANGE "49900010001" "49900020001" RANDOM
```

You can also obtain values from a text file, such as one for vouchers. For example, the following expression will take a line from **vouchers.txt** and use that value wherever **VOUCHERNUM** is used:

```
VOUCHERNUM=FROM_FILE "vouchers.txt"
```

If you want to randomly use rows from **vouchers.txt**, you need to randomize the file before you pass it to the **split** utility. Not having enough rows in your file to match the number of calls causes the **split** utility to produce an error and stop once the numbers have run out.

The INAP numbers are obtained from a text file. For example, the **APARTY** expression will take a line from **APARTY\_INAP.txt**. file and use the value wherever **APARTY** is used:

```
APARTY = FROM_INAP_FILE "APARTY_INAP.txt"
```

If sufficient rows are not available in your file, to match the number of calls causes the **split** utility to produce an error and stop once the numbers have run out. Another example of the file:

```
(5) 111121 screening 1 presind 2 numberplan 3 innorni 0
```

and a section of the split:

```
define call deciseconds_camel {
APARTY = FROM_INAP_FILE "APARTY_INAP.txt"
BPARTY = FROM_INAP_FILE "BPARTY_INAP.txt"
send {
initialdp
appContext      "0,4,0,0,1,0,50,1"
calledpartynumber BPARTY
```

```
callingpartynumber APARTY
locationNumber    "111144"
}
```

A comparator is a pattern for checking received values such as the parameters in received operations. There are three comparators:

- any
- [=] <expression>
- <comparator> -> <ID>

The any comparator matches any value.

The simplest comparator is an expression that tests for equality. You can optionally precede the expression with = to make the equality test explicit. Because the simplest expression is a constant value, comparators usually test for equality with a simple constant value. It might also be useful to compare to the value of a variable.

The last comparator generates a match or a mismatch based on the result of the comparator, which can be any other comparator. It stores the value being checked in the variable named by <ID>. This allows you to store a received parameter value for later use.

In the syntax description, <integer comparator> indicates that you can include any comparator at that point, but the comparison should be for an integer, so the expression or expressions underlying the comparison should generate integers. The same thing applies for other comparator types like <number comparator>.

```
<number>:
[( <noa> )] <digits>
[screening <integer>]
[presind <integer>]
[numberplan <integer>]
[innorni <integer>]
```

For outgoing numbers, the following default values are substituted for any field not specified:

```
noa=3 screening=0 presind=1 numberplan=1 innorni=0
```

For incoming numbers, any value is allowed for fields that have not been specified except <digits>.

## Call Messages

Call messages are divided into send message operations and receive message operations.

This chapter does not explain the semantics of INAP, MAP, or CAP operations, except where the mapping from the parameters in the script to those in the actual operations is not obvious. Please refer to the relevant standards documentation for the descriptions and procedures for particular operations. See the following standards documents for more information:

- *Intelligent Network (IN); Intelligent Network Capability Set 1 (CS1); Core Intelligent Network Application Protocol (INAP); Part 1: Protocol specification*. European Telecommunication Standard, ETS 300-374-1, September 1994.

- *3rd Generation Partnership Project; Technical Specification Group Core Network; Customized Applications for Mobile network Enhanced Logic (CAMEL) Phase 4; CAMEL Application Part (CAP) specification (Release 5). 3GPP 29.978 5.4.0 (2003-06).*
- *Digital cellular telecommunications system (Phase 2+); Mobile Application Part (MAP) specification (GSM 09.02 version 7.5.0 Release 1998). ETSI TS 100 974 V7.5.0 (2000-07).*

In the syntax descriptions in this section, `<integer expression>` indicates that an expression should appear at that point and the expression should produce an integer. Likewise for the syntax `<number expression>`. The syntax `<integer comparator>` indicates that you can include any comparator at that point, but the comparison should be for an integer, so the expression or expressions underlying the comparison should generate integers. Likewise for the syntax `<number comparator>`. See ["About Expressions and Comparators"](#) for more information.

## Send Message Operations

You can use the following operations in the send message portion of a call definition.

### **alertServiceCentre [<parameters>]**

You can use this operation for MAP handling. It sends alerts between MSC and HLR and it has the following parameters in any order:

**Table 2–3 alertServiceCenter Parameters**

Parameter	Value
msisdn	<number expression>
serviceCentreAddress	<number expression>

### **alertServiceCenterWithoutResult [<parameters>]**

You can use this operation for MAP handling. It sends alerts between MSC and HLR and it has the following parameter in any order:

**Table 2–4 alertServiceCenterWithoutResult Parameters**

Parameter	Value
msisdn	<number expression>
serviceCentreAddress	<number expression>

### **anyTimeInterrogation [<parameters>]**

This operation queries for information between GSM SCF and HLR. It has the following parameters:

**Table 2–5 anyTimeInterrogation Parameters**

Parameter	Value	Min.	Max
requestedInfo	(locationInformation   subscriberState)	N/A	N/A
imsi	<bcd>	N/A	N/A
msisdn	<bcd>	N/A	N/A
qmScf	<bcd>	N/A	N/A
sccp_orig_pc	<integer>	0	65535
sccp_orig_ssn	<integer>	0	255

**Table 2–5 (Cont.) anyTimeInterrogation Parameters**

Parameter	Value	Min.	Max
sccp_orig_tt	<integer>	0	255
sccp_orig_np	<integer>	N/A	N/A
sccp_orig_noa	<integer>	0	127
sccp_orig_rti	<integer>	0	1
sccp_orig_digits	<digits>	0	15
sccp_dest_pc	<integer>	0	65535
sccp_dest_ssn	<integer>	0	255
sccp_dest_tt	<integer>	0	255
sccp_dest_np	<integer>	0	15
sccp_dest_noa	<integer>	0	127
sccp_dest_rti	<integer>	0	1
sccp_dest_digits	<digits>	N/A	N/A

Table 2–6 lists the valid combinations of the fields that make up a global title:

**Table 2–6 Fields that make up a global title**

Global Title Type	Fields
1	noa, digits
2	tt, digits
3	tt, np, digits
4	tt, np, noa, digits

For global title types 3 and 4, the encoding is always binary coded decimal (BCD) that is 1 when there is an odd number of digits and 2 when there is an even number of digits.

### **applychargingreport**

This operation provides feedback from the service switching function (SSF) to the service control function (SCF). It has the following format:

```
applychargingreport
  thresholdtime <integer>
  endofcallindicator <integer>
  [freecallindicator <integer>]
```

The following format is available for use with INAP CAMEL extensions:

```
applychargingreport
  receivingSide <number>
  (timeNoTariffSwitch <number> |
   timeSinceTariffSwitch <number> |
   timeSinceTariffSwitch <number> tariffSwitchInterval <number> )
  [ callActive <number> ]
  [ callReleaseAtTcpExpiry <number> ]
```



**applychargingreportGprs**

This operation provides a report from the GPRS SCF to the GSM SSF. It has the following format:

```
applyChargingReportGprs
( gprsvolumeifnotariffswitch <integer> |
  gprsvolumesincelasttariffswitch <integer> [ gprstariffswitchinterval
<integer> ] |
  gprstimeifnotariffswitch <integer> |
  gprstimesincelasttariffswitch <integer> [ gprstariffswitchinterval <integer>
] )
<qos-list>
gprsActive <integer>
[ gprsPdpId <integer> ]
[ <ChargingRollover> ]
```

The <qos-list> section is one or more of the following in any order:

```
gprsrequestedqos <gprs-info>
gprsnegotiatedqos <gprs-info>
gprssubscribedqos <gprs-info>
```

The <gprs-info> data is the same as defined in initialDpGprs. See ["InitialDpGprs"](#) for more information.

The <ChargingRollover> section is optional, consisting of either:

```
<TransferredVolumeRollOver> | <ElapsedTimeRollOver>
```

The <TransferredVolumeRollOver> parameter consists of a choice of:

```
gprsrovolumeifnotariffswitch <integer> |
<ro-VolumeIfTariffSwitch>
```

Where <ro-VolumeIfTariffSwitch> consists of a sequence of:

```
gprsrovolumesincelasttariffswitch <integer> (optional)
gprsrovolumetariffswitchinterval <integer> (optional)
```

The <ElapsedTimeRollOver> consists of a choice of:

```
gprsrotimeifnotariffswitch <integer> |
<ro-TimeIfTariffSwitch>
```

Where <ro-TimeIfTariffSwitch> consists of a sequence of:

```
gprsrotimesincelasttariffswitch <integer> (optional)
gprsrotimetariffswitchinterval <integer> (optional)
```

**applyChargingReportAckGprs**

This operation has no parameters.

```
applyChargingReportAckGprs
```

**assistrequestinstructions**

This operation is used by the SSF to report a specific charging event to the SCF in response to the ApplyCharging operation. It has the following format:

```
assistrequestinstructions
[correlationid <digits>]
```

The message generated by this operation causes the event that contains it to be sent automatically as the first event on a new assisting dialog.

Although you can include the `correlationid` parameter in the script, it is ignored and overwritten with the value from the most recently received `EstablishTemporaryConnectioin` operation.

### **callinformationreport**

This operation sends specific call information to the SCF as requested by a previous `callinformationrequest` operation. This operation has the following format:

```
callinformationreport [<parameters>]
```

A `callinformationreport` operation should have one or more of the following parameters, appearing in any order, matching the information requested in the relevant `callinformationrequest` operation:

```
callattemptelapsedtime <integer expression>
callstoptime <digits>
callconnectedelapsedtime <integer expression>
calledaddress <number expression>
releasecause <cause expression>
```

The `callattemptelapsedtime` parameter is measured in seconds while the `callconnectedelapsedtime` parameter is measured in deciseconds. The `callstoptime` parameter is a string in the format: YYMMDDHHMMSS.

### **cap4InitiateCallAttemptResult**

This operation sends a response to a `cap4InitiateCallAttempt` request and has the following format:

```
cap4InitiateCallAttemptResult [<parameters>]
```

A `cap4InitiateCallAttemptResult` operation can have one or more of the following parameters, appearing in any order:

```
offeredCamel4Functionalities <integer expression>
supportedCamelPhases <integer expression>
releaseCallArgExtensionAllowed
```

The `offeredCamel4Functionalities` and `supportedCamelPhases` parameters are 16-bit string values.

### **collecteduserinformation**

This operation has the following format:

```
collecteduserinformation
digits <digits>
```

This is not a distinct operation. It represents the result form of the `INAP` operation, `promptAndCollectUserOperation`. The `digits` parameter corresponds to the `digitsResponse` tag in the result.

### **entityReleasedGprs**

Use this operation when the GPRS session is detached or a PDP context is disconnected and the related event is not equipped for reporting. This operation has the following format:

```
entityReleasedGprs
```

```
gprsReleaseCause <integer>
[ gprsPdPid <integer> ]
```

### **entityReleasedAckGprs**

This operation has no parameters. It is the returned result for entityReleasedGprs.

### **error**

An error operation has the following format:

```
error <name> [ invokeId <invoke-ID> ]
```

An error operation generates a U-ERROR component in the outgoing message. The name parameter determines the error code used. The following values are valid:

```
cancelled
cancelfailed
etcfailed
impropercallerresponse
missingcustomerrecord
missingparameter
parameteroutofrange
requestedinfoerror
systemfailure
taskrefused
unavailableresource
unexpectedcomponentsequence
unexpecteddatavalue
unexpectedparameter
unknownlegid
```

Some errors would typically have additional error codes, but the **slpit** utility supports only the ones listed here.

The <invoke-ID> value is from the last received INVOKE component, unless you specifically define it with the invokeId parameter.

### **eventreportbcs**

This operation notifies the SCF of a call-related event that was requested by the SCF in a previous RequestReportBCSMEvent operation. Examples of call-related events are busy and no answer. This operation has the following format:

```
eventreportbcs [ <event>... ]
```

The event parameter has the following format:

```
eventtypebcs <type>
[ miscallinfo <miscallinfo> | monitormode <mode> ]
[ legid <legid> | ( <integer> ) ]
[ eventspecificinfo <info> ]
```

The <mode> parameter has one of the following values:

```
interrupted
notifyAndContinue
transparent
```

The <legid> parameter has one of the following values:

```
[sendingsideid] <legtype>
[receivingsideid] <legtype>
```

The <legtype> parameter has one of the following values:

```
ltleg1
ltleg2
```

Event-specific information includes the following:

```
busycase <cause>
releasecause <cause>
failurecause <cause>
calledpartynumber <number>
```

### **eventReportGprs**

This operation notifies the GSM SCF of a GPRS session or PDP context related events:

```
eventReportGprs
gprsEventType <number>
[ gprsPdpId <integer> ]
```

### **eventReportAckGprs**

This operation has no parameters.

### **eventReportSms**

This operation notifies the GSM service control function (gsmSCF) of a previously requested short message related event. This message has no parameters.

### **informServiceCentre**

This operation is required for SMS gateway procedures between MSC and HLR. This message has the following format:

```
informServiceCentre [<parameters>]
```

The parameters consist of the following values:

```
storedMSISDN <number expression>
```

### **initialdp**

This operation is used after a trigger detection point (TDP) to issue a request for service. This message has the following format:

```
initialdp [<parameters>]
```

An initialdp message can have any of the following parameters, specified in any order:

```
calledpartynumber <number expression>
originalcalledpartynumber <number expression>
callingpartynumber <number expression>
redirectingpartynumber <number expression>
locationnumber <number expression>
additionalcallingpartynumber <number expression>
callingpartyscategory <categoryvalue or number>
callingpartyspin <digits>
origredirreason <integer> redirindicator <integer>
eventtypebcsn <type>
appcontext <string>
extension <integer> <type> <integer> <digits> <integer>
extension <integer> <type> <integer> <digits>
idp_sccp_orig_pc <integer> // 0 - 65535
```

```

idp_sccp_orig_ssn <integer> // 0 - 255
idp_sccp_orig_tt <integer> // 0 - 255
idp_sccp_orig_np <integer> // 0 - 15
idp_sccp_orig_noa <integer> // 0 - 127
idp_sccp_orig_rti <integer> // 0 or 1
idp_sccp_orig_digits <digits>
idp_sccp_dest_pc <integer> // 0 - 65535
idp_sccp_dest_ssn <integer> // 0 - 255
idp_sccp_dest_tt <integer> // 0 - 255
idp_sccp_dest_np <integer> // 0 - 15
idp_sccp_dest_noa <integer> // 0 - 127
idp_sccp_dest_rti <integer> // 0 or 1
idp_sccp_dest_digits <digits>

```

The following parameter is available for UCP handling:

```
AspID <string>
```

The following parameters are available for use with INAP CAMEL extensions:

```

iMSI <bcd>
countryCode <digits> networkCode <digits> locationAreaCode <integer> [ cellID
<integer> ]
[ bearerCapCodingStandard <number> bearerCapITC <number> [ bearerCapTransferMode
<number> bearerCapITR <number> bearerCapUIProtol <number> ] ]
hlCharacteristicsId <number>
calledPartyBCDNumber [ ( <integer> ) ] "number" [ numberPlan <integer> ]
vlrNumber [ ( <integer> ) ] "number" [ numberPlan <integer> ]
ageoflocationinfo <digits>
subscriberstate <digits>
locationnumberlocationinfo [ ( <integer> ) ] "number" [ numberPlan <integer> ]
extBearerService <hex digits>
extTeleService <hex digits>
callreference <string>
[ callForwardingSSPending ]
iMEI <bcd>

```

The countryCode and networkCode values can be only three digits long.

Bearer capability fields are optional and are divided in two stages as shown above. If the second stage is not present, the following default values are assigned:

bearerCapTransferMode = BC\_TM\_CIRCUIT (0x0), bearerCapITR = BC\_ITR\_64\_KBIT\_S (0x10) and bearerCapUIProtol = BC\_UIL1\_NOT\_PRESENT (0xff)

The following values are available for Bearer Capability fields:

**Table 2-7 Bearer Capability Values**

Bearer Capability Name	Constants	Value
bearerCapcodingStandard	BC_CS_ITU_T	0x00
	BC_CS_ISO_IEC	0x01
	BC_CS_NATIONAL	0x02
	BC_CS_NETWORK	0x03
bearerCapITC	BC_ITC_SPEECH	0x00
	BC_ITC_UDI	0x08
	BC_ITC_RDI	0x09
	BC_ITC_3_1_KHZ_AUDIO	0x10

**Table 2–7 (Cont.) Bearer Capability Values**

Bearer Capability Name	Constants	Value
	BC_ITC_UDI_TA	0x11
	BC_ITC_7_KHZ_AUDIO	0x11
	BC_ITC_VIDEO	0x18
bearerCapTransferMode	BC_TM_CIRCUIT	0x0
	BC_TM_PACKET	0x2
bearerCapITR	BC_ITR_PACKET	0x00
	BC_ITR_64_KBIT_S	0x10
	BC_ITR_2_64_KBIT_S	0x11
	BC_ITR_384_KBIT_S	0x13
	BC_ITR_1536_KBIT_S	0x15
	BC_ITR_1920_KBIT_S	0x17
	BC_ITR_MULTIRATE	0x18
bearerCapUIProtol	BC_UIL1_ITU_V110_I460_X30	0x01
	BC_UIL1_G711_U_LAW	0x02
	BC_UIL1_G711_A_LAW	0x03
	BC_UIL1_G721_32_KBIT_S	0x04
	BC_UIL1_H221_H242	0x05
	BC_UIL1_H223_H245	0x06
	BC_UIL1_NON_ITU_SRA	0x07
	BC_UIL1_ITU_V120	0x08
	BC_UIL1_X31_HDLC	0x09
	BC_UIL1_NOT_PRESENT	0xff

**InitialDpGprs**

When a trigger is detected at a detection point in the general GPRS state machines, this operation requests instructions from the GSM SCF. This message has the following format:

```

initialDpGprs
gprsEventType <integer>
gprsMsisdn <number expression>
gprsImsi <number expression>
gprsOriginatingReferenceNumber <number expression>
[ gprsEndUserAddress <PdpTypeOrganisation> <PdpTypeNumber> [ <address byte> ] ]
[ gprsrequestedqos <qos-info> ]
[ gprssubscribedqos <qos-info> ]
[ gprsnegotiatedqos <qos-info> ]
[ gprsaccesspointname <string> ]
[ gprschargingid <integer> ]
[ gprslocationinformation
gprsmobilecountrycode <bcd>
gprsmobilenetworkcode <bcd>
gprsmobilelocationareacode <bcd>
gprscellidentity <integer>
gprspdpinitiationtype <integer> ]

```

```
[ gprsggsnaddress <integer> [ <integer> ] ]
[ sgsnNumber <number expression> ]
```

The <gos-info> variable can have one of the following parameter values, all of which are integers:

**Table 2–8 InitialDpGprs**

Parameter	Min	Max
gprsqosprioritylevel	0	255
gprsqosdeloferrsdu	0	7
gprsqosdelorder	0	3
gprsqostrafficclass	0	7
gprsqosmaxsdusize	0	255
gprsqosmaxbrforuplink	0	255
gprsqosmaxbrfordownlink	0	255
gprsqosduerrratio	0	15
gprsqosresidualber	0	15
gprsqostrafhlingpri	0	3
gprsqostransferdelay	0	63
gprsqosguabrforuplink	0	255
gprsqosguabrfordownlink	0	255

### InitialDpSms

After it detects a TDP-R, the SMS SSF uses this operation to request instructions from the GSM SCF to complete the short-message submission to the SMSC or the short message delivery to the served subscriber. This message has the following format:

```
initialDpSms
[<parameters>]
```

An initialDpSms message can have the following parameters in any order:

```
callingPartyNumber <number expression>
destinationSubscriberNumber <number expression>
idp_sccp_orig_pc <integer> // 0 - 65535
idp_sccp_orig_ssn <integer> // 0 - 255
idp_sccp_orig_tt <integer> // 0 - 255
idp_sccp_orig_np <integer> // 0 - 15
idp_sccp_orig_noa <integer> // 0 - 127
idp_sccp_orig_rti <integer> // 0 or 1
idp_sccp_orig_digits <digits>
idp_sccp_dest_pc <integer> // 0 - 65535
idp_sccp_dest_ssn <integer> // 0 - 255
idp_sccp_dest_tt <integer> // 0 - 255
idp_sccp_dest_np <integer> // 0 - 15
idp_sccp_dest_noa <integer> // 0 - 127
idp_sccp_dest_rti <integer> // 0 or 1
idp_sccp_dest_digits <digits>
vlnrNumber [ ( <integer> ) ] "number" [ numberPlan <integer> ]
countryCode <digits> networkCode <digits> locationAreaCode <integer> [ cellID
<integer> ]
```

```
mScAddr <digits>
sMScAddr <digits>
```

**mergeCallSegmentResult**

This message has the following format with no parameters:

```
mergeCallSegmentResult
```

**moForwardSm**

This service forwards mobile-originated short messages between the serving mobile switching center (MSC) or the SGSN and the SMS internetworking MSC. This message has the following format:

```
moForwardSm [<parameters>]
```

For MAP version 3, this is a mobile-originated Forward-SM message, which is distinct from the `mtForwardSm` message. For MAP versions 1 and 2, this operation is a Forward-SM and it can originate or terminate from a mobile device, depending on the type of PDU in the SM-RP-UI.

A Forward-SM message has the following parameters in any order:

```
MapVersion <integer>
```

```
SegmentedBegin
SegmentedBody
```

```
imsiOA <number expression> //optional, only valid for MAP version 3
privateExtension <comma separated object ID string> <integer ASN.1 tag> <hex
value> // optional, only valid for MAP version 3
countryCode <digits> networkCode <digits> locationAreaCode <integer> cellID
<integer> // optional, valid for MAP versions 2 and 3
```

The `countryCode`, `networkCode`, `locationAreaCode`, and `cellID` parameters are used to construct the global cell ID. The `countryCode` and `networkCode` values can be only three digits long.

The `SM_RP_DA` field can be service center (MO) on an IMSI (MT):

```
imsi <number expression> (optional for MAP v2/v3 segmented body)
lmsi <number expression> (optional)
ServiceCentreAddressDA <number expression>
```

In a MAP version 2 or 3 segmented MT message, the `imsi` parameter is omitted in segments after the initial segment. If it is omitted, the MT message is encoded with the `noSM_RP_DA` parameter set.

The `SM_RP_OA` field can be an MSISDN (MO) or a service center (MT):

```
msisdn <number expression>
ServiceCentreAddressOA <number expression> (optional for MAP v2/v3 segmented body)
```

In a MAP version 2 or 3 segmented MT message, the originating service center is omitted in segments subsequent to the initial segment. If it is omitted, the MT message is encoded with the `noSM_RP_OA` parameter set.

Depending on the MAP version, the `SM_RP_UI` field can contain one of the following PDUs:



**Table 2–9 PDUs**

PDU	MAP Version	Comment
SMS-SUBMIT	1, 2, and 3	
SMS-DELIVER	1 and 2	In MT-ForwardSM for version 3
SMS-STATUS-REPORT	2	In MT-ForwardSM for version 3)

The type of PDU is determined by the message type indicator, TP-MTI:

TP\_MTI <number>

For an SMS-SUBMIT PDU, with TP-MTI=1, the following parameters are available:

TP\_VPF <number>  
 replyPath  
 requestStatusReport  
 TP\_MR <number>  
 TP\_DA [ToN] <string>  
 TP\_DCS <number>  
 TP\_VP { <1 or 7 octets (numbers)> }  
 userDataHeader { <number> <number> ... }  
 userDataText <string>

---

---

**Note:** For TP\_DA, alphabetic characters (non-telephony digits) are allowed only if ToN = 5 (alphanumeric).

---

---

For an SMS-DELIVER (TP-MTI=0), the following parameters are available:

moreMessages <0-1>  
 replyPath  
 TP\_OA [ToN] <string>  
 TP\_DCS <number>  
 userDataHeader { <number> <number> ... }  
 userDataText <string>

---

---

**Note:** For TP\_OA, alphabetic characters (non-telephony digits) are allowed only if ToN=5 (alphanumeric).

---

---

For an SMS-STATUS-REPORT (TP-MTI=2), the following parameters are available:

moreMessages <0-1>  
 TP\_MR <number>  
 TP\_RA [ToN] <string>  
 TP\_DCS <number>  
 userDataHeader { <number> <number> ... }  
 userDataText <string>

---

---

**Note:** For TP\_RA, alphabetic characters (non-telephony digits) are allowed only if ToN=5 (alphanumeric).

---

---

**Table 2–10 Min and Max for Parameters**

Parameter	Value	Min	Max
sccp_orig_pc	<integer>	0	65535
sccp_orig_ssn	<integer>	0	255
sccp_orig_tt	<integer>	0	255
sccp_orig_np	<integer>	0	15
sccp_orig_noa	<integer>	0	127
sccp_orig_rti	<integer>	0	1
sccp_orig_digits	<digits>	0	15
sccp_dest_pc	<integer>	0	65535
sccp_dest_ssn	<integer>	0	255
sccp_dest_tt	<integer>	0	255
sccp_dest_np	<integer>	0	15
sccp_dest_noa	<integer>	0	127
sccp_dest_rti	<integer>	0	1
sccp_dest_digits	<digits>	0	15

There must be exactly one each of `imsi`, `lmsi`, `ServiceCentreAddressDA`, and `noSM_RP_DA`. There must be exactly one of `msisdn`, `ServiceCentreAddressOA`, `noSM_RP_OA`., and `imsiOA`. You can use the `imsiOA` parameter only for MAP3.

If the `SegmentedBegin` parameter is present, the only other parameters allowed are `MapVersion` and `IMSI`. The result is that a `TCAP_BEGIN` message is sent with the appropriate application context but with no component (the User Information part of the `TCAP_BEGIN` message contains a `MAP-OPEN` with an optional `IMSI` in it.) If the `IMSI` parameter is present in the `SegmentedBegin`, the `RP-DA` in the `ForwardSM` should be a `LMSI`, but this is not enforced by the `slpit` utility.

If the `SegmentedBody` parameter is present, a normal `moForwardSM` operation is sent (in a `Continue`) but with no application context. You must always pair `SegmentedBegin` and `SegmentedBody` operations with appropriate MAP versions and a `receive{}` message between them.

The following segmentation scenarios are valid.

- `IMSI` and `LMSI` parameters in segmented message:

**Table 2–11 IMSI and LMSI Parameters Segmentation Scenario**

Primitive	MAP-OPEN	ForwardSM RP-DA	Segment
<code>TCAP_BEGIN</code>	<code>imsi</code>	N/A	Begin
<code>TCAP_CONTINUE</code>	N/A	<code>lmsi</code>	Body #1
<code>TCAP_CONTINUE</code>	N/A	<code>noSM-RP-DA</code>	Body #2

- `IMSI` only in a segmented message:

**Table 2–12 IMSI-only Parameters Segmentation Scenario**

Primitive	MAP-OPEN	ForwardSM RP-DA	Segment
TCAP_BEGIN	empty	N/A	Begin
TCAP_CONTINUE	N/A	imsi	Body #1
TCAP_CONTINUE	N/A	noSM-RP-DA	Body #2

- IMSI and LMSI in a non-segmented message:

**Table 2–13 IMSI and LMSI Non-Segmentation Scenario**

Primitive	MAP-OPEN	ForwardSM RP-DA	Segment
TCAP_BEGIN	imsi	imsi	N/A

- IMSI only in a non-segmented message:

**Table 2–14 IMSI-only Non-Segmentation Scenario**

Primitive	MAP-OPEN	ForwardSM RP-DA	Segment
TCAP_BEGIN	empty	imsi	N/A

You may specify either the `userDataheader` or the `userDatatext` or both. You must specify the header byte by byte, and in decimal or hex (with 0x as a prefix) – for example, `userDataHeader {0x17 0x34}`. The header is automatically prefixed with a one-byte length field.

The `userDatatext` parameter will be added to the packet after the `userDataheader` parameter in either GSM 7-bit (default) or Unicode UCS2/UTF16 (big endian, meaning the most significant bytes in multi-byte data types are stored first) or binary, depending on the value of the data coding scheme `TP_DCS`.

The **slpit** utility does not support compressed user data.

You can specify `TP_VF` (validity period format) and `TP_VP` (validity period). See GSM 03.40 v7.5.0 sections 9.2.3.3 and 9.2.3.12 for encoding details. For example:

- `tp_vf 0`  
VPF of 0, or not specified, means no validity period format.
- `tp_vf 1`  
Enhanced format (new to MAP version 3) `tp_vp {0x42 0x80 0x00 0x00 0x00 0x00 0x00}`. Relative; 128 (0x80) seconds and `single-shot=true`.
- `tp_vf 2`  
Relative format `tp_vp { 128 }`, where 128 is decimal and means 645 minutes.
- `tp_vpf 3`  
Absolute format `tp_vp { 0x40 0x50 0x32 0x61 0x10 0x20 0x00}`. 2004-05-23 16:01:02 GMT.

### mtForwardSM

This operation is a MAP version 3 mobile-terminated `Forward-SM` and is available for use with MAP. It forwards mobile terminated short messages between the gateway mobile switching center (MSC) and the servicing MSC or the SGSN.

```
mtForwardSm [<parameters>]
```

An `mtForwardSm` operation should have the following parameters, appearing in any order:

```
MapVersion <integer> // only 3 is valid
SegmentedBegin
SegmentedBody
```

The `SM_RP_DA` field must be an IMSI number for MT-ForwardSM if the message is not getting segmented. If the message is segmented, the `SM_RP_DA` can be a LMSI, in which case the `segmentedBegin` should contain the IMSI:

```
imsi <number expression> // optional in the SegmentedBegin
lmsi <number expression> // optional in the SegmentedBody
```

In a segmented MT-ForwardSM operation, the IMSI is omitted in segments following the initial segment. If it is omitted, the operation is encoded with the `noSM_RP_DA` parameter set.

The `SM_RP_OA` field must be a service center for MT-ForwardSM:

```
ServiceCentreAddressOA <number expression> (optional)
```

In a segmented MT-ForwardSM operation, the originating service center is omitted in segments following the initial segment. If it is omitted, the operation is encoded with the `noSM_RP_OA` parameter set.

The `SM_RP_UI` field must contain an SMS-DELIVER or an SMS-STATUS-REPORT for MT-ForwardSM. For more information, see "[moForwardSm](#)".

```
sccp_orig_pc <integer> // 0 - 65535
sccp_orig_ssn <integer> // 0 - 255
sccp_orig_tt <integer> // 0 - 255
sccp_orig_np <integer> // 0 - 15
sccp_orig_noa <integer> // 0 - 127
sccp_orig_rti <integer> // 0 or 1
sccp_orig_digits <digits>
sccp_dest_pc <integer> // 0 - 65535
sccp_dest_ssn <integer> // 0 - 255
sccp_dest_tt <integer> // 0 - 255
sccp_dest_np <integer> // 0 - 15
sccp_dest_noa <integer> // 0 - 127
sccp_dest_rti <integer> // 0 or 1
sccp_dest_digits <digits>
```

If `SegmentedBegin` is present, the only other parameters allowed are `MapVersion` and `IMSI`. This results in a `TCAP_BEGIN` being sent with the appropriate application context but no component (the User Information part of the `TC_BEGIN` contains a `MAP-OPEN` with an optional `IMSI` in it). If the `IMSI` is present in the `SegmentedBegin`, the `RP-DA` in the `ForwardSM` should be a `LMSI`, but this is not enforced by the `split` utility.

If `SegmentedBody` is present, a normal `moForwardSM` is sent in a `CONTINUE` but with no application context. You are responsible for always pairing `SegmentedBegin` and `SegmentedBody` operations, with matching `MapVersions` and a `receive{}` message between them.

See the segmentation scenarios in the "[moForwardSm](#)" section for more information.

You may specify either the `userData` header or the text or both. You must specify the header byte by byte in decimal or hex (with a `0x` prefix) – for example, `userData { 0x02 0x17 0x34 }`. The first number in the user data header should be the length, in

bytes, of the remainder of the user data header. In this case, 0x02 indicates that there are two more bytes to follow in the header.

Any user data text will be copied after the user data header, with bit padding inserted to align to a septet boundary.

### **readyForSM**

This operation is available for MAP handling. It is used between the message switching center (MSC) and the VLR and between the VLR and the HLR. If a subscriber has available memory, the MSC initiates this service and the VLR indicates this condition to the HLR. If a subscriber, whose message waiting flag is active in the VLR, has radio contact in the MSC, the VLR initiates this service.

Likewise, if a subscriber has available memory, the SGSN initiates this service to indicate this to the HLR. Also, if a subscriber whose message waiting flag is active in the SGSN has radio contact in the GPRS, the SGSN initiates this service.

```
readyForSM [<parameters>]
```

A readyForSM operation should have the following parameters, appearing in any order.

```
imsi <bcd>
alertReason <alertReason> | <number>
```

The <alertReason> value can be one of the following:

```
ms_Present
memoryAvailable
```

### **reportSMDeliveryStatus**

This operation is available for MAP handling. It is used by the message switching center (MSC) to set the message waiting data into the HLR or to inform the SLR of a successful short message (SM) transfer after polling.

```
reportSMDeliveryStatus [<parameters>]
```

A reportSMDeliveryStatus operation should have the following parameters, appearing in any order.

```
msisdn <number expression>
serviceCentreAddress <number expression>
smDeliveryOutcome <smDeliveryOutcome> | <number>
```

The <smDeliveryOutcome> value can be one of the following:

```
memoryCapacityExceeded
absentSubscriber
successfulTransfer
```

### **sendRoutingInfoForSm**

This operation is for MAP handling and has the following format.

```
sendRoutingInfoForSm [<parameters>]
```

A sendRoutingInfoForSm operation should have the following parameters, appearing in any order.

```
MapVersion <number>
msisdn <number expression>
AttemptDelivery <0-1>
```

```
ServiceCentreAddress <number expression>
(optional parameters)
MessageTypeIndicator <number>
OriginatingSmeAddr <number expression>
GprsSupport <0-1>
sccp_orig_pc <integer> // 0 - 65535
sccp_orig_ssn <integer> // 0 - 255
sccp_orig_tt <integer> // 0 - 255
sccp_orig_np <integer> // 0 - 15
sccp_orig_noa <integer> // 0 - 127
sccp_orig_rti <integer> // 0 or 1
sccp_orig_digits <digits>
sccp_dest_pc <integer> // 0 - 65535
sccp_dest_ssn <integer> // 0 - 255
sccp_dest_tt <integer> // 0 - 255
sccp_dest_np <integer> // 0 - 15
sccp_dest_noa <integer> // 0 - 127
sccp_dest_rti <integer> // 0 or 1
sccp_dest_digits <digits>
```

### **sendRoutingInformation**

This operation is available for MAP handling and has the following format:

```
sendRoutingInformation [<parameters>]
```

A sendRoutingInformation operation should have the following parameters, appearing in any order:

```
interrogationType <0-1>
gsmcAddress <number expression>
msisdn <number expression>
(optional parameters)
sccp_orig_pc <integer> // 0 - 65535
sccp_orig_ssn <integer> // 0 - 255
sccp_orig_tt <integer> // 0 - 255
sccp_orig_np <integer> // 0 - 15
sccp_orig_noa <integer> // 0 - 127
sccp_orig_rti <integer> // 0 or 1
sccp_orig_digits <digits>
sccp_dest_pc <integer> // 0 - 65535
sccp_dest_ssn <integer> // 0 - 255
sccp_dest_tt <integer> // 0 - 255
sccp_dest_np <integer> // 0 - 15
sccp_dest_noa <integer> // 0 - 127
sccp_dest_rti <integer> // 0 or 1
sccp_dest_digits <digits>
```

An interrogationType value of 0 indicates a basic call; a value of 1 indicates a forwarding call.

### **smsNotification**

This operation is available for IS-41 support. Your application can expect to receive one of these from an MSC when a SME comes back online after sleeping through a direct delivery attempt.

```
smsNotification [<parameters>]
```

An smsNotification operation can have the following parameters.

```
smsnot_MIN <bcd-string> // 10 digit number
```

```
smsnot_ESN <integer> <integer> // 0..2^8, 0..2^24
```

### smsNotificationResult

The response to an smsNotification operation does not contain any parameters.

```
smsNotificationResult
```

### locationRequest

This operation is available for IS-41 support and has the following format:

```
locationRequest [<parameters>]
```

A locationRequest operation has the following parameters:

```
locreq_BID <integer> <integer> <integer> <integer> // 0..2^16, 0..2^8, 0..2^24,
0..2^8
locreq_DIGITS <integer> <integer> <bcd-string>
locreq_MSCID <integer> <integer> // 0..2^16, 0..2^8
locreq_SYSTEMMYTYPECODE <integer>
sccp_orig_pc <integer> // 0 - 65535
sccp_orig_ssn <integer> // 0 - 255
sccp_orig_tt <integer> // 0 - 255
sccp_orig_np <integer> // 0 - 15
sccp_orig_noa <integer> // 0 - 127
sccp_orig_rti <integer> // 0 or 1
sccp_orig_digits <digits>
sccp_dest_pc <integer> // 0 - 65535
sccp_dest_ssn <integer> // 0 - 255
sccp_dest_tt <integer> // 0 - 255
sccp_dest_np <integer> // 0 - 15
sccp_dest_noa <integer> // 0 - 127
sccp_dest_rti <integer> // 0 or 1
sccp_dest_digits <digits>
```

The locreq\_BID (Billing ID) parameters are: Market ID, Switch Number, ID Number, and Segment Counter. The locreq\_DIGITS parameters are: Type of Digits, Nature of Number, and BCD Digits. The locreq\_MSCID parameters are: Market ID, and Switch Number.

The locreq\_SYSTEMMYTYPECODE parameter sets VENDOR\_IDENTIFIER\_, which is the only content of locreq\_SYSTEMMYTYPECODE.

You can use the following values for VENDOR\_IDENTIFIER:

```
VENDOR_IDENTIFIER_NotUsed = 0,
VENDOR_IDENTIFIER_EDS = 1,
VENDOR_IDENTIFIER_Astronet = 2,
VENDOR_IDENTIFIER_LucentTechnologies = 3,
VENDOR_IDENTIFIER_Ericsson = 4,
VENDOR_IDENTIFIER_GTE = 5,
VENDOR_IDENTIFIER_Motorola = 6,
VENDOR_IDENTIFIER_NEC = 7,
VENDOR_IDENTIFIER_NORTEL = 8,
VENDOR_IDENTIFIER_NovAtel = 9,
VENDOR_IDENTIFIER_Plexsys = 10,
VENDOR_IDENTIFIER_DigitalEquipmentCorp = 11,
VENDOR_IDENTIFIER_INET = 12,
VENDOR_IDENTIFIER_Bellcore = 13,
VENDOR_IDENTIFIER_AlcatelSEL = 14,
VENDOR_IDENTIFIER_Tandem = 15,
VENDOR_IDENTIFIER_QUALCOMM = 16,
```

```
VENDOR_IDENTIFIER_Aldiscon = 17,  
VENDOR_IDENTIFIER_Celcore = 18,  
VENDOR_IDENTIFIER_TELOS = 19,  
VENDOR_IDENTIFIER_Stanilite = 20,  
VENDOR_IDENTIFIER_CoralSystems = 21,  
VENDOR_IDENTIFIER_SynacomTechnology = 22,  
VENDOR_IDENTIFIER_DSC = 23,  
VENDOR_IDENTIFIER_MCI = 24,  
VENDOR_IDENTIFIER_NewNet = 25,  
VENDOR_IDENTIFIER_SemaGroupTelecoms = 26,  
VENDOR_IDENTIFIER_LGInformationAndCommunications = 27,  
VENDOR_IDENTIFIER_CBIS = 28,  
VENDOR_IDENTIFIER_Siemens = 29
```

### **locationRequestResult**

This is the response to a locationRequest operation.

```
locationRequestResult [<parameters>]
```

A locationRequestResult operation has the following parameters:

```
smsreq_ESN <integer> <integer> // 0..2^8, 0..2^24  
smsreq_MIN <integer> // must be 10 digits  
smsreq_MSCID <integer> <integer> // 0..2^16, 0..2^8
```

The MSCID, ESN and MIN parameters are mandatory in the response. However, if the ESN is unknown, it is set to "0 0"; if the MIN is unknown it is set to "0000000000".

### **smsRequest**

This operation is available for IS-41 support. Your applications should never receive one of these. It is included only to assist in testing scenarios in which the service control point, acting as an SMSC, receives an unexpected operation.

```
smsRequest [<parameters>]
```

A smsRequest operation can have the following parameters.

```
smsreq_MIN <bcd-string> // 10 digit number  
smsreq_IMSI <number expression>  
smsreq_MDN <integer> <integer> <bcd-string>  
smsreq_ESN <integer> <integer> // 0..2^8, 0..2^24  
smsreq_notificationIndicator <integer> // 0..255  
smsreq_teleserviceNameIdentifier <integer> // 0..65535  
sccp_orig_pc <integer> // 0 - 65535  
sccp_orig_ssn <integer> // 0 - 255  
sccp_orig_tt <integer> // 0 - 255  
sccp_orig_np <integer> // 0 - 15  
sccp_orig_noa <integer> // 0 - 127  
sccp_orig_rti <integer> // 0 or 1  
sccp_orig_digits <digits>  
sccp_dest_pc <integer> // 0 - 65535  
sccp_dest_ssn <integer> // 0 - 255  
sccp_dest_tt <integer> // 0 - 255  
sccp_dest_np <integer> // 0 - 15  
sccp_dest_noa <integer> // 0 - 127  
sccp_dest_rti <integer> // 0 or 1  
sccp_dest_digits <digits>
```

The smsreq\_MDN parameters are: Type of Digits, Nature of Number, and BCD Digits.



## smsRequestResult

This is the response to an smsRequest operation.

```
smsRequestResult [<parameters>]
```

An smsRequest operation can be an Ack or a Nack. Acks contain an address, and can also return ESN data. Nacks may specify a value for the accessDeniedReason parameter.

```
smsreq_ESN <integer> <integer> // 0..2^8, 0..2^24
smsreq_address <integer> <integer> <bcd-string> // NoN, NPI, digits
smsreq_accessDeniedReason <integer> // 0..255
```

## smsDeliveryPointToPoint

This operation is available for IS-41 support. You can use this to deliver a short message over IS-41.

```
smsDeliveryPointToPoint [<parameters>]
```

The **slpit** utility supports three text-based teleservices, CDMA 4098, CDMA 4101, and TDMA 32513 and two use cases for the text message. The first is human-readable text with an optional header. The text is encoded as 7-bit ASCII for CDMA or IRA for TDMA. (The actual encoding step is independent of the smdpp\_userDataEncoding parameter.) You may not specify both text and header for a TDMA message.

The CDMA text plus header has the following format:

tag	length	encoding	num_fields	header	padding-1	text	padding-2
-----	--------	----------	------------	--------	-----------	------	-----------

The text and header fields can have the following values:

**Table 2–15 smsDeliveryPointToPoint values**

Field	Value
tag	0x01
length	The number of octets after this one.
encoding	The first five bits of the smdpp_userDataEncoding value. Note that everything after this is shifted 3 bits to the left.
num_fields	The number of characters (7 or 8-bit) after this octet.
header	Zero or more octets of GSM user-data-header. This is taken directly from the smdpp_userDataHeader value.
padding-1	Padding required to make the header end on a septet boundary. This is only done if the encoding is 2 (7-bit ASCII, default) or 3 (IA5).
text	Encoded message text. This will always be 7-bit ASCII.
padding-2	Padding required to make this whole block end on an octet boundary.

The TDMA text has the following format:

length	type	padding	text
--------	------	---------	------

The fields can have the following values:

**Table 2–16 TDMA values**

Field	Value
length	The number of octets following this one.
type	The first 5 bits of <code>smdpp_userDataEncoding</code> .
padding	3 bits of padding, so that text starts on an octet boundary.
text	Text as something resembling IRA, with each character 7 bits wide but stored in an octet with the high bit off.

With the second use case for text messaging, you cannot use the human-readable text parameter (`smdpp_userDataText`); you must put the raw bytes of the message into the header (`smdpp_userDataHeader`). The header and text are packed into the message for the different use cases as follows:

The CDMA header only has the following format:

tag	length	encoding	num_fields	data	padding
-----	--------	----------	------------	------	---------

These fields have the following values:

**Table 2–17 CDMA header values**

Field	Value
tag	
length	
encoding	
num_fields	
data	The octets specified in <code>smdpp_userDataHeader</code> shifted 3 bits to the left.
padding	Empty bits required to bring the block to an octet boundary.

The TDMA header has the following format:

length	type	padding	data
--------	------	---------	------

These fields have the following values:

**Table 2–18 TDMA header values**

Field	Value
length	
type	
padding	
data	The octets specified in the <code>smdpp_userDataHeader</code>

Note that the translation of text from the human-readable input form to ASCII or IRA is not perfect. When in doubt, try using the header to set the raw data.

A `smsDeliveryPointToPoint` may have the following parameters.

**Table 2–19 smsDeliveryPointToPoint Parameters**

Parameter	Type	Value
smdpp_teleservice	<integer>	4098, 4100, 32513
smdpp_MIN	<bcd-string>	10 digit
smdpp_ESN	<integer>< integer>	0..2 <sup>8</sup> , 0..2 <sup>24</sup>
smdpp_origAddr	<integer>< integer><bcd-string>	NoN, NPI, digits
smdpp_origOrigAddr	<integer>< integer><bcd-string>	NoN, NPI, digits
smdpp_destAddr	<integer>< integer><bcd-string>	NoN, NPI, digits
smdpp_origDestAddr	<integer>< integer><bcd-string>	NoN, NPI, digits
smdpp_messageCount	<integer>	0..2 <sup>8</sup>
smdpp_notInd	<integer>	0..2 <sup>8</sup>
smdpp_chargeInd	<integer>	0..2 <sup>8</sup>
smdpp_userDataEncoding	<number>	
smdpp_userDataHeader	{<number>...}	
smdpp_userDataText	<string>	
CDMA	{ <parameters> }	
TDMA	{ <parameters> }	

The `smdpp_teleservice` parameter is mandatory, and must be set according to IS-41-D before the TDMA or CDMA sections can be used. For more information about these parameters, please consult TIA/EIA-41-D-1997 (IS-41), 3GPP2 C.S0015-A (CDMA) and TIA/EIA-136-710-C (TDMA).

Each teleservice may place a particular restriction on the data specified. These restrictions aren't generally enforced by the `slpit` utility, because you might want to send bad data. The following are common restrictions:

- CDMA 4098  
No userdata header present.
- CDMA 4100  
Encoding type is 0.
- TDMA 32513  
No userdata header present.

The following lists show the common encoding values:

- CDMA

**Table 2–20 CDMA values**

Value	Name	Width
0	octet-unspecified	8
1	Extended protocol message	N/A
2	7-bit ASCII (default)	7
3	IA5	7

**Table 2–20 (Cont.) CDMA values**

Value	Name	Width
4	UNICODE	16
5	Shift JIS	8 / 16
6	Korean	8 / 16
7	Latin/Hebrew	8
8	Latin	8

■ TDMA

**Table 2–21 TDMA values**

Value	Name	Width
1	IRA	7
2	User specific	8
3	Latin	8
5	Latin/Hebrew	8

If you are using the CDMA teleservices, you can specify the following parameters in the CDMA subsection:

**Table 2–22 CDMA parameters**

Parameter	Type	Value
smdpp_messageId	<integer><integer><boolean>	0..2 <sup>4</sup> , 0..2 <sup>16</sup> , true/false
smdpp_validityPeriod	<integer>	See 4.5.6.1 of 3GPP2 CS 15-A
smdpp_validityPeriod	<string>	YYMMDDhhmmss
smdpp_deferredDeliveryTime	<integer>	See 4.5.6.1 of 3GPP2 CS 15-A
smdpp_deferredDeliveryTime	<string>	YYMMDDhhmmss
smdpp_priorityInd	<integer>	0..3
smdpp_privacyInd	<integer>	0..3
smdpp_languageInd	<integer>	0..255
smdpp_alertOnDelivery	<integer>	0..3
smdpp_DAKRequested	<boolean>	true/false
smdpp_MAKRequested	<boolean>	true/false
smdpp_RAKRequested	<boolean>	true/false

If you are using the TDMA teleservice, you can specify the following parameters in the TDMA subsection:

**Table 2–23 TDMA parameters**

Parameter	Type	Value
smdpp_messageTypeInd	<integer>	0..2 <sup>3</sup>

**Table 2–23 (Cont.) TDMA parameters**

Parameter	Type	Value
smdpp_messageRef	<integer>	0..2 <sup>13</sup>
smdpp_privacyInd	<integer>	0..2 <sup>3</sup>
smdpp_urgencyInd	<integer>	0..2 <sup>2</sup>
smdpp_DAKRequested	<boolean>	true/false
smdpp_MAKRequested	<boolean>	true/false
smdpp_messageUpdating	<boolean>	true/false
smdpp_vp_absolute	<integer>	0..1
smdpp_vp_relativeTimerValue	<integer>	0..255
smdpp_vp_absoluteSeconds	<integer>	0..2 <sup>32</sup>
smdpp_vp_absoluteTZOffsetDirection	<integer>	0..1
smdpp_vp_absoluteTZOffsetMinutes	<integer>	0..720
smdpp_vp_absoluteTZOffsetDSI	<integer>	0..1

**smsDeliveryPointToPointResult**

This is the response to an smsDeliveryPointToPoint operation.

```
smsDeliveryPointToPointResult [<parameters>]
```

An smsDeliveryPointToPoint operation may be an Ack or a Nack. Nacks contain an SMS\_CauseCode parameter, specified as follows:

```
smdpp_causeCode <integer> // 0..2^8
```

**slpitLegResult**

This operation is available for INAP level 2 (CS-2) handling.

```
slpitLegResult
```

This operation has no parameters.

**specializedresourcereport**

This operation has no parameters.

```
specializedresourcereport
```

**tcapreject**

```
tcapreject
  problemtype <type>
  generalproblem <problem>
```

A tcapreject operation will have the slpit utility send a TCAP\_REJECT primitive on the main dialog. The problem type and ID are taken from the parameters. The mandatory parameter is problemtype which must be an integer from the following list:

**Table 2–24 Integer List**

-1	none
0	general

**Table 2–24 (Cont.) Integer List**

1	invoke
2	return_result
3	return_error

The `generalproblem` parameter is also an integer, from 0 to 255. The reject source is set to `TCAP_REJECT_LOCAL`.

### unstructuredSS

This operation is available for MAP handling. It sends a `MAP2_ProcessUnstructuredSSRequest`. The only language available is the default GSM alphabet because that is the only language that `TC_PROTOS` currently supports.

`unstructuredSS [<parameters>]`

An `unstructuredSS` operation can have the following parameters, appearing in any order:

```
msisdn <number expression>
msisdnReference <number expression>
originatingReference <number expression>
destinationReference <number expression>
ussd <string>
imei <bcd>
countryCode <digits>
networkCode <digits>
locationAreaCode <integer>
cellID <integer>
sccp_orig_pc <integer> // 0 - 65535
sccp_orig_ssn <integer> // 0 - 255
sccp_orig_tt <integer> // 0 - 255
sccp_orig_np <integer> // 0 - 15
sccp_orig_noa <integer> // 0 - 127
sccp_orig_rti <integer> // 0 or 1
sccp_orig_digits <digits>
sccp_dest_pc <integer> // 0 - 65535
sccp_dest_ssn <integer> // 0 - 255
sccp_dest_tt <integer> // 0 - 255
sccp_dest_np <integer> // 0 - 15
sccp_dest_noa <integer> // 0 - 127
sccp_dest_rti <integer> // 0 or 1
sccp_dest_digits <digits>
```

The `countryCode` and `networkCode` can be only three digits long.

A `MapOpen` is inserted into the TCAP primitive's `UserInfo` area. The `msisdnReference` is used to populate the `msisdnReference` in the `MapOpen`. The `destinationReference` populates the `destinationReference` in the `MapOpen`. The `originatingReference` is used to populate `originatingReference` in the `MapOpen`. The `msisdn` is used to populate the `msisdn` parameter in the `UnstructuredSSRequest`.

### [empty]

The `split` utility can also send empty TCAP primitives. You can accomplish this by leaving the body of the send message blank as shown in the following example:

```
send
{
```

```
}
```

## Receive Message Operations

The following operations are available in the receive message portion of a call definition.

### abort

The format of this operation is:

```
abort
```

Use this operation to receive aborts that you expect. The Calls Aborted count is not updated, but the Calls Succeeded count is updated. When you use this operation, the script expects an abort so the test is successful in that it received one and continues. This is especially useful when running multiple calls because a standard abort would cause **slpit** to stop processing.

### anyTimeInterrogation

This operation is available for handling MAP. It is used for time information enquiries between GSM SCF and HLR. It has the following format and parameters:

```
anyTimeInterrogation
[ locationInformation
[ age <integer comparator> ]
[ geographical <number comparator> ]
[ vrl <number comparator> ]
[ location <number comparator> ]
[ cell <number comparator> ]
]
```

You can define the parameters to the `locationInformation` part of this operation in any order.

### applycharging

This operation has the following format:

```
applycharging
thresholdtime <integer comparator>
[warningtime <integer comparator>]
```

The following format is available for handling CAMEL:

```
applyCharging
maxDuration <integer>
[ release <integer> tone <integer> ]
[ tariff <integer> ]
```

### applyChargingGprs

This operation is available for GPRS handling and it takes one of the following two forms:

```
applyChargingGprs
gprsTransferredVolume <integer>
[ gprstariffswitchinterval <integer> ]
[ gprsPdPid <integer> ]
```

```
applyChargingGprs
```

```
gprsElapsedTime <integer>
[ gprstariffswitchinterval <integer> ]
[ gprsPdPid <integer> ]
```

### **callinformationrequest**

This operation requests the SSF to record information about a call and use the `CallInformationReport` operation to report it to the SCF. This operation has the following format:

```
callinformationrequest <requested fields>
```

A `callinformationrequest` operation must have at least one of the following labels requesting particular information. They may appear in any order:

```
callattemptelapsedtime
callstoptime
callconnectedelapsedtime
calledaddress
releasecause
```

These are effectively flags and do not have any associated values.

### **cap4InitiateCallAttempt**

This operation requests the SSF to initiate a CAP4 call attempt and returns the result in a `cap4InitiateCallAttemptResult` message. It has the following format:

```
cap4InitiateCallAttempt [<parameters>]
```

A `cap4InitiateCallAttempt` operation may have any of the following parameters, in any order:

```
callingpartnumber <number comparator>
callreference <number comparator>
callsegmentid <integer>
destroutingaddr <number comparator>
gsmscf <number comparator>
legid <integer>
suppresstcsi
```

### **collectinformation**

This operation requests the SSF to perform the call processing actions that collect destination information from a calling party. This operation has the following format, with no parameters.

```
collectinformation
```

### **connect**

This operation requests the SSF to route a call to its destination. It has the following format:

```
connect [<parameters>]
```

The `connect` operation can have any of the following parameters in any order:

```
originalcalledpartnumber <number comparator>
  callingpartynumber <number comparator>
  redirectingpartynumber <number comparator>
  redircount <integer> redirreason <integer>
```



```

    destroutingaddr <number comparator>
    callingpartyscategory <integer> | callingpartyscategory <category>
    genericnumbers numberqualifier <qualifier> <number comparator>
    ...numberqualifier <qualifier> <number comparator>

```

You must include the `destroutingaddr` parameter. The `<category>` parameter is one of:

```

unknowncategory
operatorfrench
operatorenglish
operatorgerman
operatorrussian
operatorspanish
ordinarycallingsubscriber
callingsubscriberwithpriority
datacall
testcall
payphone

```

The `<qualifier>` parameter is either an integer value or one of the following:

```

additionalCalledNumber
additionalConnectedNumber
additionalCallingNumber
additionalOriginalCalledNumber
additionalRedirectingNumber
additionalRedirectionNumber

```

### **connectGprs**

This operation is available for GPRS handling. When establishing a PDP context, it modifies the Access Point Name. This operation has the following format:

```

connectGprs
gprsAccessPointName <string>
[ gprsPdpId <integer> ]

```

### **connecttoresource**

On receipt from the GSM SCF, this operation connects the IP to the incoming call. This operation has the following format:

```

connecttoresource
[ legid <integer> ]
[ address <digits> ]

```

If no address is specified, the received operation must have none indicated for its `resourceAddress` tag. If an address is specified, it must match the address in the `ipRoutingAddress` tag.

### **continue**

This operation requests the SSF to proceed with call processing at the detection point (DP) where it previously suspended call processing to wait for instructions from the SCF. This operation has the following format and no parameters:

```

continue

```

**continueGprs**

This operation is available for GPRS handling. It requests the GPRS SSF to proceed with the GPRS session or context processing at the detection point (DP) where it previously suspended processing to wait for instructions from the GSM SCF. It has the following format:

```
continueGprs [ gprsPdPid <integer> ]
```

The release cause must be between 0 and 255 inclusive.

**continueSms**

This operation requests the SMS SSF to proceed with processing at the detection point (DP) where it previously suspended processing to wait for instructions from the GSM SCF. It is available for CAMEL handling and it has no parameters.

```
continueSms
```

**continewithargument**

This operation requests the GSM SSF to proceed with call processing at the detection point (DP) at which it previously suspended call processing to wait for instructions from the GSM service control function. It also provides additional service-related information to the called party or the calling party while call processing proceeds.

Parameters that are provided in the operation replace the corresponding signalling parameters in the call control function (CCF) and are used in subsequent call processing. Parameters that are not replaced by the operation retain their value in the CCF for subsequent call processing. This operation is available for INAP level 2 (CS-2) handling and has the following format:

```
continewithargument [<parameters>]
```

The `continewithargument` operation can have the following parameters:

```
legId <integer>  
cap4CallSegmentId  
cap4LegId <integer>
```

Use either the `legId` parameter or use the `cap4CallSegmentId` and the `cap4LegId` parameters. For CAP4 protocols, use the `cap4CallSegmentId` and the `cap4LegId` parameters. The `legId` parameter is not valid for CAP4 protocols.

**cs1InitiateCallAttempt**

This operation requests the SSF to initiate a CS1 call attempt. Although it can produce errors, it has no returned result. It has the following format:

```
cs1InitiateCallAttempt [<parameters>]
```

A `cs1InitiateCallAttempt` operation can have any of the following parameters, in any order:

```
callingpartynumber ,number comparator.  
callingpartyscategory <integer> | callingpartyscategory <category>  
destroutingaddr <number comparator>
```

**disconnectforwardconnection**

This operation is used in two cases: 1) To disconnect a connection to a specialized resource function (SRF) and 2) to clear a connection to an assisting SSF. In the first case,

it disconnects a forward connection from the SSF. In the second case, it disconnects the temporary connection between the initiating SSF and the assisting SSF and between the assisting SSF and its associated SRF. The operation has the following format with no parameters:

```
disconnectforwardconnection
```

### **disconnectforwardconnectionwithargument**

This operation is available for INAP level 2 (CS-2) handling.

```
disconnectforwardconnectionwithargument partytodisconnect legid <integer>
```

The `partytodisconnect` parameter with the `legid` variant is the only supported parameter for this operation.

### **disconnectleg**

This operation is available for INAP level 2 (CS-2) handling. It requests the GSM SSF to release a leg associated with the call. Other legs are retained.

```
disconnectleg reason <cause comparator> [legid <legid> | ( <integer> )]
```

Please see the description of "[releasecall](#)" for the possible values for the `reason` parameter. See the description of "[eventreportbcs](#)" for a description of the possible values for `legid`.

### **establishtemporaryconnection**

This operation creates a connection to a resource for a limited period of time to play an announcement or collect information and so on. It has the following format and parameter:

```
establishtemporaryconnection address <digits>
```

The `address` parameter, which is a string in double quotes, is mandatory.

### **furnishcharginginformation**

This operation requests the SSF to generate or register a call record or to include some information in the default call record. This operation has no parameters:

```
furnishcharginginformation
```

---

**Note:** Increasing the output level causes the parameters of the received operation to be written out even though the **slpit** utility does not check them.

---

### **mergecallsegments**

This operation is available for INAP level 2 (CS-2) handling. It has the following format and mandatory parameters

```
mergecallsegments sourcecallsegment <integer> targetcallsegment <integer>
```

### **moForwardSmResult**

This operation is available for MAP handling. It has no parameters:

```
moForwardSmResult
```

**mtForwardSmResult**

This operation is available for MAP handling. It has no parameters:

```
mtForwardSmResult
```

**playannouncement**

This operation is used for in-band interaction with an analog user or for interaction with an Integrated Services Digital Network (ISDN) user. It has the following format and parameters:

```
playannouncement
    [connectedparty <integer>]
    annid <integer comparator> [, <integer comparator>...]
    [variableparts <parts>]
```

If you include the `variableparts` parameter, you must include one or more of the part value specifiers:

```
price <integer> <integer>
digits <digits>
time <integer> <integer>
date <integer> <integer> <integer>
integer <integer>
```

These correspond to the obvious sub-tags in the `variableparts` parameter of the outgoing operation. The price specifier should have two integer parameters giving dollars (or big currency unit) and cents (or little currency unit) respectively. You specify the time value in hours and minutes and the date value as day of the month, month number (1-12), and year (0-99).

**prearrangedend**

This operation has no parameters. It expects the other side of the dialog to send the fake TCAP primitive `TCAP_PRE_END`.

```
prearrangedend
```

**promptandcollectuserinformation**

This operation interacts with a user to collect information. It has the following format and parameters:

```
promptandcollectuserinformation
    annid <integer comparator> [, <integer comparator>...]
    [minnumberofdigits <integer>]
    maxnumberofdigits <integer>
    [<digit parameter>...]
    [variableparts <part> [<part>...]]
```

You can use the following specifiers for `digit` parameter in any order:

```
endofreplydigit <digits>
canceldigit <digits>
startdigit <digits>
interdigittimeout <integer>
firstdigittimeout <integer>
```

If you include the `variableparts` parameter, you must specify one or more of the following part value specifiers. See the description of ["playannouncement"](#) for more information.

**readyForSMResult**

This operation is available for MAP handling. It has no parameters:

```
readyForSMResult
```

**releasecall**

This operation causes the SCF to terminate an existing call at any phase for all parties. It has the following format and one parameter:

```
releasecall reason <cause comparator>
```

You can specify an integer for the `reason` parameter or one of the following names:

```
unalloc_num
norm_call_clr
user_busy
no_user_resp
no_answer
call_rejected
num_changed
out_of_order
inval_num_fmt
normal
temp_failure
```

**releaseGprs**

This operation causes the GSM service control function (SCF) to terminate an existing GPRS Session or PDP context at any phase. It is available for GPRS handling and it has the following format:

```
releaseGprs gprsReleaseCause <integer> [ gprsPdpId <integer> ]
```

**releaseSms**

This operation causes the GSM (SCF) to terminate a short message submission attempt or short message delivery attempt and is allowed only within a control relationship. It is available for CAMEL handling and has the following parameter:

```
releaseSms reason <integer comparator>
```

**reportSMSDeliveryStatusResult**

This operation is available for MAP handling:

```
reportSMSDeliveryStatusResult [<parameters>]
```

A `reportSMSDeliveryStatusResult` operation must have the following parameter:

```
msisdn <number expression>
```

**requestreportbcsmevent**

This operation causes the SSF to monitor for call-related BCSM events such as busy or no-answer and notify the SCF when one is detected. This operation has the following format:

```
requestreportbcsmevent [<event>...]
```

A `requestreportbcsmevent` must have one or more event descriptions:

```
eventtypebcsml <type> [monitormode <mode>] [legid <legid> | ( <integer> )]
[dbspecificcriteria <criteria>]
```

The value of `legid` must be one of the following:

```
[sendingsideid] <legtype>
[receivingsideid] <legtype>
```

The value of `criteria` must be one of the following:

```
numberofdigits <integer comparator>
applicationtimer <integer comparator>
```

For example:

```
eventTypeBCSM oNoAnswer (2) dpspecificcriteria applicationTimer 20
```

### **requestReportGprsEvent**

Causes the GSM SCF to request the GPRS SSF to monitor for a GPRS session event or a PDP context event, such as establish or detach, and to notify the GSM SCF when one is detected. You can request monitoring of more than one event in a single operation but each one will be reported in a separate `EventReportGPRS` operation. This operation has the following format:

```
RequestReportGprsEvent gprsEventType <number> [ gprsPdpId <integer> ]
```

### **requestReportSmsEvent**

Causes the GSM service control function to request the SMS SSF to monitor for a short message related event such as failure, delivery, or submission, and to notify the GSM SCF when it detects one. You can request monitoring of more than one event with a single operation but each event will be reported in a separate `EventReportSMS` operation. This operation is available for CAMEL handling and has the following format.

```
eventTypeSms [ smsFailure | smsSubmitted ]
```

### **resettimer**

This operation causes the SCF to refresh the `tSSF` application timer to avoid the `tSSF` time-out at the service SSF. This operation supports only one parameter, `timervalue`. You cannot specify the timer ID and it is not checked in the received operation. It defaults to `tSSF`.

```
resettimer timervalue <integer>
```

### **returnError**

The operation has the following format:

```
returnError|tcapError [invokeID <integer>] errorCode <integer>
```

The `returnError` operation and the `tcapError` parameter operation are synonymous. If you specify `invokeID`, it must match the response. Otherwise, the returned `invokeID` is not checked. In the **slpit** script, calls start with an `invokeID` of 0 and the value is increased by 1 for each subsequent call.

### **sendcharginginformation**

This operation instructs the SSF on the charging information to be sent. No parameters are supported for this operation and the received content is not validated.

```
sendcharginginformation
```

**sendRoutingInfoForSmResult**

This operation is available for MAP handling and has the following format and parameters:

```
sendRoutingInfoForSmResult [ imsi <number comparator> ] [ nnn <number comparator> ]
```

**sendRoutingInformationResult**

This operation is available for MAP handling and has the following format and parameters:

```
sendRoutingInformationResult [ imsi <number comparator> ]
[ nnn <number comparator> ]
```

**splitleg**

This operation causes the GSM SCF to request the GSM SSF to separate one party from the source call segment and place it in a new target call segment. This operation is available for INAP level 2 (CS-2) handling and has the following format and parameters.

```
splitleg legtobesplit <integer> newcallsegment <integer>
```

**tcapError**

This operation has the following format and parameters:

```
returnError|tcapError [invokeID <integer>] errorCode <integer>
```

The returnError parameter and tcapError parameter are synonymous. If you specify invokeID, it must match the response. Otherwise, the returned invokeID is not checked. In the **slpit** script, calls start with an invokeID of 0 and the value is increased by 1 for each subsequent call.

**unstructuredSSResult**

This operation is available for MAP handling and has the following format and parameters.

```
unstructuredSSResult ussdString <string>
```

The ussdString parameter is the expected parameter in an unstructuredSSResult operation. If you do not specify it, no check is performed. If a check is performed, the string must match the returned string, or the call will be counted in the failed call statistics.

## Example Scripts

This section illustrates the call definition statements in a **slpit** script file for two sample calls: a standard point A to point B call and a call that plays an announcement.

**A Standard Call**

The statements in this example define a standard point A to point B call with one subsequent reservation in which the called party hangs up. This is not a CAMEL call.

```
define call atb_two_periods {
    DN ?= "39421234567"
    CLI ?= "3099440000"

    send {
        initialdp
```

```

        calledpartynumber DN
        callingpartynumber CLI
        callingpartyscategory 10
        locationnumber CLI
        eventtypebcs analyzedinformation
    }

receive {
    applycharging
        thresholdtime any -> threshold
        warningtime threshold - 10

    requestreportbcsmevent
        eventtypebcs omidcall (2)

    requestreportbcsmevent
        eventtypebcs oCalledPartyBusy (2)
        eventtypebcs oNoanswer (2)
        eventtypebcs oabandon (1)
        eventtypebcs RouteselectFailure
        eventtypebcs oDisconnect (2)
        eventtypebcs oDisconnect (1)

    callinformationrequest
        callattemptElapsedTime
        callstopTime
        callConnectedElapsedTime
        calledaddress
        releaseCause

    connect
        destroutingaddr DN
}

talktime = threshold

wait 1.0

send {
    eventreportbcs
        eventtypebcs omidcall (2)
}

receive {
    applyCharging
        thresholdtime any -> threshold
        warningtime threshold - 10

    RequestReportBCSMEvent
        eventtypebcs omidcall (2)
    continue
}

talktime = talktime + threshold

wait 1.0

send {
    eventreportbcs
        eventtypebcs odisconnect (2)
}

```



```

        applychargingreport
            thresholdtime 20
            endofcallindicator 1

        callinformationreport
            callattemptelapsedtime 10
            callstoptime "001002000000"
            callConnectedElapsedTime (talktime - 20) * 10
            calledaddress DN
            releasecause 31
    }

    receive {
        releasercall
        reason 31
    }
}

startcall atb_two_periods using once

```

### A Call that Plays an Announcement

The statements in this example define a simple call that requests assistance and plays an announcement.

```

define call assisting_ip_pa {
    SERVICE_NUMBER ?= "555801"

    send {
        initialdp
        calledpartynumber SERVICE_NUMBER
        callingpartynumber "40002000"
        callingpartyscategory 10
        locationnumber "40002000"
        eventtypebcm analyzedinformation
    }

    receive {
        establishtemporaryconnection
        address "1234"
    }

    send {
        assistrequestinstructions
    }

    receive {
        playannouncement
        annid any
    }

    // Might receive the abort any time after sending the SRR.
    allow abort assisting

    send {
        specializedresourcereport
    }

    receive {
        disconnectForwardConnection
    }
}

```

```
        releasecall
        reason normal
    }

    // The abort might not have arrived yet.
    abort open
}
```

---

## Testing IP Interactions with the mipt Utility

This chapter describes how to use the Oracle Communications Network Charging and Control (NCC) **mipt** test utility.

### About the mipt Utility

The **mipt** utility generally tests the sending and receiving of messages over IP, or internet-based protocols, and you can use it to do high load testing. See ["Overview of the mipt Utility"](#) for an overview of **mipt**.

The **mipt** utility processes operations from an input text file rather than a real network. The input text file is called the *script file* and it is a file that you create. In the script file, you add commands and send and receive messages that define the message sequences that you want to test. You can include send and receive messages of the following protocols: Diameter, EMI, M3UA, RADIUS, SMPP, and SUA. The scripting language allows you to define the test sequences. See ["Creating the mipt Script File"](#) for more information.

Depending on the protocol, the **mipt** utility can act as an Application Service Provider (ASP), a Short Message Service Center (SMSC), a RADIUS client, a DIAMETER Credit Control Client, or a DIAMETER Credit Control Server.

See Appendix B, "Supported Protocol Fields for mipt," for the fields that **mipt** supports for each protocol.

You can run multiple instances of **mipt**, acting as ASPs or SMSCs, communicating with each other on the same machine.

### Running the mipt Utility

The **mipt** utility is located in the following directory:

```
/IN/service_packages/TEST_TOOLS/bin
```

### Command Syntax

Use the following command to run the **mipt** utility:

```
mipt {<option> ...} [<file> ... <file>]
```

You can specify the user name, password, host name, and port either on the command line or in the script file.

See ["Command-Line Options"](#) for explanations of the command line options.

When the utility is acting as an ASP you can specify the user name, password, host name, and port number of the SMSC in the script with a statement like the following:

```
connect smpp_asp tcp smschost smscport bind_receiver system_id=username
password=user_password
```

See ["Specifying the Test Sequence"](#) for additional information.

If you specify values both on the command line and in the script, the values you specify in the script override the values you specify on the command line.

## Command-Line Options

The **mipt** utility takes the following command-line options:

### **-A**

Accelerated time (for testing purposes only). Causes **mipt** to ignore any times specified in the script and perform operations as fast as it can

### **-D <var>=<string>**

Assigns a string to a variable.

### **<file>**

You must specify at least one script file on the command line. You can give your script files any name. If you specify multiple script files, **mipt** runs them in parallel. You can specify the script file name as -, in which case **mipt** reads the script from standard input. For example:

```
mipt {<options>} -<<EOF
```

This would be followed by lines of script like you would find in a script file and would be terminated by typing EOF.

See ["Creating the mipt Script File"](#) for more information.

### **-N <var>=<number>**

Assigns a number to a variable.

### **-P <password>**

Specifies the user's password on the host computer.

### **-U <user>**

Specifies the user's login name on the host computer.

### **-V**

Displays **mipt** version number and details about how and when **mipt** was created.

### **-d**

Prints the script file after parsing it, rather than running it.

### **-e**

Exits on error.

### **-l [<log options>]**

Sets logging options. See ["Logging Options"](#) for a list of logging options.

### **-h <host>**

Specifies the name of the host short message service center (SMSC) computer.

**-n <protocol>**

Specifies the network protocol to use if none is specified in the script file.

**-p <port>**

Specifies the port number on the host SMSC computer.

**-q**

Suppresses output to the command window other than errors, stats, and warnings.

**-u latin**

Sets EMI string processing to latin-1 (ISO8859-1).

**-u unicode**

Sets EMI string processing to UTF-8 (default is latin-1).

**-v**

Triggers verbose mode, which displays the packets being sent and received, including the `smpp_bind_transceiver` packet that enables the SMSC to authenticate the connection. The `smpp_bind_transceiver` packet has the following fields:

**Table 3–1** *smpp\_bind\_transceiver packet fields*

Field Name	Default Value
<code>smpp_command_status</code>	0
<code>smpp_sequence_number</code>	1
<code>smpp_password</code>	"PASSWORD"
<code>smpp_system_id</code>	"mipt"
<code>smpp_system_type</code>	"mipt"
<code>smpp_interface_version</code>	0x50
<code>smpp_addr_ton</code>	1
<code>smpp_addr_npi</code>	1
<code>smpp_address_range</code>	""

## Logging Options

You can specify the following logging options with the **-l** command-line option. The default options are error, script, stats, and warning.

You can turn off a default logging option by preceding it with a dash (-).

The logging options are:

**all**

Enable all logging options except for binary and execute.

**binary**

Log binary packet contents as they are sent and received.

**control**

Log control packets as they are sent and received.

**data**

Log data packet contents as they are sent and received.

**error**

Log error messages.

**execute**

Log **mipt** execution at a low level. Use only for development.

**match**

Trace progress of packet matching.

**network**

Log information about the network state.

**-q**

Specify **-q** as shorthand for `-all,error,stats,warning`.

**script**

Log script execution.

**stats**

Print statistics.

**-v**

Enable all logging options except for `binary` and `execute`.

**warning**

Log warning messages.

**werror**

Log an error on any warnings.

## Creating the mipt Script File

The **mipt** script file is a text file that you create to define message sequences that you want to test. You can name the **mipt** script file whatever you like.

---

---

**Note:** The following sections use SMPP examples, using **mipt** as an ASP or SMSC, except for those examples that are specific to other protocols. The syntax and concepts demonstrated in the SMPP examples, however, apply to all protocols.

---

---

## Specifying the Test Sequence

A script consists of the following five basic statements that you specify to create a test sequence.

- `connect <node>`

The `connect` statement specifies the role of the initiating node and initiates the connection with the receiving node.

---

---

**Note:** You can also specify the host name, port name, user ID, and password in the `connect` statement, using the following format:

`connect <node> <protocol> <host> <port> <ID> <password>`

---

---

- `accept <node>`

The `accept` statement specifies the role of the receiving node and accepts a connection request.

- `send <message>`

The `send` statement sends a message as defined by `<message>`.

- `receive <message>`

The `receive` statement defines the expected short message response in `<message>`.

- `end`

The `end` statement defines the end of a repeat block and also defines the end of the test message script and causes **mipt** to disconnect. Its absence results in a syntax error.

### Reserved keywords

The mipt utility supports the following reserved keywords for the `connect` and `accept` statements:

- `emi_asp`
- `emi_smsg`
- `m3ua_asp`
- `m3ua_sgp`
- `diameter_raw`
- `diameter_cooked`
- `diameter_agent`
- `smpp_asp`
- `smpp_smsg`
- `sua_asp`
- `sua_sgp`

## Using mipt as an ASP or SMSC

The **mipt** utility can run as either the ASP or the SMSC. The first line of the script specifies the role that **mipt** plays. For example, the following line indicates that **mipt** is acting as an ASP and is ready to send messages to an SMSC and receive messages from it.

```
connect smpp_asp
```

The following line specifies that **mipt** is acting as an SMSC and is ready to receive messages from ASPs.

```
accept smpp_smsg
```

The following example shows a sample test script with SMPP messages, one sent and one received. This script simulates an ASP that sends a message to an SMSC and waits for it to be accepted.

```
connect smpp_asp

send submit_sm
    source_addr = "0274022020"
```

```
destination_addr = "0274022023"
short_message = octets "Hello World"

receive submit_sm_resp
command_status = 0          # Expect success

end
```

## Sending Multiple Messages

Typically, an ASP script will keep the connection open and send multiple messages, as seen in the following script:

```
connect smpp_asp

send submit_sm
source_addr = "0274022020"
destination_addr = "0274022023"
short_message = octets "Hello World"

receive submit_sm_resp
command_status = 0          # Expect success.

send submit_sm
source_addr = "0274022020"
destination_addr = "0274022023"
short_message = octets "I'm still here"

receive submit_sm_resp
command_status = 0          # Expect success.

end
```

To handle multiple messages on the SMSC, you must create a loop. For example:

```
accept smpp_smsc
repeat
    receive submit_sm
    send submit_sm_resp
end
end
```

The repeat statement specifies that the set of statements before the first end statement will repeat indefinitely until a message causes the SMSC to disconnect from the ASP. The first end statement specifies the end of the statements to be repeated, that is, the end of the loop. The second end statement terminates the script.

See "[Controlling Loops](#)" for more information about controlling loops.

## Rejecting Messages

You might not want to accept all messages. The following script segment rejects messages that contain the word *bad*:

```
accept smpp_smsc
repeat
    receive submit_sm
    short_message = octets "bad"
    send submit_sm_resp
    command_status = 1 # Failure
end
```



## Using Variables

You can use variables to save values while the script is running. The following SMSC script saves the `message_id` field in `query_sm` to a variable named `$MID` and then uses it to set `message_id` in the `query_sm_resp` operation:

```
receive query_sm
    message_id -> $MID
send query_sm_resp
    message_id = $MID
    final_date = "2005071815234500Z"
    message_state = 1
    error_code = 0
```

---

---

**Note:** The **mipt** utility has many reserved words and using a reserved word as a variable name will result in an error. If you prefix your variable name with a \$, you can avoid conflicts with reserved words.

---

---

## Controlling the Message Flow

The **mipt** utility provides several statements that enable you to control the flow of messages in the script.

### Providing an Alternate Flow

The following script example uses the `or` statement to direct the flow to an alternate path if a message does not meet a specific condition:

```
accept smpp_smsg
    repeat
        receive submit_sm
            short_message = octets "bad"
        send submit_sm_resp
            command_status = 1 # Failure

    or

        receive submit_sm
        send submit_sm_resp
    end
end
```

### Controlling the Processing Sequence

When you send two messages at the same time, the replies could arrive out of order. The following is an example of sending two messages:

```
send submit_sm
    source_addr = "0274022020"
    destination_addr = "0274022023"
    short_message = octets "bad"

send submit_sm
    source_addr = "0274022020"
    destination_addr = "0274022023"
    short_message = octets "good"

receive submit_sm_resp
    command_status = 0 # success
```

```
receive submit_sm_resp
    command_status != 0 # failure
```

In this case, you do not know the order in which the replies will come so either response could be handled incorrectly as a success or a failure.

You can use the `and` operation to send two messages at the same time and ensure that the results are processed in the correct sequence. In the following example, the `and` operation allows you to send two statements at the same time and associate the receive operations with the correct send operations:

```
begin
    send submit_sm
        source_addr = "0274022020"
        destination_addr = "0274022023"
        short_message = octets "bad"
    receive submit_sm_resp
        command_status != 0 # failure
and
    send submit_sm
        source_addr = "0274022020"
        destination_addr = "0274022023"
        short_message = octets "good"
    receive submit_sm_resp
        command_status = 0 # success
end
```

The `begin` and `end` keywords define the scope of the `and` operation. In this case, the first receive operation will match only the first send operation, and the second receive operation will match only the second send operation.

The SMSC should be able to respond to `query_sm` requests as well as `submit_sm` requests. The following example uses the `and` operation to run two loops in parallel to respond to both `query_sm` and `submit_sm` requests:

```
begin
    repeat
        receive query_sm
            message_id -> MID
        send query_sm_resp
            message_id = MID
            final_date = "2005071815234500Z"
            message_state = 1
            error_code = 0
    end
and
    repeat
        receive submit_sm
        send submit_sm_resp
    end
end
```

### Controlling Loops

You can add options to the `repeat` operation to specify a rate or time that controls how many times or how long a loop will continue. For example, **mipt** does not know when to stop the following loop, which continuously sends `enquire_link` operations from the ASP to the SMSC:

```
repeat
```

```

    send enquire_link
    receive enquire_link_resp
    sleep 1 # Wait a second
end

```

You can limit how long a loop will repeat by specifying a time limit after which it will stop. The following loop repeats for up to 10 seconds:

```

repeat for 10 seconds
    send enquire_link
    receive enquire_link_resp
    sleep 1 # Wait a second.
end

```

You can also repeat the loop at a particular pace by specifying a rate of hertz, which is one iteration per second. The following example repeats the loop at a uniform distribution of 2 hertz for a duration of 10 seconds:

```

repeat uniform 2 hertz for 10 seconds
    send enquire_link
    receive enquire_link_resp
end

```

You can also specify intervals instead of frequencies. In this example, uniform 0.5 seconds means one iteration every 0.5 seconds, which is equal to 2 hertz:

```

repeat uniform 0.5 seconds for 10 seconds
    send enquire_link
    receive enquire_link_resp
end

```

You can also ramp the rate up and down gradually. This example ramps up the rate from 0 to 10 hertz over a period of 5 seconds and then holds it at 10 hertz for a period of 6 seconds:

```

repeat uniform (5 seconds) 10 hertz for 6 seconds
    send enquire_link
    receive enquire_link_resp
end

```

This example ramps up the rate and then switches rates twice:

```

repeat poisson 10 hertz (10 seconds) 20 hertz ( ) 1000 hertz (100 iterations)
    1000 hertz ( ) 1 hertz for 20 seconds

```

This statement has the following effect on the loop:

- Uses a Poisson distribution model
- Ramps up from 10 hertz to 20 hertz over 10 seconds
- Switches to 1000 hertz for an average of 100 iterations, 1 iteration every 0.001 second for about 0.1 seconds
- Switches back to 1 hertz
- Runs for a total of 20 seconds

The following example demonstrates the implicit flow control in a **mipt** script. It sends messages as fast as possible until an error is returned:

```

send submit_sm
    source_addr = "0274022020"
    destination_addr = "0274022023"

```

```

        short_message = octets "spam"

    repeat
        receive submit_sm_resp
        command_status = 0 // OK
        send submit_sm
        source_addr = "0274022020"
        destination_addr = "0274022023"
        short_message = octets "spam"
    end

    receive submit_sm_resp
    command_status != 0 // OK

```

The fields and values within the receive section, such as `command_status = 0`, specify the expected values. If the actual value received does not match the expected value, **mipt** generates an Unmatched packet error, which would terminate the loop in this case.

## Using the RADIUS Protocol

The following example of a **mipt** script for the RADIUS protocol simulates a short prepaid billing session. The connect statement specifies the RADIUS protocol. The name of the script file can be anything.

```

connect radius_raw udp 'radius-server-hostname' 1812 packet radius_secret = octets
"SECRET"

    # Initial request for quota allocation
    send access_request
        user_name = '0219393571'
        radius_correlation_id = '12345678'
        nas_identifier = '12345'
        PPAC = {
            PPAC__select_for_session = octets 00 00 00 10 #Duration accounting
        }

    # Assume successful response and a quota allocated
    receive access_accept

    # Wait 10 seconds before disconnecting
    sleep 10

    # User disconnects
    send access_request
        radius_correlation_id = '12345678'

        radius_service_type = 17 # 'Authorize only', i.e. this is an "on-line"
Access-Request

        PPAQ = {
            PPAQ__quota_identifier = 1
            PPAQ__duration_quota = 10
            PPAQ__update_reason = octets 00 06 # Client Service termination
        }

    # Acknowledgement from the radius server
    receive access_accept

end

```

## Using mipt as a Diameter Client or Server

You can send Diameter messages over either a transmission control protocol (TCP) transport or a stream control transmission protocol (SCTP) transport. This section describes how to create a connection as a Diameter client and how to listen for a connection as a Diameter server, as well as how to send an error message.

See [Appendix B, "Supported Protocol Fields for mipt,"](#) for a list of fields that the **mipt** utility supports for the Diameter protocol.

### Connecting as a Diameter Client

Use the following format of the connect message to create a connection as a Diameter client in raw mode:

```
connect diameter_raw <protocol> <hostname> <port>
```

For example, the following connect statements establish Diameter client connections for the TCP and SCTP protocols, respectively:

```
connect diameter_raw tcp my_host 3868
connect diameter_raw sctp my_host 3868
```

You can also create a connection using cooked or agent mode, which have the following formats:

```
connect diameter_cooked <protocol> <hostname> <port>
connect diameter_agent <protocol> <hostname> <port>
```

There is no difference between cooked and raw mode when **mipt** is running as a Diameter client. When **mipt** is running as a Diameter server and using cooked mode, it automatically responds to Device-Watchdog-Request messages so that you do not need to handle them explicitly in the script.

The agent mode is similar to cooked mode except that it automatically performs a basic Capabilities-Exchange at the beginning of the connection.

The following script example connects to a Diameter server, performs a basic Capabilities-Exchange, sends a Credit-Control-Request (CCR) message, and waits for the answer:

```
connect diameter_agent 'server-hostname' 3868

send CCR
    end_to_end_identifier = 55
    session_id = 'session id oh yeah'
    origin_host = 'host.example.com'
    origin_realm = 'host.example.com'
    destination_realm = 'host.example.com'
    auth_application_id = 1
    service_context_id = 'service context id woohoo'
    cc_request_type = 0
    cc_request_number = 1
    cost_information = {
        unit_value = {
            value_digits = -1000
            exponent = -20
        }
    }
    currency_code = 888
    cost_unit = 'Polish Zlotys'
```

```
    }

    receive CCA
        end_to_end_identifier = 55

end
```

### Accepting a Connection as a Diameter Server

When **mipt** is running as a Diameter server, use the following format to listen for and accept a connection:

```
accept diameter_raw <protocol> <port>
```

The value of `<protocol>` is either TCP or SCTP and `<port>` is the port number to which **mipt** is listening.

### Sending a Diameter Error Message

You can send a Diameter error message by sending an answer message and explicitly setting the error bit in the `command_flags` field, as shown in the following example:

```
send CCA
    command_flags = 0x20 # Error bit
    session_id = 'session id oh yeah'
    error_message = 'Error #12345'
```

---

## Testing Messaging with the SMSC Test Tool

This chapter describes how to configure and use the Oracle Communications Network Charging and Control **smsc** test tool.

### About the **smsc** Test Tool

The **smsc** test tool emulates various parts of the short message service (SMS) messaging environment, including a Short Message Service Center (SMSC), Visitor Mobile Switching Center (VMSC), and Home Location register (HLR). You use the utility to test the sending and receiving of SMS messages. See ["Overview of the \*\*smsc\*\* Test Tool"](#) for an overview of **smsc**.

The **smsc** test tool attaches to the SLEE as a TCAP interface and handles both MAP and IS-41 incoming short message requests. It can simulate an SMSC by sending an MO ForwardSM operation, an HLR by sending an SendRoutingInfoForSM operation, or an MSC by sending an MT ForwardSM operation at MAP levels 1-3. The responses to each method are defined in a configuration file. Selection of functionality is automatic, depending on which type of operation the test tool receives.

### Running the **smsc** Test Tool

The **smsc** test tool is located in the following directory:

```
/IN/service_packages/TEST_TOOLS/bin/smsc
```

The **smsc** test tool runs as a SLEE interface when you start the SLEE; therefore, starting the SLEE starts **smsc**. You must have configured the **smsc** test tool and configured the SLEE for **smsc** before **smsc** will run. See ["Configuring SLEE for \*\*smsc\*\*"](#) for information about configuring the SLEE.

The **smsc** test tool redirects its output to a log file. The log file is written to the `/IN/service_packages/TEST_TOOLS/tmp/smsc.log` file.

Before starting the SLEE, set the following environment variables for **smsc**:

- **ESERV\_CONFIG\_FILE**  
Optional. Set to the location of the **eserv.config** file, which contains the XMS configuration. Defaults to `/IN/service_packages/etc/eserv.config`.
- **SMSC\_CONFIG\_FILE**  
Set to the location of the **smsc.cfg** file, which defines the SMSC responses to incoming messages. The following example illustrates a setting of the **SMSC\_CONFIG\_FILE** environment variable:

```
SMSC_CONFIG_FILE=/IN/service_packages/TEST_TOOLS/etc/smsc.cfg
```

```
export SMSC_CONFIG_FILE
```

- **DEBUG**

Set to `fred_smsc` to obtain useful information about what **smsc** is doing.

---

**Note:** If this variable is set to `all`, every SLEE program writes out debugging information, which is usually not desirable due to the volume of information, most of which is not meaningful for **smsc**.

---

## Configuring SLEE for smsc

To configure the Service Logic Execution Environment (SLEE) for SMSC, you must include the following parameters in the **slee.cfg** file:

- **SERVICEKEY=INTEGER 42 SMSCINT**
- **INTERFACE=Timer timerIF /IN/service\_packages/SLEE/bin EVENT**
- **INTERFACE=SMSCINT smsc </path/to/the\_smsc> EVENT**

The following example highlights these parameters in an excerpt from the **slee.cfg** file.

```
# Standard SLEE definitions...
# (MAXAPPLICATIONS, MAXDIALOGS, etc)
WATCHDOG=/IN/service_packages/SLEE/bin/ watchdog
WATCHDOGCYCLETIME=3000
SERVICEKEY=INTEGER 101 xmsIf
SERVICEKEY=INTEGER 42 SMSCINT
SERVICE=ACS 1 slee_acs ACS
INTERFACE=Timer timerIF /IN/service_packages/SLEE/bin EVENT
INTERFACE=SMSCINT smsc </path/to/the_smsc> EVENT
INTERFACE=xmsIf xmsTrigger.sh /IN/service_packages/XMS/bin EVENT
APPLICATION=slee_acs slee_acs /IN/service_packages/ACS/bin 1 1
```

Other parameters listed here, which are important to running SLEE, are described in *Service Logic Execution Environment Technical Guide*.

## Configuring the smsc Test Tool

Configuring the **smsc** test tool consists of adding configuration parameters to the **smsc.cfg** file, which is in the `/IN/service_packages/TEST_TOOLS/etc` directory by default. You can specify a different location for the file by setting the `SMSC_CONFIG` environment variable.

You add parameters to the **smsc.cfg** file based on the testing that you want to do. Configuring the **smsc** test tool can include the following tasks:

- [Configuring General Parameters](#)
- [Configuring for CAP3 GPRS](#)
- [Configuring for MAP](#)
- [Configuring for MAP as HLR](#)
- [Configuring for IS-41](#)
- [Configuring for IS-41 as HLR](#)



## Configuring General Parameters

The following parameters apply to the **smsc** test tool rather than a particular protocol.

Set the following parameters in the **smsc.cfg** file to specify a sleep time and a request delay range.

### Protocol

Deprecated.

---

---

**Note:** The Protocol parameter formerly specified the protocol ("map" or "is41") to be used. However, the **smsc** test tool currently determines the protocol based on the incoming message.

---

---

### requestDelayRangeStart

The requestDelayRangeStart and requestDelayRangeEnd parameters specify a range in seconds by which responses are delayed. The delay is randomly selected from within the specified range.

Specifies the start of the delay range.

Allowed Values:	Zero or a positive integer
Units:	Seconds
Default:	0
Example:	requestDelayRangeStart = 0

### requestDelayRangeEnd

Specifies the end of the delay range.

Allowed Values:	Zero or a positive integer
Units:	Seconds
Default:	0
Example:	requestDelayRangeEnd = 0

### sleepTime

Specifies the sleep time between event polls when idle.

Allowed Values:	Zero or a positive integer
Units:	milliseconds
Default:	200
Example:	sleepTime = 200

## Configuring for CAP3 GPRS

You can use the SMSC test tool to perform one CAP3 GPRS operation, ActivityTestGPRS.

Use the following parameters in the **smc.cfg** file to perform an **ActivityTestGPRS** operation for the CAP3 GPRS protocol. This operation tests whether a relationship exists between the **gsmSCF** and **gprsSSF**. If so, the **gprsSSF** replies.

### **CAP3DestinationReferenceRange**

Optional. Specifies an array of Destination Reference patterns and associated behaviors.

```
CAP3DestinationReferenceRange = [
  {
    pattern = ""
    responses = [
      {
        reply = true | false
        delay = <seconds>
      }
      ...
    ]
  }
  ...
]
```

You set the following values in the **CAP3DestinationReferenceRange** parameter.

#### ■ **delay**

Mandatory for an entry in the responses array of **CAP3DestinationReferenceRange**. Specifies in seconds the length of time to delay the response.

Allowed Values:	Zero or a positive integer
Unit:	seconds
Default:	30
Example	delay = 30

#### ■ **pattern**

Mandatory for entry in the **CAP3DestinationReferenceRange** array. Specifies a regular expression as understood by the UNIX **grep** command.

Allowed Values:	A string that specifies a pattern as understood by the UNIX <b>grep</b> command.
Default:	""
Example:	pattern = 95.* (matches any destination reference beginning with a 95. pattern. The * specifies a match for any value following the 95. value.)

#### ■ **reply**

Mandatory for entry in the **CAP3DestinationReferenceRange** array. Specifies whether to reply to an **ActivityTestGPRS** operation sent by the **gsmSCF**.

Allowed Values:	true or false
Default:	true
Example:	reply = true

### ■ responses

Mandatory for an entry in the CAP3DestinationReferenceRange array. Specifies an array of responses, each of which specifies a reply of true or false and a delay in seconds.

Allowed Values:	An array in which each entry consists of a boolean value and a number of seconds.
Default:	[true, 30]
Example:	response = [{true, 30}, {false, 20}];

## Configuring for MAP

To use the MAP protocol, set the appropriate parameters in the **smc.cfg** file.

### AbortRequest

Deprecated. Setting AbortRequest to true is equivalent to Action = ABORT.

Allowed Values:	true or false
Default:	false
Example:	AbortRequest = false

### Action

Specifies the action to take when a message is received. These values override IgnoreRequest, AbortRequest, or FailResponse.

Allowed Values:	<ul style="list-style-type: none"> <li>■ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>■ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>■ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>■ "NACK", "FAIL_REQUEST", 3 Send a TCAP ReturnError component.</li> <li>■ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> <li>■ "MAP_FALLBACK", "MAP_FALLBACK_REQUEST", 6 Respond to the request with a TCAP ABORT message requesting to fall back to the MAP version specified by fallbackVersion.</li> <li>■ "CANCEL", "CANCEL_REQUEST", "TCAP_CANCEL", 7 Respond to the request with a TCAP CANCEL message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	Action = "NACK"

### altAction

Used instead of Action for the percentage of time specified by altPercentage.

Allowed Values:	<ul style="list-style-type: none"> <li>■ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>■ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>■ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>■ "NACK", "FAIL_REQUEST", 3 Send a TCAP ReturnError component.</li> <li>■ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> <li>■ "MAP_FALLBACK", "MAP_FALLBACK_REQUEST", 6 Respond to the request with a TCAP ABORT message requesting to fall back to the MAP version specified by fallbackVersion.</li> <li>■ "CANCEL", "CANCEL_REQUEST", "TCAP_CANCEL", 7 Respond to the request with a TCAP CANCEL message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	altAction = "ACKNOWLEDGE_REQUEST"

**altPercentage**

Specifies the percentage of time to use altAction instead of Action

Allowed Values:	An integer between 0 and 255
Default:	0
Example:	altPercentage = 0

**FailOpid**

The error code to put in a TCAP ReturnError.

Allowed Values:	Zero or a positive integer.
Default:	32 (sm-DeliveryFailure))
Example:	FailOpid= 32

**FailCause**

The value that specifies the cause in a ReturnError message when the error code is 32 (sm-DeliveryFailure).

Allowed Values	Zero or a positive integer. Sensible values: 0 (memoryCapacityExceeded) 1 (equipmentProtocolError) 2 (equipmentNotSM-Equipped) 3 (unknownServiceCenter) 4 (sc-Congestion) 5 (invalidSME-Address) 6 (subscriberNotSC-Subscriber)
Default:	32 (which is not meaningful)
Example:	FailCause = 0

### FailResponse

Deprecated. Setting FailResponse to true is equivalent to Action = "NACK".

Allowed Values:	true or false
Default:	false
Example:	FailResponse = false

### fallbackVersion

Specifies the value when Action is MAP\_FALLBACK. This is the MAP version to put in the TCAP ABORT message when MAP fallback is requested.

Allowed Values:	1, 2, or 3
Default:	1
Example:	fallbackVersion = 1

---

**Note:** While this chapter and the **smsc.cfg** file refer to MAP version 3, its official name is MAP phase 2+.

---

### IgnoreRequest

Deprecated. Setting IgnoreRequest to true is equivalent to Action = "IGNORE".

Allowed Values:	true or false
Default:	false
Example:	IgnoreRequest = false

### MapVersion

Specifies the MAP version to support. SMC or SMSC requests that use a higher version are aborted (TCAP\_ABORT) and **smsc** requests a fallback to this version, regardless of the value of the Action parameter.

---

**Note:** While this chapter and the **smmc.cfg** file refer to MAP version 3, its official name is MAP phase 2+.

---

Allowed Values:	1, 2, or 3
Default:	1
Example:	MapVersion = 3

### **moreMessages**

If true, the **smmc** test tool sends the MAP result in a TCAP\_CONTINUE message, leaving the TCAP dialog open. If false, the **smmc** test tool sends the MAP result in a TCAP\_END message, ending the TCAP dialog.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

### **RECEIVED\_SMS\_STATUS\_REPORT**

Specifies the Action and FailOpId to use when processing messages that contain an SMS Status Report.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

### **SEND\_USSD\_MAP\_ERROR\_VALUE**

The error code to put in a TCAP ReturnError message for a MAP UNSTRUCTURED\_SS\_NOTIFY or PROCESS\_UNSTRUCTURED\_SS operation.

Allowed Values:	Zero or a positive integer
Default:	1
Example:	SEND_USSD_MAP_ERROR_VALUE = 1

### **SEND\_USSD\_PROCESS\_UNSTRUCTURED\_SS\_RESPONSE**

Specifies the action to take on receipt of a MAP\_PROCESS\_UNSTRUCTURED\_SS operation.

Allowed Values:	0 Send a TCAP ReturnError 1 Send a TCAP ReturnResult 2 Do nothing
Default:	1
Example:	SEND_USSD_PROCESS_UNSTRUCTURED_SS_RESPONSE = 1

### **SEND\_USSD\_SS\_NOTIFY\_RESPONSE**

Specifies the action to take on receipt of a MAP\_UNSTRUCTURED\_SS\_NOTIFY operation.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

### TCAP\_ABORT\_cause

Specifies the cause (p-abortCause) to put in a TCAP ABORT message.

Allowed Values:	An integer between 0 and 255. Meanings for commonly used values include: <ul style="list-style-type: none"> <li>■ unrecognizedMessageType (0)</li> <li>■ unrecognizedTransactionID (1)</li> <li>■ baadlyFormatteTransactionPortion (2)</li> <li>■ incorrectTransactionPortion (3)</li> <li>■ resourceLimitation (4)</li> </ul>
Default:	0
Example:	TCAP_ABORT_cause = 0

### Example MAP Configuration

The following example illustrates the **smsc** configuration parameters for MAP in the **smsc.cfg** file:

```
# smsc.cfg
SMSC = {
    ...
    MAP = {
        moreMessages = False
        MapVersion = 3
        IgnoreRequest = False
        AbortRequest = False
        FailResponse = False
        Action = "ACKNOWLEDGE_REQUEST"
        TCAP_ABORT_cause = 0
        altAction = "ACKNOWLEDGE_REQUEST"
        altPercentage = 0
        FailOpid = 32
        FailCause = 32
        fallbackVersion = 1
        SEND_USSD_SS_NOTIFY_RESPONSE = 1
        SEND_USSD_PROCESS_UNSTRUCTURED_SS_RESPONSE = 1
        SEND_USSD_MAP_ERROR_VALUE = 1
        RECEIVED_SMS_STATUS_REPORT = {
            Action = "ACKNOWLEDGE_REQUEST"
            altAction = "ACKNOWLEDGE_REQUEST"
            altPercentage = 0
            FailOpid = 32
            FailCause = 32
        }
    }
}
```

## Configuring for MAP as HLR

When Protocol is set to MAP, you can also configure SMSC to respond as an HLR when it receives a SendRoutingInfoForSM message.

---

**Note:** You can enable both SMS and HLR capabilities at the same time.

---

Use the following parameters to configure SMSC as an HLR.

### Action

Specifies the action to take upon receipt of a lookup request. This action supersedes the IgnoreRequest, AbortRequest, and FailResponse parameters.

Allowed Values:	<ul style="list-style-type: none"> <li>■ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>■ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>■ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>■ "NACK", "FAIL_REQUEST", 3 Send a TCAP ReturnError component.</li> <li>■ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> <li>■ "MAP_FALLBACK", "MAP_FALLBACK_REQUEST", 6 Respond to the request with a TCAP ABORT message requesting to fall back to the MAP version specified by fallbackVersion.</li> <li>■ "CANCEL", "CANCEL_REQUEST", "TCAP_CANCEL", 7 Respond to the request with a TCAP CANCEL message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	Action = "ACKNOWLEDGE_REQUEST"

### Address

These are the digits of the MSC number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

Allowed Values:	A string of digits
Default:	empty (do not return an address)
Example:	Address = 12345678

### AddressNature

This is the nature address of the MSC number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.



Allowed Values:	An integer between 0 and 7 Meanings: 0 unknown 1 international number 2 national significant number 3 network specific number 4 subscriber number 5 reserved 6 abbreviated number 7 reserved for extension
Default:	0
Example:	AddressNature = 1

### AddressPlan

This is the indicator of the numbering plan for the MSC number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

Allowed Values:	An integer between 0 and 15 Meanings: 0 unknown 1 ISDN/Telephony Numbering plan (Rec CCITT E.164) 2 spare 3 data numbering plan (CCITT rec X.121) 4 Telex numbering plan (CCITT rec F.69) 5 spare 6 land mobile numbering plan (CCITT Rec E.212) 7 spare 8 national numbering plan 9 private numbering plan 15 reserved for extension
Default:	0
Example:	AddressPlan = 1

### canSendEmptyImsi

Controls what happens if the value of the IMSI parameter is an empty string (" "). If the value of canSendEmptyImsi is true, the IMSI is sent as an empty string. If the value of canSendEmptyImsi is false, the IMSI is constructed of the imsiPrefix value followed by the MSISDN.

Allowed Values:	true or false
Default:	false
Example:	canSendEmptyImsi = false

**Denied**

Deprecated. A value of true is equivalent to Action = "NACK".

Allowed Values:	true or false
Default:	false
Example:	Denied = false

**Enabled**

Deprecated. When true, enables the HLR functions and **sm**sc responds to those messages. A value of false is equivalent to Action = "IGNORE".

Allowed Values:	true or false
Default:	true
Example:	Enabled = true

**Error**

Deprecated. When true, **sm**sc responds to HLR messages with an error code.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

**ErrorCause**

The cause of failure to include in the NACK response, if appropriate to the operation ID.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

**ErrorOpid**

Deprecated. The error code to put in a TCAP ReturnError message.

Allowed Values:	0 or a positive integer
Default:	0, which is undefined and not meaningful.
Example:	ErrorOpid = 1 (unknownSubscriber)

**FailOpid**

The error code to put in a TCAP ReturnError message.

---

---

**Note:** FailOpid overrides the deprecated ErrorOpid parameter.

---

---

Allowed Values:	0 or a positive integer
Default:	0, which is undefined and not meaningful.

Example:	FailOpId = 1 (unknownSubscriber)
----------	----------------------------------

**fallbackVersion**

If the action is FALLBACK\_REQUEST, this value is the version specified in TCAP\_ABORT, assuming that the logic for MapVersion does not apply.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

**GPRSNodeIndicator**

The LocationInfoWithLMSI.gprsNodeIndicator value to put in a MAP2 SEND\_ROUTING\_INFORMATION\_FOR\_SM result.

Allowed Values:	true or false
Default:	false
Example:	GPRSNodeIndicator = true

**hlrAltAction**

Specifies the alternative action to take upon receipt of a lookup request. The hlrAltAction parameter is used instead of the Action parameter for the percentage of time specified by hlrAltPercentage.

Allowed Values:	<ul style="list-style-type: none"> <li>■ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>■ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>■ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>■ "NACK", "FAIL_REQUEST", 3 Send a TCAP ReturnError component.</li> <li>■ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> <li>■ "MAP_FALLBACK", "MAP_FALLBACK_REQUEST", 6 Respond to the request with a TCAP ABORT message requesting to fall back to the MAP version specified by fallbackVersion.</li> <li>■ "CANCEL", "CANCEL_REQUEST", "TCAP_CANCEL", 7 Respond to the request with a TCAP CANCEL message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	hlrAltAction = "ACKNOWLEDGE_REQUEST"

**hlrAltPercentage**

Specifies as a percentage the number of times that **smsc** uses hlrAltAction instead of Action.

Allowed Values:	An integer between 0 and 255
Default:	0
Example:	hlrAltPercentage = 0

### HLRSequence

Optional. This parameter is an array that enables you to configure a different responses for the MAP plugin when using HLR functionality for Status Reports and Submit messages. See ["SMSC Sequence for MAP as HLR"](#) for more information.

### IMSI

The International Mobile Subscriber Identifier (IMSI) to put in the SEND\_ROUTING\_INFORMATION result or SEND\_ROUTING\_INFORMATION\_FOR\_SM result.

Allowed Values:	A string of exactly 16 hex digits
Default:	"" (empty string) See <a href="#">"canSendEmptyImsi"</a> for related information on sending an empty string.
Example:	IMSI = "0123456789ABCDEF"

### imsiPrefix

Specifies the prefix to turn the MSISDN into an IMSI, when the IMSI parameter is empty.

Allowed Values:	A string of between 0 and 15 hex digits
Default:	"" (empty)
Example:	imsiPrefix = "123"

### ISC

MAP 3 only. Specifies whether to follow every ReturnError or ReturnResult message with an INFORM\_SERVICE\_CENTER operation.

Allowed Values:	true or false
Default:	false
Example:	ISC = false

### ISCMwStatus

If non-zero, ISCMwStatus is included as the mw-Status field of the MAP INFORM\_SERVICE\_CENTER operation. Only the following six least-significant bits are valid:

Allowed Values:	An integer between 0 and 63. Only the following six least-significant bits are valid: 0x20 AddressNotIncluded 0x10 mnrf-Set (Mobile Not Reachable Flag) 0x08 mcef-Set (Memory Capacity Exceeded Flag) 0x04 mnrg-Set (Memory Not Reachable for GPRS)
Default:	0.

Example:	ISCMwStatus = 4
----------	-----------------

---

**Note:** You can apply the logical OR operation to these bits. For example, applying a logical OR operation to 0x20 (01 0000) and 0x04 (00 0100) results in 0x24 (01 0100), which means address not included and memory not reachable for GPRS.

---

### ISCSeparate

Specifies whether to send the INFORM\_SERVICE\_CENTER in a separate TCAP message from the TCAP ReturnError message.

Allowed Values:	true or false
Default:	false
Example:	ISCSeparate= false

### ISCStoredMsisdnNoa, ISCStoredMsisdnNpi, ISCStoredMsisdn

If present, is included as the storedMSISDN field of the ISC operation.

Allowed Values:	true or false
Default:	true
Example:	moreMessages = false

### LMSI

Specifies the LMSI to put in the SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

Allowed Values:	A string of exactly 8 hex digits
Default:	empty (do not return an LMSI)
Example:	LMSI = "12345678"

### MapVersion

Specifies the MAP version to use. If the incoming MAP version is higher, SMSC sends a TCAP ABORT message to fall back to this version, regardless of the version specified.

---

**Note:** While this chapter and the **smc.cfg** file refer to MAP version 3, its official name is MAP phase 2+.

---

Allowed Values:	1, 2, or 3
Default:	1
Example:	MapVersion = 1

### SGSN

Specifies the digits of the SGSN number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

Allowed Values:	A string of digits
Default:	empty (do not return an address)
Example:	SGSN= "12345678"

**SGSNNature**

Specifies the nature address of the Service GPRS Support Node (SGSN) number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

On behalf of mobile subscribers, SGSN manages access to network resources and enacts the packet scheduling policy. It also initiates the Packet Data Protocol (PDP) context with the gateway GPRS support node (GGSN).

Allowed Values:	An integer between 0 and 7 Meanings: 0 unknown 1 international number 2 national significant number 3 network specific number 4 subscriber number 5 reserved 6 abbreviated number 7 reserved for extension
Default:	0
Example:	SGSNNature = 1

**SGSNPlan**

Specifies the indicator of the numbering plan of the SGSN number to put in SEND\_ROUTING\_INFORMATION\_FOR\_SM results.

Allowed Values:	An integer between 0 and 15 Meanings: 0 unknown 1 ISDN/Telephony Numbering Plan (Rec CCITT E.164) 2 spare 3 data numbering plan (CCITT Rec x.121) 4 telex numbering plan (CCITT Rec F.69) 5 spare 6 land mobile numbering plan (CCITT Rec E.212) 7 spare 8 national numbering plan 9 private numbering plan 15 reserved for extension
Default:	0
Example:	SGSNPlan = 1

## Example MAP as HLR Configuration

The following example illustrates the **smsc** configuration parameters for MAP when **smsc** acts as an HLR:

```
# smsc.cfg
SMSC = {
    ...
    MAP = {
        ...
        RECEIVED_SMS_STATUS_REPORT = {
            ...
        }
    }
}

# This section describes how the SMSC handles SEND-ROUTING-INFORMATION
# and SEND_ROUTING-INFORMATION-FOR-SM requests.
HLR = {

    Enabled = True
    Denied = False
    Action = "ACKNOWLEDGE_REQUEST"
    MapVersion = 1
    ErrorOpid = 1 # unknownSubscriber
    FailOpid = 1 # unknownSubscriber
    ISC = False
    ISCSeparate = False
    TCAP_ABORT_cause = 0
    ISCStoredMsisdnNoa = 1
    ISCStoredMsisdnNpi = 1
    ISCStoredMsisdn = "12345678"
    ISCMwStatus
    IMSI = "0123456789ABCDEF"
    canSendEmptyImsi = False
    GPRSNodeIndicator
    imsiPrefix = "123"
    AddressNature = 1
    AddressPlan = 1
    Address = "12345678"
    SGSNNature = 1
    SGSNPlan = 1
    SGSN = "12345678"
    LMSI = "12345678"
}
}
```

## SMSC Sequence for MAP as HLR

When Protocol is set to MAP, you can add an **HLRSequence** parameter to configure different responses for the MAP plugin when using HLR functionality for Status Reports and Submit messages. **HLRSequence** is an array where each array element represents a response to a **SEND\_ROUTING\_INFORMATION** or **SEND\_ROUTING\_INFORMATION\_FOR\_SM** request.

Each parameter available for HLR configuration is also available for **HLRSequence**.

The following rules apply to use of the **HLRSequence** parameter:

- If **HLRSequence** has one response, it is used for all responses.
- If **HLRSequence** has more than one response, the first request will be handled according to the first array element, the second request will be handled according

to the second array element, and so on. When the **smsc** test tool reaches the end of the array, it loops back to the beginning of the array.

- If HLRSequence is absent or is present but has no responses, HLR is used for all responses.

The following example illustrates the use of the HLRSequence parameter:

```
SMSC = {
    ...
    MAP = {
        ...
        RECEIVED_SMS_STATUS_REPORT = {
            ...
        }
        # This section describes how the SMSC should handle
        # SEND-ROUTING-INFORMATION and SEND-ROUTING-INFORMATION-FOR-SM requests.
        HLR = {
            ...
        }
        hlrAltAction = "ACKNOWLEDGE_REQUEST"
        hlrAltPercentage = 0
        HLRSequence = [
            {
                # Each of these sections has the same format as the SMSC.MAP.HLR
                # section above.
            }
            ...
            {
            }
        ]
        ...
    }
    ...
}
```

### Map SendUSSDNotification

The SEND\_USSD\_SS\_NOTIFY\_RESPONSE and SEND\_USSD\_MAP\_ERROR\_VALUE parameters configure the response to the Advanced Control Services (ACS) for a MAP-UNSTRUCTURED-SS-NOTIFY message.

To send a valid response, which is the default, set SEND\_USSD\_SS\_NOTIFY\_RESPONSE to 1:

SEND\_USSD\_SS\_NOTIFY\_RESPONSE=1

To send a MAP ERROR response, set SEND\_USSD\_SS\_NOTIFY\_RESPONSE to 0:

SEND\_USSD\_SS\_NOTIFY\_RESPONSE=0

---

---

**Note:** Use SEND\_USSD\_MAP\_ERROR\_VALUE=*value* to set the error code value (1 - 44) as defined in **Map2Types.h**.

---

---

Set SEND\_USSD\_SS\_NOTIFY\_RESPONSE to 2 to indicate that no response is returned:

SEND\_USSD\_SS\_NOTIFY\_RESPONSE=2

The following example illustrates the SEND\_USSD\_SS\_NOTIFY\_RESPONSE and SEND\_USSD\_MAP\_ERROR\_VALUE parameters:



```

AP = {
    ...
    SEND_USSD_SS_NOTIFY_RESPONSE=0
    SEND_USSD_MAP_ERROR_VALUE=1
}

```

### XMS tcapInterfaceName

The tcapInterfaceName parameter specifies the name of the interface that XMS uses to communicate with the SMSC. The parameter value is the same name that is specified as the SMSC interface by the INTERFACE parameter in the **SLEE.cfg** file.

The following example illustrates the tcapInterfaceName parameter in the **smmc.cfg** file:

```

XMS = {
  xmsTrigger = {
    plugins = [
      # MAP plugin
      {
        lib = "xmsiMap.so"
        SSN = 8
        prefix = "485"
        pluginId = 1
        config = {
          contextKey = 1234
          tcapInterfaceName = "SMSCINT"
          GT = "5114406267"
          PC = 55
          SSN = 8
        }
      }
    ]
  }
}

```

## Configuring for IS-41

When the Protocol parameter in the **smmc.cfg** file is set to IS-41, **smmc** accepts SMSDeliveryPointToPoint requests and responds to them based on the following IS-41 parameters.

Use the following parameters to configure **smmc** for the IS-41 protocol.

### ACK

Deprecated in favor of Action.

If the value is true, respond with a positive value for SMSDeliveryPointToPointResult, but one without an SMS\_CauseCode value.

Allowed Values:	true or false
Default:	false
Example:	ACK = false

### Action

Specifies the action to take upon receipt of a message, which supersedes the ACK, NACK, TCAP\_ABORT, and Ignore items. You can also use the strings "ack", "nack", "abort", and "ignore".

Allowed Values:	<ul style="list-style-type: none"> <li>▪ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>▪ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>▪ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>▪ "NACK", "FAIL_REQUEST", 3 Respond to the request with a ReturnResult message but with a cause value to indicate failure. See <a href="#">"SMS CauseCode Mapping"</a> for cause values.</li> <li>▪ "TCAP_U_ERROR", 4 Send a TCAP ReturnError component.</li> <li>▪ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	Action = "ACKNOWLEDGE_REQUEST"

**altAction**

Specifies the action to take upon receipt of a message, which supersedes the ACK, NACK, TCAP\_ABORT, and Ignore items. You can also use the strings "ack", "nack", "abort", and "ignore".

Allowed Values:	<ul style="list-style-type: none"> <li>▪ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>▪ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>▪ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Meaning: Close the dialog with a TCAP ABORT message.</li> <li>▪ "NACK", "FAIL_REQUEST", 3 Meaning: Respond to the request with a ReturnResult message but with a cause value to indicate failure. See <a href="#">"SMS CauseCode Mapping"</a> for cause values.</li> <li>▪ "TCAP_U_ERROR", 4 Meaning: Send a TCAP ReturnError component.</li> <li>▪ "NOTIFY_REQUEST", 5 Meaning: Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	altAction = "ACKNOWLEDGE_REQUEST"

**altPercentage**

Specifies the percentage of time to use altAction instead of Action.

Allowed Values:	An integer between 0 and 255
-----------------	------------------------------

Default:	0
Example:	altPercentage = 0

**defaultDestPC**

The point code to put in the SCCP Called Party Address of TCAP messages containing IS-41 operations.

Allowed Values:	An integer between 0 and 16383
Default:	3
Example:	defaultDestPC = 2001

**defaultDestSSN**

The subsystem number to put in the SCCP Called Party Address of TCAP messages containing IS-41 operations.

Allowed Values:	An integer between 0 and 255
Default:	3
Example:	defaultDestSSN = 8

**Ignore**

Deprecated in favor of Action. You can also use the string "ignore".

If the value is true, ignore the request as if it was not received.

Allowed Values:	true or false
Default:	false
Example:	Ignore = false

**NACK**

Deprecated in favor of Action.

If the value is true, respond with a negative value for SMSDeliveryPointToPointResult by including an SMS\_CauseCode value.

Allowed Values:	true or false
Default:	false
Example:	NACK = false

**NACK\_StatusCode**

The action to put in the status code when the action is FAIL\_REQUEST.

Allowed Values:	Zero or a positive integer. Meaningful values: 0 AddressVacant 1 AddressTranslationFailure 2 NetworkResourceShortage 3 NetworkFailure 4 InvalidTeleserviceID 5 OtherNetworkProblem (6 - 31 are reserved, treated as OtherNetworkProblem) 32 NoPageResponse 33 DestinationBusy 34 NoAcknowledgement 35 DestinationResourceShortage 36 SMSDeliveryPostponed 37 DestinationOutOfService 38 DestinationNoLongerAtThisAddress 39 OtherTerminalProblem (40 - 47 are reserved, treated as OtherTerminalProblem) (48 - 63 are reserved, treated as SMSDeliveryPostponed) 64 RadioInterfaceResourceShortage 65 RadioInterfaceIncompatibility 66 OtherRadioInterfaceProblem (67 - 95 are reserved, treated as OtherRadioInterfaceProblem) 96 EncodingProblem 97 SMSOriginationDenied 98 SMSTerminationDenied 99 SupplementaryServiceNotSupported 100 SMSNotSupported 101 (reserved) 102 MissingExpectedParameter 103 MissingMandatoryParameter 104 UnrecognizedParameterValue 105 UnexpectedParameterValue 106 UserDataSizeError 107 OtherGeneralProblems
Default:	3
Example:	NACK_StatusCode = 3

### RECEIVED\_SMS\_STATUS\_REPORT

The parameters in this section have the same meaning as their counterparts in the IS41 section. They apply, however, only to the action that the **smc** test tool takes upon receiving a RECEIVED\_SMS\_STATUS\_REPORT message. You can include the following parameters in the RECEIVED\_SMS\_STATUS\_REPORT section:

- Action

- altAction
- altPercentage
- NackStatusCode
- TCAP\_ABORT
- TCAP\_Notice\_cause
- TCAP\_U\_ERROR\_code

---

**Note:** If any of these parameters is not present, the value from its counterpart IS-41 parameter is used instead.

---

For example:

```
IS41 = {
  ...
  RECEIVED_SMS_STATUS_REPORT = {
    Action = "ACKNOWLEDGE_REQUEST"
    altAction = "ACKNOWLEDGE_REQUEST"
    altPercentage = 0
    TCAP_ABORT_cause = 0
    TCAP_NOTICE_cause = 0
    TCAP_U_ERROR_code = 0
    NACK_StatusCode = 3
  }
  ...
}
```

### TCAP\_ABORT

Deprecated in favor of Action. You can also use the string "abort".

If the value is true, respond by sending a TCAP\_ABORT and closing the dialog.

Allowed Values:	true or false
Default:	false
Example:	TCAP_ABORT = false

### TCAP\_ABORT\_cause

If TCAP\_ABORT is true, the value of TCAP\_ABORT\_cause is the numeric code for the cause of the abort.

Allowed Values:	An integer between 0 and 255 Meaningful Values: 0 Unrecognized Packet Type 1 Unrecognized Trans ID 2 Badly Structured Trans Portion 3 Incorrect Trans Portion 4 Resource Unavailable 5 Permission To Release Problem 6 Unrecognized dialogue portion ID 7 Badly structured dialogue portion 8 Missing dialogue portion 9 Inconsistent dialogue portion
Default:	0
Example:	TCAP_ABORT_cause = 0

**TCAP\_NOTICE\_cause**

The cause to put in a TCAP\_NOTICE message.

Allowed Values:	Zero or a positive integer. Meaningful values: 0 no translation for an address of such nature 1 no translation for this specific address 2 subsystem congestion 3 subsystem failure 4 unequipped user 5 MTP failure 6 network congestion 7 unqualified 8 error in message transport (Note) 9 error in local processing (Note) 10 destination cannot perform reassembly (Note) 11 SCCP failure 12 hop counter violation 13 segmentation not supported 14 segmentation failure
Default:	0
Example:	TCAP_NOTICE_cause = 0

**TCAP\_U\_ERROR**

Deprecated in favor of Action.

Allowed Values:	true or false
Default:	false

Example:	TCAP_U_ERROR = false
----------	----------------------

**TCAP\_U\_ERROR\_code**

The error code to put in a TCAP ReturnError

Allowed Values:	Zero or a positive integer.
Default:	0
Example:	TCAP_U_ERROR_code = 0

**Configuring for IS-41 as HLR**

When Protocol is set to IS41, you can configure **smsc** to respond when it is sent an SMSRequest.

---

**Note:** SMS and HLR functionality are independent of each other.

---

The **smsc** response is based on the following parameters:

**AccessDenied**

Deprecated. When true, this parameter is equivalent to Action = "NACK". which responds to the request with a ReturnResult and a cause value that indicates failure.

Allowed Values:	true or false
Default:	False
Example:	AccessDenied = False

**AccessDeniedReason**

Specifies the reason access was denied when the action is FAIL\_REQUEST.

Allowed Values:	0 NotUsed 1 Denied 2 Postponed 3 Unavailable 4 Invalid
Default:	0
Example:	AccessDeniedReason = 0

**Action**

Specifies the action to take upon receipt of a message. The Action parameter supersedes the Enabled and AccessDenied items.

Allowed Values:	<ul style="list-style-type: none"> <li>▪ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>▪ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>▪ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Meaning: Close the dialog with a TCAP ABORT message.</li> <li>▪ "NACK", "FAIL_REQUEST", 3 Meaning: Respond to the request with a ReturnResult message but with a cause value to indicate failure. See "TCAP_U_ERROR", 4 Meaning: Send a TCAP ReturnError component.</li> <li>▪ "NOTIFY_REQUEST", 5 Meaning: Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	Action = "ACKNOWLEDGE_REQUEST"

**Enabled**

Deprecated. Enables HLR capabilities when true. When false, is equivalent to Action = "IGNORE".

Allowed Values:	true or false
Default:	true
Example:	Enabled= true

**esnManufacturerCode**

The manufacturer code of the mobile device's Electronic Serial Number (ESN). This is returned in the SMSRequestResult message if an ESN was not present in the SMSRequest message.

Allowed Values:	An integer between 0 and 255
Default:	0
Example:	esnManufacturerCode = 123

**esnSerialNumber**

The mobile device's Electronic Serial Number (ESN), which is returned in the SMSRequestResult message if an ESN was not present in the SMSRequest message.

Allowed Values:	An integer between 0 and 16777215
Default:	0
Example:	esnSerialNumber = 12345678



**hlrAltAction**

Specifies the alternative action to take upon receipt of a lookup request. The hlrAltAction parameter is used instead of the Action parameter the percentage of time specified by hlrAltPercentage.

Allowed Values:	<ul style="list-style-type: none"> <li>■ "ACK", "ACKNOWLEDGE_REQUEST", 0 Respond to an SMSDeliveryPointToPoint message by acknowledging it as a success.</li> <li>■ "IGNORE", "IGNORE_REQUEST", 1 Ignore the request as if it was not received.</li> <li>■ "ABORT", "TCAP_ABORT", "ABORT_REQUEST", 2 Close the dialog with a TCAP ABORT message.</li> <li>■ "NACK", "FAIL_REQUEST", 3 Respond to the request with a ReturnResult message but with a cause value that indicates failure. See <a href="#">"SMS CauseCode Mapping"</a> for a list of cause codes.</li> <li>■ "TCAP_U_ERROR", 4 Send a TCAP ReturnError component.</li> <li>■ "NOTIFY_REQUEST", 5 Respond to a SendRoutingInformation operation with a TCAP NOTICE message.</li> </ul>
Default:	"ACKNOWLEDGE_REQUEST"
Example:	hlrAltAction = "ACKNOWLEDGE_REQUEST"

**hlrPercentage**

Specifies the percentage of time to use the [hlrAltAction](#) parameter instead of the [Action](#) parameter.

Allowed Values:	An integer between 0 and 255.
Default:	0
Example:	hlrAltPercentage

**HLRSequence**

Optional. This parameter is an array that enables you to configure a different responses for the MAP plugin when using HLR functionality for Status Reports and Submit messages. See ["SMSC Sequence for MAP as IS-41"](#) for more information.

**mobileIdentificationNumber**

The mobile identification number (MIN), which is returned in the SMSRequestResult message if the MDN was present in the SMSRequest message.

Allowed Values:	A string of exactly ten digits
Default:	"1234567890"
Example:	mobileIdentificationNumber = "1234567890"

**NatureOfNumber**

Specifies whether the routing address is national or international.

Allowed Values:	"national" or "international" (case sensitive).
Default:	"national"
Example:	NatureOfNumber = "national"

### NumberPlan

Specifies the number plan portion of the routing address, which is the address of the MSC at which the mobile device currently can be reached.

Allowed Values:	An integer between 0 and 255 Meaning (from standard IS-41D): 0 Unknown or not applicable. 1 ISDN Numbering (not used in this Standard). 2 Telephony Numbering (ITU-T Rec. E.164, E.163). 3 Data Numbering (ITU-T Rec. X.121) (not used in this Standard). 4 Telex Numbering (ITU-T Rec. F.69) (not used in this Standard). 5 Maritime Mobile Numbering (not used in this Standard). 6 Land Mobile Numbering (ITU-T Rec. E.212) 7 Private Numbering Plan (service provider defined). 13 ANSI SS7 Point Code (PC) and SubsystemNumber (SSN). 14 Internet Protocol (IP) Address. 15 Reserved for extension. X Other values are reserved.
Default:	2 (Telephony Numbering)
Example:	NumberPlan = 2

### returnMIN

Specifies whether to include the MIN in the SMSRequestResult message.

Allowed Values:	true or false
Default:	false
Example:	returnMIN = false

### RoutingAddress

The global address of the MSC at which the mobile device currently can be reached.

Allowed Values:	A string of digits.
Default:	0
Example:	RoutingAddress = "12345678"

### TCAP\_ABORT\_cause

If TCAP\_ABORT is true, the value of TCAP\_ABORT\_cause is the numeric code for the cause of the abort.

Allowed Values:	An integer between 0 and 255 Meaningful Values: 0 Unrecognized Packet Type 1 Unrecognized Trans ID 2 Badly Structured Trans Portion 3 Incorrect Trans Portion 4 Resource Unavailable 5 Permission To Release Problem 6 Unrecognized dialogue portion ID 7 Badly structured dialogue portion 8 Missing dialogue portion 9 Inconsistent dialogue portion
Default:	0
Example:	TCAP_ABORT_cause = 0

**TCAP\_NOTICE\_cause**

The cause to put in a TCAP\_NOTICE message.

Allowed Values:	An integer between 0 and 255. Meaningful values: 0 no translation for an address of such nature 1 no translation for this specific address 2 subsystem congestion 3 subsystem failure 4 unequipped user 5 MTP failure 6 network congestion 7 unqualified 8 error in message transport (Note) 9 error in local processing (Note) 10 destination cannot perform reassembly (Note) 11 SCCP failure 12 hop counter violation 13 segmentation not supported 14 segmentation failure
Default:	0
Example:	TCAP_NOTICE_cause = 0

**SMSC Sequence for MAP as IS-41**

When Protocol is set to IS41, you can add an HLRSequence parameter to configure different responses for the MAP plugin when using HLR functionality for Status Reports and Submit messages. HLRSequence is an array where each array element represents a response.

Each parameter available for HLR configuration is also available for HLRSequence.

The following rules apply to use of the HLRSequence parameter:

- If HLRSequence has one response, it is used for all responses.
- If HLRSequence has more than one response, the first request will be handled according to the first array element, the second request will be handled according to the second array element, and so on. When the **smc** test tool reaches the end of the array, it loops back to the beginning of the array..
- If HLRSequence is absent or is present but has no responses, HLR is used for all responses.

The following example illustrates the use of the HLRSequence parameter for MAP as IS-41:

```
# smsc.cfg
SMSC = {
    Protocol = "IS41"
    IS41 = {
        Action = "ACK"
        HLRSequence = [
            {
                Action = 0
                NatureOfNumber = "international"
                RoutingAddress = "6449393400"
            }
            {
                Action = "NACK"
                AccessDeniedReason = 2
                NatureOfNumber = "international"
                RoutingAddress = "6449393400"
            }
        ]
    }
}
```

### Specifying AccessDeniedReason Values

Use the values in [Table 4-1](#) to specify values for the AccessDeniedReason parameter.

**Table 4-1** AccessDeniedReason Values

Value	Meaning
0	NotUsed
1	Denied
2	Postponed
3	Unavailable
4	Invalid

### tcapInterfaceServiceKey for XMS

The tcapInterfaceServiceKey parameter specifies the service key that XMS uses to communicate with the **smc** test tool. This service key must match the SERVICEKEY parameter for the SMSC interface in the **SLEE.cfg** file.

The following example shows the tcapInterfaceServiceKey parameter in the **smc.cfg** file:

```
# eserv.config
XMS = {
```

```

xmsTrigger = {
  plugins = [
    # IS41 plugin
    {
      lib = "libxmsiIS41.so"
      pluginId = 1
      config = {
        # ....
        TDMA = {
          xmsPointCode = 200
          tcapInterfaceServiceKey = 42
          # ....
        }
        CDMA = {
          xmsPointCode = 201
          tcapInterfaceServiceKey = 42
        }
      }
    }
  ]
}

```

## SMS CauseCode Mapping

Use the values in [Table 4–2](#) to specify the SMS CauseCode values.

**Table 4–2 SMS CauseCode Values**

Numeric Value	String Value
0	AddressVacant
1	AddressTranslationFailure
2	NetworkResourceShortage
3	NetworkFailure
4	InvalidTeleserviceID
5	OtherNetworkProblem
6-31	Reserved, treated as OtherNetworkProblem
32	NoPageResponse
33	DestinationBusy
34	NoAcknowledgement
35	DestinationResourceShortage
36	SMSDeliveryPostponed
37	DestinationOutOfService
38	DestinationNoLongerAtThisAddress
39	OtherTerminalProblem
40-47	Reserved, treated as OtherTerminalProblem
48-63	Reserved, treated as SMSDeliveryPostponed
64	RadioInterfaceResourceShortage
65	RadioInterfaceIncompatibility
66	OtherRadioInterfaceProblem
67-95	Reserved, treated as OtherRadioInterfaceProblem

**Table 4–2 (Cont.) SMS CauseCode Values**

<b>Numeric Value</b>	<b>String Value</b>
96	EncodingProblem
97	SMSOriginationDenied
98	SMSTerminationDenied
99	SupplementaryServiceNotSupported
100	SMSNotSupported
101	Reserved
102	MissingExpectedParameter
103	MissingMandatoryParameter
104	UnrecognizedParameterValue
105	UnexpectedParameter Value
106	UserDataSizeError
107	OtherGeneralProblems

---


## About the SS7 Protocol Suite

The SS7 protocol suite is a set of telephony signaling protocols that are used to establish and terminate telephone calls on public switched telephone networks. The SS7 protocol suite provides additional services as well, including number translation, local number portability, prepaid billing mechanisms, short message service (SMS), and a variety of other services.

Each protocol within a suite usually has a particular purpose. Such modularization makes design and assessment of the protocols easier. Because each protocol module usually communicates with two others, they are ordinarily considered as layers in a protocol stack. The lowest-layer protocol performs the low-level, physical interaction with the network hardware. Higher layers add more features.

Figure A-1 illustrates the SS7 protocol suite:

**Figure A-1 SS7 Protocol Suite**



### The INAP Protocol

The INAP protocol is the signalling protocol that is used in Intelligent Networks (INs). INAP was developed by the International Telecommunications Union (ITU), and is recognized as an international standard. The functionality of INAP has been defined and implemented by the ITU in segments called capability sets. The first version was Capability Set 1 (CS-1) and Capability Set 2 (CS-2) is currently available.

INAP communicates between a service switching point (SSP), network media resources (intelligent peripherals), and a centralized network database called a service control point (SCP). The SCP encompasses operator or third-party-derived service logic programs and data.

## The CAP Protocol

The CAMEL Application Part (CAP) protocol is a signalling protocol in the IN architecture and is layered on top of the TCAP protocol. It makes possible the implementation of carrier-grade, value added services like unified messaging services, prepaid services, fraud control, and Freephone (800 number calls) in both the Global System for Mobile Communication (GSM) voice and General Packet Radio Service (GPRS) data networks. CAMEL is a means of adding intelligent applications to mobile networks. It builds upon established practices in the fixed-line telephony business that are generally considered part of the INAP CS-2 protocol.

## The MAP Protocol

The Mobile Application Part (MAP) protocol supplies an application layer for nodes in the following networks:

- GSM (mobile) networks
- Universal Mobile Telecommunications System (UMTS) networks
- GPRS networks

The nodes in these networks use the MAP protocol to communicate with each other so they can provide services to mobile phone users. These services include mobility services such as location management to support roaming, call handling, SMS for text messaging, packet data protocol (PDP) services for GPRS, and operation and maintenance, as well as other services.

## The IS-41 Protocol

The Interim Standard 41 protocol enables mobile, cellular telecommunications operations between different networks. It is similar to GSM and supports capabilities such as handover between networks, roaming authentication, and SMS delivery. It includes the Visitor Location Register (VLR) and Home Location Register (HLR) databases.

## The TCAP Protocol

The TCAP protocol provides a presentation layer that facilitates the distribution of intelligent network services. The presentation layer deals with data format, operating system compatibility, and encapsulating data to send over the network. Fundamentally, TCAP simplifies simultaneous communications between subsystems on the same machines by using transaction IDs to associate multiple messages with a particular transaction.

In intelligent networks TCAP transports INAP and in mobile phone networks it transports MAP. See ["Using TCAP Primitives"](#) for more information.

## The SCCP Protocol

The Signaling Connection Control Part (SCCP) protocol is a routing protocol that routes TCAP messages to their proper database. SCCP provides connectionless and connection-oriented network services. SCCP provides subsystem numbers that enable messages to be addressed to specific applications or subsystems at signaling points. SCCP is the transport layer for TCAP-based services such as calling card, local number portability, wireless roaming, personal communications services (PCS), and freephone (800 numbers).



## The M3UA Protocol

M3UA stands for Message Transfer Part Level 3 (MTP3) User Adaptation Layer. The M3UA protocol enables the SS7 protocol User Part SCCP, as well as others, to run over internet protocol instead of telephony equipment. The M3UA protocol is generally transmitted by using the services of Stream Control Transmission Protocol (SCTP).

## The SUA Protocol

SUA stands for the SCCP User Adaptation layer. The SUA protocol facilitates the transfer of SCCP user messages, such as TCAP, between the signalling gateway and the application server process (ASP).

## The SCTP Protocol

The Stream Control Transmission Protocol (SCTP) is a transport-layer protocol that delivers in-sequence messages. It performs path selection and provides fail-over support for duplicated paths in the network.

The SCTP protocol was originally designed to transport telephony over the internet, but it has evolved to have other purposes as well.

## The Internet Protocol

The Internet Protocol (IP) provides routing for data packets from source to destination hosts based on IP addresses. It facilitates the internetworking that constitutes the internet and defines structures that enclose data and add the source and destination addresses. Because it is often used together with the Transport Control Protocol, it is frequently referred to as TCP/IP. It runs on top of data link interfaces such as Ethernet and Wi-Fi, operating at layer 3 of the OSI model, which is the network layer. The network layer provides routing and switching functionality to transmit data between nodes.



## Supported Protocol Fields for mipt

This appendix lists the fields supported by the **mipt** utility for each of the protocols that you can use:

- Supported Fields for the Diameter Protocol
  - Base AVP Diameter Fields
  - Vendor-Specific Diameter Fields
- Supported Fields for the EMI Protocol
- Supported Fields of the M3UA Protocol
- Supported Fields of the RADIUS Protocol
  - Supported Vendor-Specific Fields of the RADIUS Protocol
- Supported Fields of the SMPP Protocol
  - Supported SMPP TLV Fields

### Supported Fields for the Diameter Protocol

Table B-1 lists the fields that the **mipt** utility supports for the Diameter protocol.

**Table B-1 Supported Fields of the Diameter Protocol**

Diameter Field Name	Diameter Field Name
3gpp_abort_cause	3gpp_acceptable_service_info
3gpp_access_network_charging_address	3gpp_access_network_charging_identifier
3gpp_access_network_charging_identifier_gx	3gpp_access_network_charging_identifier_value
3gpp_access_network_information	3gpp_account_expiration
3gpp_accumulated_cost	3gpp_adaptations
3gpp_additional_content_information	3gpp_additional_mbms_trace_info
3gpp_additional_type_information	3gpp_address_data
3gpp_address_domain	3gpp_address_type
3gpp_addressee_type	3gpp_af_application_identifier
3gpp_af_charging_identifier	3gpp_af_correlation_information
3gpp_af_signalling_protocol	3gpp_allocation_retention_priority
3gpp_alternate_charged_party_address	3gpp_alternative_apn

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_an_gw_address	3gpp_aoc_cost_information
3gpp_aoc_format	3gpp_aoc_information
3gpp_aoc_request_type	3gpp_aoc_service
3gpp_aoc_service_obligatory_type	3gpp_aoc_service_type
3gpp_aoc_subscription_information	3gpp_apn_aggregated_max_bitrate_dl
3gpp_apn_aggregated_max_bitrate_ul	3gpp_applic_id
3gpp_application_provided_called_party_address	3gpp_application_server
3gpp_application_server_information	3gpp_application_service_provider_identity
3gpp_associated_party_address	3gpp_associated_uri
3gpp_authorised_qos	3gpp_aux_applic_info
3gpp_base_time_interval	3gpp_bearer_control_mode
3gpp_bearer_identifier	3gpp_bearer_operation
3gpp_bearer_service	3gpp_bearer_usage
3gpp_billing_information	3gpp_called_asserted_identity
3gpp_called_party_address	3gpp_calling_party_address
3gpp_carrier_select_routing_information	3gpp_cause_code
3gpp_cg_address	3gpp_change_condition
3gpp_change_time	3gpp_charged_party
3gpp_charging_characteristics_selection_mode	3gpp_charging_correlation_indicator
3gpp_charging_id	3gpp_charging_rule_base_name
3gpp_charging_rule_definition	3gpp_charging_rule_install
3gpp_charging_rule_name	3gpp_charging_rule_remove
3gpp_charging_rule_report	3gpp_class_identifier
3gpp_client_address	3gpp_cn_ip_multicast_distribution
3gpp_coa_information	3gpp_coa_ip_address
3gpp_codec_data	3gpp_content_class
3gpp_content_disposition	3gpp_content_length
3gpp_content_size	3gpp_content_type
3gpp_csg_access_mode	3gpp_csg_information_reporting
3gpp_csg_membership_indication	3gpp_cug_information
3gpp_current_tariff	3gpp_data_coding_scheme
3gpp_dcd_information	3gpp_default_eps_bearer_qos
3gpp_deferred_location_event_type	3gpp_delivery_report
3gpp_delivery_report_requested	3gpp_diagnostics
3gpp_domain_name	3gpp_drm_content
3gpp_dynamic_address_flag	3gpp_dynamic_address_flag_extension

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_early_media_description	3gpp_envelope
3gpp_envelope_end_time	3gpp_envelope_reporting
3gpp_envelope_start_time	3gpp_event
3gpp_event_charging_timestamps	3gpp_event_report_indication
3gpp_event_trigger	3gpp_event_type
3gpp_experimental_result_code	3gpp_expires
3gpp_file_repair_supported	3gpp_flow_description
3gpp_flow_direction	3gpp_flow_information
3gpp_flow_label	3gpp_flow_number
3gpp_flow_status	3gpp_flow_usage
3gpp_flows	3gpp_ggsn_address
3gpp_guaranteed_bitrate_dl	3gpp_guaranteed_bitrate_ul
3gpp_im_information	3gpp_ims_application_reference_identifier
3gpp_ims_charging_identifier	3gpp_ims_communication_service_identifier
3gpp_ims_information	3gpp_imsi
3gpp_imsi_unauthenticated_flag	3gpp_incoming_trunk_group_id
3gpp_incremental_cost	3gpp_initial_ims_charging_identifier
3gpp_initial_recipient_address	3gpp_inter_operator_identifier
3gpp_interface_id	3gpp_interface_port
3gpp_interface_text	3gpp_interface_type
3gpp_ip_can_type	3gpp_ip_realm_default_indication
3gpp_lcs_client_dialed_by_ms	3gpp_lcs_client_external_id
3gpp_lcs_client_id	3gpp_lcs_client_name
3gpp_lcs_client_type	3gpp_lcs_data_coding_scheme
3gpp_lcs_format_indicator	3gpp_lcs_information
3gpp_lcs_name_string	3gpp_lcs_requestor_id
3gpp_lcs_requestor_id_string	3gpp_local_gw_inserted_indication
3gpp_local_sequence_number	3gpp_location_estimate
3gpp_location_estimate_type	3gpp_location_type
3gpp_low_balance_indication	3gpp_low_priority_indicator
3gpp_max_bandwidth_ul	3gpp_max_requested_bandwidth_dl
3gpp_max_supported_bandwidth_dl	3gpp_max_supported_bandwidth_ul
3gpp_maximum_bandwidth	3gpp_mbms_2g_3g_indicator
3gpp_mbms_access_indicator	3gpp_mbms_bmsc_ssm_ip_address
3gpp_mbms_bmsc_ssm_ipv6_address	3gpp_mbms_bmsc_ssm_udp_port
3gpp_mbms_counting_information	3gpp_mbms_flow_identifier
3gpp_mbms_ggsn_address	3gpp_mbms_ggsn_ipv6_address

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_mbms_gw_address	3gpp_mbms_gw_ssm_ip_address
3gpp_mbms_gw_ssm_ipv6_address	3gpp_mbms_gw_udp_port
3gpp_mbms_gw_udp_port_indicator	3gpp_mbms_hc_indicator
3gpp_mbms_information	3gpp_mbms_service_area
3gpp_mbms_service_type	3gpp_mbms_session_duration
3gpp_mbms_session_identity	3gpp_mbms_session_repetition_number
3gpp_mbms_startstop_indication	3gpp_mbms_time_to_data_transfer
3gpp_mbms_user_data_mode_indication	3gpp_mbms_user_service_type
3gpp_media_component_description	3gpp_media_component_number
3gpp_media_initiator_flag	3gpp_media_initiator_party
3gpp_media_sub_component	3gpp_media_type
3gpp_message_body	3gpp_message_class
3gpp_message_id	3gpp_message_size
3gpp_message_type	3gpp_metering_method
3gpp_min_requested_bandwidth_dl	3gpp_min_requested_bandwidth_ul
3gpp_mm_content_type	3gpp_mm10_recipient_address
3gpp_mmbox_storage_requested	3gpp_mms_information
3gpp_mmtel_information	3gpp_monitoring_key
3gpp_mps_identifier	3gpp_msisdn
3gpp_network_request_support	3gpp_next_tariff
3gpp_node_functionality	3gpp_node_id
3gpp_number_of_diversions	3gpp_number_of_messages_sent
3gpp_number_of_participants	3gpp_number_of_received_talk_bursts
3gpp_number_of_talk_bursts	3gpp_number_portability_routing_information
3gpp_offline	3gpp_offline_charging
3gpp_online	3gpp_online_charging_flag
3gpp_originating_interface	3gpp_originating_ioi
3gpp_originator	3gpp_originator_address
3gpp_originator_received_address	3gpp_originator_sccp_address
3gpp_outgoing_session_id	3gpp_outgoing_trunk_group_id
3gpp_packet_filter_content	3gpp_packet_filter_identifier
3gpp_packet_filter_information	3gpp_packet_filter_operation
3gpp_packet_filter_usage	3gpp_participant_access_priority
3gpp_participant_action_type	3gpp_participant_group
3gpp_participants_involved	3gpp_pcc_rule_status
3gpp_pdg_address	3gpp_pdg_charging_id

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_pdn_connection_charging_id	3gpp_pdn_connection_id
3gpp_pdp_address	3gpp_pdp_address_prefix_length
3gpp_pdp_context_type	3gpp_poc_change_condition
3gpp_poc_change_time	3gpp_poc_controlling_address
3gpp_poc_event_type	3gpp_poc_group_name
3gpp_poc_information	3gpp_poc_server_role
3gpp_poc_session_id	3gpp_poc_session_initiation_type
3gpp_poc_session_type	3gpp_poc_user_role
3gpp_poc_user_role_ids	3gpp_poc_user_role_info_units
3gpp_positioning_data	3gpp_pre_emption_capability
3gpp_precedence	3gpp_preemption_vulnerability
3gpp_preferred_aoc_currency	3gpp_priority
3gpp_priority_level	3gpp_ps_append_free_format_data
3gpp_ps_free_format_data	3gpp_ps_furnish_charging_information
3gpp_ps_information	3gpp_qos_class_identifier
3gpp_qos_information	3gpp_qos_negotiation
3gpp_qos_rule_base_name	3gpp_qos_rule_definition
3gpp_qos_rule_install	3gpp_qos_rule_name
3gpp_qos_rule_remove	3gpp_qos_rule_report
3gpp_qos_upgrade	3gpp_quota_consumption_time
3gpp_quota_holding_time	3gpp_rai
3gpp_rat_type	3gpp_rate_element
3gpp_read_reply	3gpp_read_reply_report_requested
3gpp_real_time_tariff_information	3gpp_reason_code
3gpp_received_talk_burst_time	3gpp_received_talk_burst_volume
3gpp_recipient_address	3gpp_recipient_info
3gpp_recipient_received_address	3gpp_recipient_sccp_address
3gpp_refund_information	3gpp_remaining_balance
3gpp_reply_applic_id	3gpp_reply_path_requested
3gpp_reporting_level	3gpp_reporting_reason
3gpp_requested_party_address	3gpp_required_mbms_bearer_capabilities
3gpp_resource_allocation_notification	3gpp_result_recipient_address
3gpp_revalidation_time	3gpp_role_of_node
3gpp_routeing_address	3gpp_routeing_address_resolution
3gpp_routing_filter	3gpp_routing_ip_address
3gpp_routing_rule_definition	3gpp_routing_rule_identifier
3gpp_routing_rule_install	3gpp_routing_rule_remove

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_rr_bandwidth	3gpp_rs_bandwidth
3gpp_rule_activation_time	3gpp_rule_deactivation_time
3gpp_rule_failure_code	3gpp_scale_factor
3gpp_sdp_answer_timestamp	3gpp_sdp_media_component
3gpp_sdp_media_description	3gpp_sdp_media_name
3gpp_sdp_offer_timestamp	3gpp_sdp_session_description
3gpp_sdp_timestamps	3gpp_sdp_type
3gpp_security_parameter_index	3gpp_sender_address
3gpp_sender_visibility	3gpp_sequence_number
3gpp_served_party_ip_address	3gpp_served_user_identity
3gpp_service_data_container	3gpp_service_generic_information
3gpp_service_id	3gpp_service_info_status
3gpp_service_information	3gpp_service_key
3gpp_service_mode	3gpp_service_specific_data
3gpp_service_specific_info	3gpp_service_specific_type
3gpp_service_type	3gpp_service_urn
3gpp_serving_node_type	3gpp_session_linking_indicator
3gpp_session_release_cause	3gpp_sgsn_address
3gpp_sgsn_mcc_mnc	3gpp_sgw_address
3gpp_sgw_change	3gpp_sip_forking_indication
3gpp_sip_method	3gpp_sip_request_timestamp
3gpp_sip_request_timestamp_fraction	3gpp_sip_response_timestamp
3gpp_sip_response_timestamp_fraction	3gpp_sm_discharge_time
3gpp_sm_message_type	3gpp_sm_protocol_id
3gpp_sm_service_type	3gpp_sm_status
3gpp_sm_user_data_header	3gpp_sms_information
3gpp_sms_node	3gpp_smsc_address
3gpp_specific_action	3gpp_sponsor_identity
3gpp_sponsored_connectivity_data	3gpp_start_time
3gpp_status	3gpp_status_code
3gpp_status_text	3gpp_stop_time
3gpp_submission_time	3gpp_subscriber_role
3gpp_supplementary_service	3gpp_talk_burst_exchange
3gpp_talk_burst_time	3gpp_talk_burst_volume
3gpp_tariff_information	3gpp_tariff_xml
3gpp_terminating_ioi	3gpp_tft_filter
3gpp_tft_packet_filter_information	3gpp_time_first_usage



**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
3gpp_time_last_usage	3gpp_time_quota_mechanism
3gpp_time_quota_threshold	3gpp_time_quota_type
3gpp_time_stamps	3gpp_time_usage
3gpp_tmgi	3gpp_token_text
3gpp_tos_traffic_class	3gpp_traffic_data_volumes
3gpp_transcoder_inserted_indication	3gpp_trigger
3gpp_trigger_event	3gpp_trigger_type
3gpp_trunk_group_id	3gpp_tunnel_header_filter
3gpp_tunnel_header_length	3gpp_tunnel_information
3gpp_type_number	3gpp_unit_cost
3gpp_unit_quota_threshold	3gpp_usage_monitoring_information
3gpp_usage_monitoring_level	3gpp_usage_monitoring_report
3gpp_usage_monitoring_support	3gpp_user_csg_information
3gpp_user_location_information	3gpp_user_participating_type
3gpp_user_session_id	3gpp_vas_id
3gpp_vasp_id	3gpp_volume_quota_threshold
3gpp_wag_address	3gpp_wag_plmn_id
3gpp_wlan_information	3gpp_wlan_radio_container
3gpp_wlan_session_id	3gpp_wlan_technology
3gpp_wlan_ue_local_ipaddress	abort_session_answer
abort_session_request	ACA
ACCOUNTING	accounting_answer
accounting_realtime_required	accounting_record_number
accounting_record_type	accounting_request
accounting_session_id	accounting_sub_session_id
acct_application_id	acct_interim_interval
acct_multi_session_id	ACR
ALL_APPLICATION	ALL_HOST
ALL_REALM	ALL_SESSION
ALL_USER	ALLOW_SERVICE
application_id	art_AUTHORIZE_AUTHENTICATE
art_AUTHORIZE_ONLY	ASA
ASR	auth_application_id
auth_grace_period	auth_request_type
auth_session_state	AUTHENTICATE_ONLY
authorization_lifetime	balanceExpiry
balanceInfo	balanceLimitType

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
balanceMaxCredit	balanceType
balanceUnit	balanceUserValue
balanceValue	BUSY
capabilities_exchange_answer	capabilities_exchange_request
cc_correlation_id	cc_input_octets
cc_money	cc_output_octets
cc_request_number	cc_request_type
cc_service_specific_units	cc_session_failover
cc_sub_session_id	cc_time
cc_total_octets	cc_unit_type
CCA	CCR
CEA	CER
charge	chargeBalanceType
chargeBalanceUnit	chargeBalanceValue
chargeInfo	chargingStartTimestamp
CHECK_BALANCE	check_balance_result
class	command_flags
CONTINUE	cost_information
cost_unit	CREDIT_AUTHORIZATION
credit_control	credit_control_answer
credit_control_failure_handling	credit_control_request
currency_code	DELIVER_AND_GRANT
destination_host	destination_realm
device_watchdog_answer	device_watchdog_request
DIRECT_DEBITING	direct_debiting_failure_handling
disconnect_cause	disconnect_peer_answer
disconnect_peer_request	DO_NOT_WANT_TO_TALK_TO_YOU
DONT_CACHE	DPA
DPR	DWA
DWR	ELECTION_LOST
end_to_end_identifier	END_USER_IMSI
END_USER_NAI	END_USER_PRIVATE
END_USER_SIP_URI	ENOUGH_CREDIT
error_message	error_reporting_host
esg_address	esg_diamident
esg_diamuri	esg_enumerated
esg_grouped	esg_grouped_1

**Table B-1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
esg_grouped_2	esg_grouped_3
esg_grouped_4	esg_grouped_5
esg_integer32	esg_integer32_1
esg_integer32_2	esg_integer32_3
esg_integer64	esg_ipfilterrule
esg_octetstring	esg_time
esg_unsigned32	esg_unsigned64
esg_utf8string	esg_utf8string_1
esg_utf8string_2	esg_utf8string_3
EVENT_RECORD	EVENT_REQUEST
event_timestamp	experimental_result
experimental_result_code	exponent
failed_avp	FAILOVER_NOT_SUPPORTED
FAILOVER_SUPPORTED	final_unit_action
final_unit_indication	firmware_revision
g_s_u_pool_identifier	g_s_u_pool_reference
GRANT_AND_LOSE	GRANT_AND_STORE
granted_service_unit	hop_by_hop_identifier
host_ip_address	IMEISV
inband_security_id	INITIAL_REQUEST
INPUT_OCTETS	INTERIM_RECORD
MAC	message_process_answer
message_process_request	Mobile_IP
MONEY	MPA
MPR	multi_round_time_out
multiple_services_credit_control	multiple_services_indicator
MULTIPLE_SERVICES_NOT_SUPPORTED	MULTIPLE_SERVICES_SUPPORTED
NASREQ	NO_CREDIT
NO_INBAND_SECURITY	NO_STATE_MAINTAINED
origin_host	origin_realm
origin_state_id	OUTPUT_OCTETS
PRICE_ENQUIRY	product_name
proxy_host	proxy_info
proxy_state	RAA
RAR	rart_AUTHORIZE_AUTHENTICATE
rart_AUTHORIZE_ONLY	rating_group
RE_AUTH	re_auth_answer

**Table B–1 (Cont.) Supported Fields of the Diameter Protocol**

<b>Diameter Field Name</b>	<b>Diameter Field Name</b>
re_auth_request	re_auth_request_type
RE_AUTHORIZATION	REALM_AND_APPLICATION
REBOOTING	REDIRECT
redirect_address_type	redirect_host
redirect_host_usage	redirect_max_cache_time
redirect_server	redirect_server_address
REFUND_ACCOUNT	REFUSE_SERVICE
Relay	requested_action
requested_service_unit	RESTRICT_ACCESS
restriction_filter_rule	result_code
RETRY_AND_TERMINATE	route_record
sb_STR	service_context_id
service_identifier	service_parameter_info
service_parameter_type	service_parameter_value
SERVICE_SPECIFIC_UNITS	session_binding
session_id	session_server_failover
session_termination_answer	session_termination_request
session_timeout	STA
START_RECORD	STATE_MAINTAINED
STOP_RECORD	STR
subscription_id	subscription_id_data
subscription_id_type	supported_vendor_id
tariff_change_usage	tariff_time_change
TERMINATE	TERMINATE_OR_BUFFER
termination_cause	TERMINATION_REQUEST
TIME	TLS
topUpAmount	topUpValueDigits
topUpVoucherId	topUpVoucherNumber
topUpVoucherType	TOTAL_OCTETS
TRY_AGAIN	TRY_AGAIN_ALLOW_SERVICE
UNIT_AFTER_TARIFF_CHANGE	UNIT_BEFORE_TARIFF_CHANGE
UNIT_INDETERMINATE	unit_value
UPDATE_REQUEST	URL
used_service_unit	user_equipment_info
user_equipment_info_type	user_equipment_info_value
user_name	validity_time
value_digits	vendor_id

**Table B–1 (Cont.) Supported Fields of the Diameter Protocol**

Diameter Field Name	Diameter Field Name
vendor_specific_application_id	voucherBalance
voucherInfo	voucherInfoBalanceExpiryExtension
voucherInfoBalanceExpiryExtensionPolicy	voucherInfoBalanceExpiryExtensionType
voucherInfoBalanceType	voucherInfoMissingBalancePolicy
voucherInfoNewBucket	voucherInfoReplaceBalance
voucherInfoValue	voucherInfoVoucher
voucherInfoWalletExpiryExtension	voucherInfoWalletExpiryExtensionPolicy
voucherInfoWalletExpiryExtensionType	voucherTypeName
walletActivationDate	walletExpiry
walletInfo	walletLastAccessed
walletMaxConcurrent	walletState
walletSysCurrency	walletUserCurrency

## Base AVP Diameter Fields

Table B–2 lists separately the base AVP fields that the **mip**t utility supports for the Diameter protocol. These fields are also listed in Table B–1, "Supported Fields of the Diameter Protocol".

**Table B–2 Base AVP Diameter Fields**

Base AVP Diameter Field Name	MIPT Field Name
Acct-Interim-Interval	acct_interim_interval
Accounting-Realtime-Required	accounting_realtime_required
Acct-Multi-Session-Id	acct_multi_session_id
Accounting-Record-Number	accounting_record_number
Accounting-Record-Type	accounting_record_type
Accounting-Session-Id	accounting_session_id
Accounting-Sub-Session-Id	accounting_sub_session_id
Acct-Application-Id	acct_application_id
Auth-Application-Id	auth_application_id
Auth-Request-Type	auth_request_type
Authorization-Lifetime	authorization_lifetime
Auth-Grace-Period	auth_grace_period
Auth-Session-State	auth_session_state
Re-Auth-Request-Type	re_auth_request_type
Class	class
Destination-Host	destination_host
Destination-Realm	destination_realm
Disconnect-Cause	disconnect_cause

**Table B-2 (Cont.) Base AVP Diameter Fields**

Base AVP Diameter Field Name	MIPT Field Name
Error-Message	error_message
Error-Reporting-Host	error_reporting_host
Event-Timestamp	event_timestamp
Experimental-Result	experimental_result
Experimental-Result-Code	experimental_result_code
Failed-AVP	failed_avp
Firmware-Revision	firmware_revision
Host-IP-Address	host_ip_address
Inband-Security-Id	inband_security_id
Multi-Round-Time-Out	multi_round_time_out
Origin-Host	origin_host
Origin-Realm	origin_realm
Origin-State-Id	origin_state_id
Product-Name	product_name
Proxy-Host	proxy_host
Proxy-Info	proxy_info
Proxy-State	proxy_state
Redirect-Host	redirect_host
Redirect-Host-Usage	redirect_host_usage
Redirect-Max-Cache-Time	redirect_max_cache_time
Result-Code	result_code
Route-Record	route_record
Session-Id	session_id
Session-Timeout	session_timeout
Session-Binding	session_binding
Session-Server-Failover	session_server_failover
Supported-Vendor-Id	supported_vendor_id
Termination-Cause	termination_cause
User-Name	user_name
Vendor-Id	vendor_id
Vendor-Specific-Application-Id	vendor_specific_application_id
CC-Correlation-Id	cc_correlation_id
CC-Input-Octets	cc_input_octets
CC-Money	cc_money
CC-Output-Octets	cc_output_octets
CC-Request-Number	cc_request_number
CC-Request-Type	cc_request_type

**Table B-2 (Cont.) Base AVP Diameter Fields**

<b>Base AVP Diameter Field Name</b>	<b>MIPT Field Name</b>
CC-Service-Specific-Units	cc_service_specific_units
CC-Session-Failover	cc_session_failover
CC-Sub-Session-Id	cc_sub_session_id
CC-Time	cc_time
CC-Total-Octets	cc_total_octets
CC-Unit-Type	cc_unit_type
Check-Balance-Result	check_balance_result
Cost-Information	cost_information
Cost-Unit	cost_unit
Credit-Control	credit_control
Credit-Control-Failure-Handling	credit_control_failure_handling
Currency-Code	currency_code
Direct-Debiting-Failure-Handling	direct_debiting_failure_handling
Exponent	exponent
Final-Unit-Action	final_unit_action
Final-Unit-Indication	final_unit_indication
Granted-Service-Unit	granted_service_unit
G-S-U-Pool-Identifier	g_s_u_pool_identifier
G-S-U-Pool-Reference	g_s_u_pool_reference
Multiple-Services-Credit-Control	multiple_services_credit_control
Multiple-Services-Indicator	multiple_services_indicator
Rating-Group	rating_group
Redirect-Address-Type	redirect_address_type
Redirect-Server	redirect_server
Redirect-Server-Address	redirect_server_address
Requested-Action	requested_action
Requested-Service-Unit	requested_service_unit
Restriction-Filter-Rule	restriction_filter_rule
Service-Context-Id	service_context_id
Service-Identifier	service_identifier
Service-Parameter-Info	service_parameter_info
Service-Parameter-Type	service_parameter_type
Service-Parameter-Value	service_parameter_value
Subscription-Id	subscription_id
Subscription-Id-Data	subscription_id_data
Subscription-Id-Type	subscription_id_type
Tariff-Change-Usage	tariff_change_usage

**Table B–2 (Cont.) Base AVP Diameter Fields**

Base AVP Diameter Field Name	MIPT Field Name
Tariff-Time-Change	tariff_time_change
Unit-Value	unit_value
Used-Service-Unit	used_service_unit
User-Equipment-Info	user_equipment_info
User-Equipment-Info-Type	user_equipment_info_type
User-Equipment-Info-Value	user_equipment_info_value
Value-Digits	value_digits
Validity-Time	validity_time

## Vendor-Specific Diameter Fields

Table B–3 lists the vendor-specific fields that the **mipt** utility supports for the Diameter protocol. These fields are also listed in Table B–1, "Supported Fields of the Diameter Protocol".

**Table B–3 Vendor-Specific Diameter Fields**

Vendor-Specific Diameter Field Name	MIPT Field Name	Vendor ID
Abort-Cause	3gpp_abort_cause	10415
Acceptable-Service-Info	3gpp_acceptable_service_info	10415
Access-Network-Charging-Address	3gpp_access_network_charging_address	10415
Access-Network-Charging-Identifier	3gpp_access_network_charging_identifier	10415
Access-Network-Charging-Identifier-Gx	3gpp_access_network_charging_identifier_gx	10415
Access-Network-Charging-Identifier-Value	3gpp_access_network_charging_identifier_value	10415
Access-Network-Information	3gpp_access_network_information	10415
Account-Expiration	3gpp_account_expiration	10415
Accumulated-Cost	3gpp_accumulated_cost	10415
Adaptations	3gpp_adaptations	10415
Additional-Content-Information	3gpp_additional_content_information	10415
Additional-MBMS-Trace-Info	3gpp_additional_mbms_trace_info	10415
Additional-Type-Information	3gpp_additional_type_information	10415
Address-Data	3gpp_address_data	10415
Address-Domain	3gpp_address_domain	10415
Address-Type	3gpp_address_type	10415
Addressee-Type	3gpp_addressee_type	10415
AF-Application-Identifier	3gpp_af_application_identifier	10415
AF-Charging-Identifier	3gpp_af_charging_identifier	10415



**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
AF-Correlation-Information	3gpp_af_correlation_information	10415
AF-Signalling-Protocol	3gpp_af_signalling_protocol	10415
Allocation-Retention-Priority	3gpp_allocation_retention_priority	10415
Alternate-Charged-Party-Address	3gpp_alternate_charged_party_address	10415
Alternative-APN	3gpp_alternative_apn	10415
AN-GW-Address	3gpp_an_gw_address	10415
AoC-Cost-Information	3gpp_aoc_cost_information	10415
AoC-Format	3gpp_aoc_format	10415
AoC-Information	3gpp_aoc_information	10415
AoC-Request-Type	3gpp_aoc_request_type	10415
AoC-Service	3gpp_aoc_service	10415
AoC-Service-Obligatory-Type	3gpp_aoc_service_obligatory_type	10415
AoC-Service-Type	3gpp_aoc_service_type	10415
AoC-Subscription-Information	3gpp_aoc_subscription_information	10415
APN-Aggregated-Max-Bitrate-DL	3gpp_apn_aggregated_max_bitrate_dl	10415
APN-Aggregated-Max-Bitrate-UL	3gpp_apn_aggregated_max_bitrate_ul	10415
Applic-Id	3gpp_applic_id	10415
Application-Provided-Called-Party-Address	3gpp_application_provided_called_party_address	10415
Application-Server	3gpp_application_server	10415
Application-Server-Information	3gpp_application_server_information	10415
Application-Service-Provider-Identity	3gpp_application_service_provider_identity	10415
Associated-Party-Address	3gpp_associated_party_address	10415
Associated-URI	3gpp_associated_uri	10415
Authorised-QoS	3gpp_authorised_qos	10415
Aux-Applic-Info	3gpp_aux_applic_info	10415
Base-Time-Interval	3gpp_base_time_interval	10415
Bearer-Control-Mode	3gpp_bearer_control_mode	10415
Bearer-Identifier	3gpp_bearer_identifier	10415
Bearer-Operation	3gpp_bearer_operation	10415
Bearer-Service	3gpp_bearer_service	10415
Bearer-Usage	3gpp_bearer_usage	10415
Billing-Information	3gpp_billing_information	10415
Called-Asserted-Identity	3gpp_called_asserted_identity	10415
Called-Party-Address	3gpp_called_party_address	10415
Calling-Party-Address	3gpp_calling_party_address	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Carrier-Select-Routing-Information	3gpp_carrier_select_routing_information	10415
Cause-Code	3gpp_cause_code	10415
CG-Address	3gpp_cg_address	10415
Change-Condition	3gpp_change_condition	10415
Change-Time	3gpp_change_time	10415
Charged-Party	3gpp_charged_party	10415
Charging-Characteristics-Selection-Mode	3gpp_charging_characteristics_selection_mode	10415
Charging-Correlation-Indicator	3gpp_charging_correlation_indicator	10415
Charging-Rule-Base-Name	3gpp_charging_rule_base_name	10415
Charging-Rule-Definition	3gpp_charging_rule_definition	10415
Charging-Rule-Install	3gpp_charging_rule_install	10415
Charging-Rule-Name	3gpp_charging_rule_name	10415
Charging-Rule-Remove	3gpp_charging_rule_remove	10415
Charging-Rule-Report	3gpp_charging_rule_report	10415
Class-Identifier	3gpp_class_identifier	10415
Client-Address	3gpp_client_address	10415
CN-IP-Multicast-Distribution	3gpp_cn_ip_multicast_distribution	10415
CoA-Information	3gpp_coa_information	10415
CoA-IP-Address	3gpp_coa_ip_address	10415
Codec-Data	3gpp_codec_data	10415
Content-Class	3gpp_content_class	10415
Content-Disposition	3gpp_content_disposition	10415
Content-Length	3gpp_content_length	10415
Content-Size	3gpp_content_size	10415
Content-Type	3gpp_content_type	10415
CSG-Access-Mode	3gpp_csg_access_mode	10415
CSG-Information-Reporting	3gpp_csg_information_reporting	10415
CSG-Membership-Indication	3gpp_csg_membership_indication	10415
CUG-Information	3gpp_cug_information	10415
Current-Tariff	3gpp_current_tariff	10415
Data-Coding-Scheme	3gpp_data_coding_scheme	10415
DCD-Information	3gpp_dcd_information	10415
Default-EPS-Bearer-QoS	3gpp_default_eps_bearer_qos	10415
Deferred-Location-Event-Type	3gpp_deferred_location_event_type	10415
Delivery-Report	3gpp_delivery_report	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Delivery-Report-Requested	3gpp_delivery_report_requested	10415
Diagnostics	3gpp_diagnostics	10415
Domain-Name	3gpp_domain_name	10415
DRM-Content	3gpp_drm_content	10415
Dynamic-Address-Flag	3gpp_dynamic_address_flag	10415
Dynamic-Address-Flag-Extension	3gpp_dynamic_address_flag_extension	10415
Early-Media-Description	3gpp_early_media_description	10415
Envelope	3gpp_envelope	10415
Envelope-End-Time	3gpp_envelope_end_time	10415
Envelope-Reporting	3gpp_envelope_reporting	10415
Envelope-Start-Time	3gpp_envelope_start_time	10415
Event	3gpp_event	10415
Event-Charging-TimeStamps	3gpp_event_charging_timestamps	10415
Event-Report-Indication	3gpp_event_report_indication	10415
Event-Trigger	3gpp_event_trigger	10415
Event-Type	3gpp_event_type	10415
Experimental-Result-Code	3gpp_experimental_result_code	10415
Expires	3gpp_expires	10415
File-Repair-Supported	3gpp_file_repair_supported	10415
Flow-Description	3gpp_flow_description	10415
Flow-Direction	3gpp_flow_direction	10415
Flow-Information	3gpp_flow_information	10415
Flow-Label	3gpp_flow_label	10415
Flow-Number	3gpp_flow_number	10415
Flow-Status	3gpp_flow_status	10415
Flow-Usage	3gpp_flow_usage	10415
Flows	3gpp_flows	10415
GGSN-Address	3gpp_ggsn_address	10415
Guaranteed-Bitrate-DL	3gpp_guaranteed_bitrate_dl	10415
Guaranteed-Bitrate-UL	3gpp_guaranteed_bitrate_ul	10415
IM-Information	3gpp_im_information	10415
IMS-Application-Reference-Identifier	3gpp_ims_application_reference_identifier	10415
IMS-Charging-Identifier	3gpp_ims_charging_identifier	10415
IMS-Communication-Service-Identifier	3gpp_ims_communication_service_identifier	10415
IMS-Information	3gpp_ims_information	10415

**Table B–3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
IMSI-Unauthenticated-Flag	3gpp_imsi_unauthenticated_flag	10415
Incoming-Trunk-Group-Id	3gpp_incoming_trunk_group_id	10415
Incremental-Cost	3gpp_incremental_cost	10415
Initial-IMS-Charging-Identifier	3gpp_initial_ims_charging_identifier	10415
Initial-Recipient-Address	3gpp_initial_recipient_address	10415
Inter-Operator-Identifier	3gpp_inter_operator_identifier	10415
Interface-Id	3gpp_interface_id	10415
Interface-Port	3gpp_interface_port	10415
Interface-Text	3gpp_interface_text	10415
Interface-Type	3gpp_interface_type	10415
IP-CAN-Type	3gpp_ip_can_type	10415
IP-REALM-Default-Indication	3gpp_ip_realm_default_indication	10415
LCS-Client-Dialed-By-MS	3gpp_lcs_client_dialed_by_ms	10415
LCS-Client-External-Id	3gpp_lcs_client_external_id	10415
LCS-Client-Id	3gpp_lcs_client_id	10415
LCS-Client-Name	3gpp_lcs_client_name	10415
LCS-Client-Type	3gpp_lcs_client_type	10415
LCS-Data-Coding-Scheme	3gpp_lcs_data_coding_scheme	10415
LCS-Format-Indicator	3gpp_lcs_format_indicator	10415
LCS-Information	3gpp_lcs_information	10415
LCS-Name-String	3gpp_lcs_name_string	10415
LCS-Requestor-Id	3gpp_lcs_requestor_id	10415
LCS-Requestor-Id-String	3gpp_lcs_requestor_id_string	10415
Local-GW-Inserted-Indication	3gpp_local_gw_inserted_indication	10415
Local-Sequence-Number	3gpp_local_sequence_number	10415
Location-Estimate	3gpp_location_estimate	10415
Location-Estimate-Type	3gpp_location_estimate_type	10415
Location-Type	3gpp_location_type	10415
Low-Balance-Indication	3gpp_low_balance_indication	10415
Low-Priority-Indicator	3gpp_low_priority_indicator	10415
Max-Bandwidth-UL	3gpp_max_bandwidth_ul	10415
Max-Requested-Bandwidth-DL	3gpp_max_requested_bandwidth_dl	10415
Max-Supported-Bandwidth-DL	3gpp_max_supported_bandwidth_dl	10415
Max-Supported-Bandwidth-UL	3gpp_max_supported_bandwidth_ul	10415
Maximum-Bandwidth	3gpp_maximum_bandwidth	10415
MBMS-2G-3G-Indicator	3gpp_mbms_2g_3g_indicator	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
MBMS-Access-Indicator	3gpp_mbms_access_indicator	10415
MBMS-BMSC-SSM-IP-Address	3gpp_mbms_bmsc_ssm_ip_address	10415
MBMS-BMSC-SSM-IPv6-Address	3gpp_mbms_bmsc_ssm_ipv6_address	10415
MBMS-BMSC-SSM-UDP-Port	3gpp_mbms_bmsc_ssm_udp_port	10415
MBMS-Counting-Information	3gpp_mbms_counting_information	10415
MBMS-Flow-Identifier	3gpp_mbms_flow_identifier	10415
MBMS-GGSN-Address	3gpp_mbms_ggsn_address	10415
MBMS-GGSN-IPv6-Address	3gpp_mbms_ggsn_ipv6_address	10415
MBMS-GW-Address	3gpp_mbms_gw_address	10415
MBMS-GW-SSM-IP-Address	3gpp_mbms_gw_ssm_ip_address	10415
MBMS-GW-SSM-IPv6-Address	3gpp_mbms_gw_ssm_ipv6_address	10415
MBMS-GW-UDP-Port	3gpp_mbms_gw_udp_port	10415
MBMS-GW-UDP-Port-Indicator	3gpp_mbms_gw_udp_port_indicator	10415
MBMS-HC-Indicator	3gpp_mbms_hc_indicator	10415
MBMS-Information	3gpp_mbms_information	10415
MBMS-Service-Area	3gpp_mbms_service_area	10415
MBMS-Service-Type	3gpp_mbms_service_type	10415
MBMS-Session-Duration	3gpp_mbms_session_duration	10415
MBMS-Session-Identity	3gpp_mbms_session_identity	10415
MBMS-Session-Repetition-Number	3gpp_mbms_session_repetition_number	10415
MBMS-StartStop-Indication	3gpp_mbms_startstop_indication	10415
MBMS-Time-To-Data-Transfer	3gpp_mbms_time_to_data_transfer	10415
MBMS-User-Data-Mode-Indication	3gpp_mbms_user_data_mode_indication	10415
MBMS-User-Service-Type	3gpp_mbms_user_service_type	10415
Media-Component-Description	3gpp_media_component_description	10415
Media-Component-Number	3gpp_media_component_number	10415
Media-Initiator-Flag	3gpp_media_initiator_flag	10415
Media-Initiator-Party	3gpp_media_initiator_party	10415
Media-Sub-Component	3gpp_media_sub_component	10415
Media-Type	3gpp_media_type	10415
Message-Body	3gpp_message_body	10415
Message-Class	3gpp_message_class	10415
Message-Id	3gpp_message_id	10415
Message-Size	3gpp_message_size	10415
Message-Type	3gpp_message_type	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Metering-Method	3gpp_metering_method	10415
Min-Requested-Bandwidth-DL	3gpp_min_requested_bandwidth_dl	10415
Min-Requested-Bandwidth-UL	3gpp_min_requested_bandwidth_ul	10415
MM10-Recipient-Address	3gpp_mm10_recipient_address	10415
MM-Content-Type	3gpp_mm_content_type	10415
MMBox-Storage-Requested	3gpp_mmbox_storage_requested	10415
MMS-Information	3gpp_mms_information	10415
MMTel-Information	3gpp_mmtel_information	10415
Monitoring-Key	3gpp_monitoring_key	10415
MPS-Identifier	3gpp_mps_identifier	10415
Network-Request-Support	3gpp_network_request_support	10415
Next-Tariff	3gpp_next_tariff	10415
Node-Functionality	3gpp_node_functionality	10415
Node-Id	3gpp_node_id	10415
Number-Of-Diversions	3gpp_number_of_diversions	10415
Number-Of-Messages-Sent	3gpp_number_of_messages_sent	10415
Number-Of-Participants	3gpp_number_of_participants	10415
Number-Of-Received-Talk-Bursts	3gpp_number_of_received_talk_bursts	10415
Number-Of-Talk-Bursts	3gpp_number_of_talk_bursts	10415
Number-Portability-Routing-Information	3gpp_number_portability_routing_information	10415
Offline	3gpp_offline	10415
Offline-Charging	3gpp_offline_charging	10415
Online	3gpp_online	10415
Online-Charging-Flag	3gpp_online_charging_flag	10415
Originating-Interface	3gpp_originating_interface	10415
Originating-IOI	3gpp_originating_ioi	10415
Originator	3gpp_originator	10415
Originator-Address	3gpp_originator_address	10415
Originator-Received-Address	3gpp_originator_received_address	10415
Originator-SCCP-Address	3gpp_originator_sccp_address	10415
Outgoing-Session-Id	3gpp_outgoing_session_id	10415
Outgoing-Trunk-Group-Id	3gpp_outgoing_trunk_group_id	10415
Packet-Filter-Content	3gpp_packet_filter_content	10415
Packet-Filter-Identifier	3gpp_packet_filter_identifier	10415
Packet-Filter-Information	3gpp_packet_filter_information	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Packet-Filter-Operation	3gpp_packet_filter_operation	10415
Packet-Filter-Usage	3gpp_packet_filter_usage	10415
Participant-Access-Priority	3gpp_participant_access_priority	10415
Participant-Action-Type	3gpp_participant_action_type	10415
Participant-Group	3gpp_participant_group	10415
Participants-Involved	3gpp_participants_involved	10415
PCC-Rule-Status	3gpp_pcc_rule_status	10415
PDG-Address	3gpp_pdg_address	10415
PDG-Charging-Id	3gpp_pdg_charging_id	10415
PDN-Connection-Charging-Id	3gpp_pdn_connection_charging_id	10415
PDN-Connection-Id	3gpp_pdn_connection_id	10415
PDP-Address	3gpp_pdp_address	10415
PDP-Address-Prefix-Length	3gpp_pdp_address_prefix_length	10415
PDP-Context-Type	3gpp_pdp_context_type	10415
PoC-Change-Condition	3gpp_poc_change_condition	10415
PoC-Change-Time	3gpp_poc_change_time	10415
PoC-Controlling-Address	3gpp_poc_controlling_address	10415
PoC-Event-Type	3gpp_poc_event_type	10415
PoC-Group-Name	3gpp_poc_group_name	10415
PoC-Information	3gpp_poc_information	10415
PoC-Server-Role	3gpp_poc_server_role	10415
PoC-Session-Id	3gpp_poc_session_id	10415
PoC-Session-Initiation-Type	3gpp_poc_session_initiation_type	10415
PoC-Session-Type	3gpp_poc_session_type	10415
PoC-User-Role	3gpp_poc_user_role	10415
PoC-User-Role-IDs	3gpp_poc_user_role_ids	10415
Poc-User-Role-Info-Units	3gpp_poc_user_role_info_units	10415
Positioning-Data	3gpp_positioning_data	10415
Pre-Emption-Capability	3gpp_pre_emption_capability	10415
Precedence	3gpp_precedence	10415
Preemption-Vulnerability	3gpp_preemption_vulnerability	10415
Preferred-AoC-Currency	3gpp_preferred_aoc_currency	10415
Priority	3gpp_priority	10415
Priority-Level	3gpp_priority_level	10415
PS-Append-Free-Format-Data	3gpp_ps_append_free_format_data	10415
PS-Free-Format-Data	3gpp_ps_free_format_data	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
PS-Furnish-Charging-Information	3gpp_ps_furnish_charging_information	10415
PS-Information	3gpp_ps_information	10415
QoS-Class-Identifier	3gpp_qos_class_identifier	10415
QoS-Information	3gpp_qos_information	10415
QoS-Negotiation	3gpp_qos_negotiation	10415
QoS-Rule-Base-Name	3gpp_qos_rule_base_name	10415
QoS-Rule-Definition	3gpp_qos_rule_definition	10415
QoS-Rule-Install	3gpp_qos_rule_install	10415
QoS-Rule-Name	3gpp_qos_rule_name	10415
QoS-Rule-Remove	3gpp_qos_rule_remove	10415
QoS-Rule-Report	3gpp_qos_rule_report	10415
QoS-Upgrade	3gpp_qos_upgrade	10415
Quota-Consumption-Time	3gpp_quota_consumption_time	10415
Quota-Holding-Time	3gpp_quota_holding_time	10415
RAI	3gpp_rai	10415
RAT-Type	3gpp_rat_type	10415
Rate-Element	3gpp_rate_element	10415
Read-Reply	3gpp_read_reply	10415
Read-Reply-Report-Requested	3gpp_read_reply_report_requested	10415
Real-Time-Tariff-Information	3gpp_real_time_tariff_information	10415
Reason-Code	3gpp_reason_code	10415
Received-Talk-Burst-Time	3gpp_received_talk_burst_time	10415
Received-Talk-Burst-Volume	3gpp_received_talk_burst_volume	10415
Recipient-Address	3gpp_recipient_address	10415
Recipient-Info	3gpp_recipient_info	10415
Recipient-Received-Address	3gpp_recipient_received_address	10415
Recipient-SCCP-Address	3gpp_recipient_sccp_address	10415
Refund-Information	3gpp_refund_information	10415
Remaining-Balance	3gpp_remaining_balance	10415
Reply-Applic-Id	3gpp_reply_applic_id	10415
Reply-Path-Requested	3gpp_reply_path_requested	10415
Reporting-Level	3gpp_reporting_level	10415
Reporting-Reason	3gpp_reporting_reason	10415
Requested-Party-Address	3gpp_requested_party_address	10415
Required-MBMS-Bearer-Capabilities	3gpp_required_mbms_bearer_capabilities	10415



**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Resource-Allocation-Notification	3gpp_resource_allocation_notification	10415
Result-Recipient-Address	3gpp_result_recipient_address	10415
Revalidation-Time	3gpp_revalidation_time	10415
Role-Of-Node	3gpp_role_of_node	10415
Routeing-Address	3gpp_routeing_address	10415
Routeing-Address-Resolution	3gpp_routeing_address_resolution	10415
Routing-Filter	3gpp_routing_filter	10415
Routing-IP-Address	3gpp_routing_ip_address	10415
Routing-Rule-Definition	3gpp_routing_rule_definition	10415
Routing-Rule-Identifier	3gpp_routing_rule_identifier	10415
Routing-Rule-Install	3gpp_routing_rule_install	10415
Routing-Rule-Remove	3gpp_routing_rule_remove	10415
RR-Bandwidth	3gpp_rr_bandwidth	10415
RS-Bandwidth	3gpp_rs_bandwidth	10415
Rule-Activation-Time	3gpp_rule_activation_time	10415
Rule-Deactivation-Time	3gpp_rule_deactivation_time	10415
Rule-Failure-Code	3gpp_rule_failure_code	10415
Scale-Factor	3gpp_scale_factor	10415
SDP-Answer-Timestamp	3gpp_sdp_answer_timestamp	10415
SDP-Media-Component	3gpp_sdp_media_component	10415
SDP-Media-Description	3gpp_sdp_media_description	10415
SDP-Media-Name	3gpp_sdp_media_name	10415
SDP-Offer-Timestamp	3gpp_sdp_offer_timestamp	10415
SDP-Session-Description	3gpp_sdp_session_description	10415
SDP-TimeStamps	3gpp_sdp_timestamps	10415
SDP-Type	3gpp_sdp_type	10415
Security-Parameter-Index	3gpp_security_parameter_index	10415
Sender-Address	3gpp_sender_address	10415
Sender-Visibility	3gpp_sender_visibility	10415
Sequence-Number	3gpp_sequence_number	10415
Served-Party-IP-Address	3gpp_served_party_ip_address	10415
Served-User-Identity	3gpp_served_user_identity	10415
Service-Data-Container	3gpp_service_data_container	10415
Service-Generic-Information	3gpp_service_generic_information	10415
Service-Id	3gpp_service_id	10415
Service-Info-Status	3gpp_service_info_status	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Service-Information	3gpp_service_information	10415
Service-Key	3gpp_service_key	10415
Service-Mode	3gpp_service_mode	10415
Service-Specific-Data	3gpp_service_specific_data	10415
Service-Specific-Info	3gpp_service_specific_info	10415
Service-Specific-Type	3gpp_service_specific_type	10415
Service-Type	3gpp_service_type	10415
Service-URN	3gpp_service_urn	10415
Serving-Node-Type	3gpp_serving_node_type	10415
Session-Linking-Indicator	3gpp_session_linking_indicator	10415
Session-Release-Cause	3gpp_session_release_cause	10415
SGSN-Address	3gpp_sgsn_address	10415
SGW-Address	3gpp_sgw_address	10415
SGW-Change	3gpp_sgw_change	10415
SIP-Forking-Indication	3gpp_sip_forking_indication	10415
SIP-Method	3gpp_sip_method	10415
SIP-Request-Timestamp	3gpp_sip_request_timestamp	10415
SIP-Request-Timestamp-Fraction	3gpp_sip_request_timestamp_fraction	10415
SIP-Response-Timestamp	3gpp_sip_response_timestamp	10415
SIP-Response-Timestamp-Fraction	3gpp_sip_response_timestamp_fraction	10415
SM-Discharge-Time	3gpp_sm_discharge_time	10415
SM-Message-Type	3gpp_sm_message_type	10415
SM-Protocol-Id	3gpp_sm_protocol_id	10415
SM-Service-Type	3gpp_sm_service_type	10415
SM-Status	3gpp_sm_status	10415
SM-User-Data-Header	3gpp_sm_user_data_header	10415
SMS-Information	3gpp_sms_information	10415
SMS-Node	3gpp_sms_node	10415
SMSC-Address	3gpp_smsc_address	10415
Specific-Action	3gpp_specific_action	10415
Sponsor-Identity	3gpp_sponsor_identity	10415
Sponsored-Connectivity-Data	3gpp_sponsored_connectivity_data	10415
Start-Time	3gpp_start_time	10415
Status	3gpp_status	10415
Status-Code	3gpp_status_code	10415
Status-Text	3gpp_status_text	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Stop-Time	3gpp_stop_time	10415
Submission-Time	3gpp_submission_time	10415
Subscriber-Role	3gpp_subscriber_role	10415
Supplementary-Service	3gpp_supplementary_service	10415
Talk-Burst-Exchange	3gpp_talk_burst_exchange	10415
Talk-Burst-Time	3gpp_talk_burst_time	10415
Talk-Burst-Volume	3gpp_talk_burst_volume	10415
Tariff-Information	3gpp_tariff_information	10415
Tariff-XML	3gpp_tariff_xml	10415
Terminating-IOI	3gpp_terminating_ioi	10415
TFT-Filter	3gpp_tft_filter	10415
TFT-Packet-Filter-Information	3gpp_tft_packet_filter_information	10415
Time-First-Usage	3gpp_time_first_usage	10415
Time-Last-Usage	3gpp_time_last_usage	10415
Time-Quota-Mechanism	3gpp_time_quota_mechanism	10415
Time-Quota-Threshold	3gpp_time_quota_threshold	10415
Time-Quota-Type	3gpp_time_quota_type	10415
Time-Stamps	3gpp_time_stamps	10415
Time-Usage	3gpp_time_usage	10415
TMGI	3gpp_tmgi	10415
Token-Text	3gpp_token_text	10415
ToS-Traffic-Class	3gpp_tos_traffic_class	10415
Traffic-Data-Volumes	3gpp_traffic_data_volumes	10415
Transcoder-Inserted-Indication	3gpp_transcoder_inserted_indication	10415
Trigger	3gpp_trigger	10415
Trigger-Event	3gpp_trigger_event	10415
Trigger-Type	3gpp_trigger_type	10415
Trunk-Group-Id	3gpp_trunk_group_id	10415
Tunnel-Header-Filter	3gpp_tunnel_header_filter	10415
Tunnel-Header-Length	3gpp_tunnel_header_length	10415
Tunnel-Information	3gpp_tunnel_information	10415
Type-Number	3gpp_type_number	10415
Unit-Cost	3gpp_unit_cost	10415
Unit-Quota-Threshold	3gpp_unit_quota_threshold	10415
Usage-Monitoring-Information	3gpp_usage_monitoring_information	10415
Usage-Monitoring-Level	3gpp_usage_monitoring_level	10415

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
Usage-Monitoring-Report	3gpp_usage_monitoring_report	10415
Usage-Monitoring-Support	3gpp_usage_monitoring_support	10415
User-CSG-Information	3gpp_user_csg_information	10415
User-Participating-Type	3gpp_user_participating_type	10415
User-Session-Id	3gpp_user_session_id	10415
VAS-Id	3gpp_vas_id	10415
VASP-Id	3gpp_vasp_id	10415
Volume-Quota-Threshold	3gpp_volume_quota_threshold	10415
WAG-Address	3gpp_wag_address	10415
WAG-PLMN-Id	3gpp_wag_plmn_id	10415
WLAN-Information	3gpp_wlan_information	10415
WLAN-Radio-Container	3gpp_wlan_radio_container	10415
WLAN-Session-Id	3gpp_wlan_session_id	10415
WLAN-Technology	3gpp_wlan_technology	10415
WLAN-UE-Local-IPAddress	3gpp_wlan_ue_local_ipaddress	10415
eServGlobal-Address	esg_address	16247
eServGlobal-DiamIdent	esg_diamident	16247
eServGlobal-DiamURI	esg_diamuri	16247
eServGlobal-Enumerated	esg_enumerated	16247
eServGlobal-Grouped	esg_grouped	16247
eServGlobal-Integer32	esg_integer32	16247
eServGlobal-Integer64	esg_integer64	16247
eServGlobal-IPFiltrRule	esg_ipfiltrrule	16247
eServGlobal-OctetString	esg_octetstring	16247
eServGlobal-Time	esg_time	16247
eServGlobal-Unsigned32	esg_unsigned32	16247
eServGlobal-Unsigned64	esg_unsigned64	16247
eServGlobal-UTF8String	esg_utf8string	16247
eServGlobal-Grouped	esg_grouped_1	16247
eServGlobal-Grouped	esg_grouped_2	16247
eServGlobal-Grouped	esg_grouped_3	16247
eServGlobal-Grouped	esg_grouped_4	16247
eServGlobal-Grouped	esg_grouped_5	16247
eServGlobal-UTF8String	esg_utf8string_1	16247
eServGlobal-UTF8String	esg_utf8string_2	16247
eServGlobal-UTF8String	esg_utf8string_3	16247

**Table B-3 (Cont.) Vendor-Specific Diameter Fields**

<b>Vendor-Specific Diameter Field Name</b>	<b>MIPT Field Name</b>	<b>Vendor ID</b>
eServGlobal-Integer32	esg_integer32_1	16247
eServGlobal-Integer32	esg_integer32_2	16247
eServGlobal-Integer32	esg_integer32_3	16247
Balance-Expiry	balanceExpiry	16247
Balance-MaxCredit	balanceMaxCredit	16247
Balance-LimitType	balanceLimitType	16247
Balance-Unit	balanceUnit	16247
Balance-Value	balanceValue	16247
Balance-Value	balanceUserValue	16247
Balance-Type	balanceType	16247
Balance-Information	balanceInfo	16247
Wallet-Information	walletInfo	16247
Wallet-Expiry	walletExpiry	16247
Wallet-State	walletState	16247
Wallet-LastAccessed	walletLastAccessed	16247
Wallet-ActivationDate	walletActivationDate	16247
Wallet-MaxConcurrent	walletMaxConcurrent	16247
Wallet-SystemCurrency	walletSysCurrency	16247
Wallet-SystemCurrency	walletUserCurrency	16247
Charge-Information	chargeInfo	16247
Charge	charge	16247
Charge-Balance-Type	chargeBalanceType	16247
Charge-Balance-Value	chargeBalanceValue	16247
Charge-Balance-Unit	chargeBalanceUnit	16247
Voucher-Information	voucherInfo	16247
Voucher-Info-Voucher	voucherInfoVoucher	16247
Voucher-Info-Wallet-Expiry-Extension	voucherInfoWalletExpiryExtension	16247
Voucher-Info-Wallet-Expiry-Extension-Policy	voucherInfoWalletExpiryExtensionPolicy	16247
Voucher-Info-Wallet-Expiry-Extension-Type	voucherInfoWalletExpiryExtensionType	16247
Voucher-Balance	voucherBalance	16247
Voucher-Info-Balance-Type	voucherInfoBalanceType	16247
Voucher-Info-Value	voucherInfoValue	16247
Voucher-Info-Balance-Expiry-Extension	voucherInfoBalanceExpiryExtension	16247
Voucher-Info-Voucher-Expiry-Extension-Policy	voucherInfoBalanceExpiryExtensionPolicy	16247

**Table B–3 (Cont.) Vendor-Specific Diameter Fields**

Vendor-Specific Diameter Field Name	MIPT Field Name	Vendor ID
Voucher-Info-Balance-Expiry-Extension-Type	voucherInfoBalanceExpiryExtensionType	16247
Voucher-Info-New-Bucket	voucherInfoNewBucket	16247
Voucher-Info-Missing-Balance-Policy	voucherInfoMissingBalancePolicy	16247
Voucher-Info-Replace-Balance	voucherInfoReplaceBalance	16247
Voucher-Type	voucherTypeName	16247
Charging-Start-Timestamp	chargingStartTimestamp	16247
Top-Up-Voucher-Number	topUpVoucherNumber	16247
Top-Up-Voucher-Id	topUpVoucherId	16247
Top-Up-Amount	topUpAmount	16247
Voucher-Value-Digits	topUpValueDigits	16247
Top-Up-Voucher-Type	topUpVoucherType	16247
3GPP-IMSI	3gpp_imsi	10415
3GPP-Charging-Id	3gpp_charging_id	10415
3GPP-SGSN-MCC-MNC	3gpp_sgsn_mcc_mnc	10415
MSISDN	3gpp_msisdn	10415
User-Location-Information	3gpp_user_location_information	10415
Fail-If-Below-Threshold	awcc_fail_if_below_threshold	16247
Charging-Start-Timestamp	awcc_charging_start_timestamp	16247
Product-Type	awcc_product_type	16247
Policy-Control	awcc_policy_control	16247
Calling-Party-Presentation-Indicator	awcc_calling_party_presentation_indicator	16247
Data-Source-System	awcc_data_source_system	16247
Data-Application-Id	awcc_data_application_id	16247
Data-Transaction-Id	awcc_data_transaction_id	16247
Balance-Information	awcc_balance_information	16247
Balance-Type-Id	awcc_balance_type_id	16247
Balance-Expire-Date	awcc_balance_expire_date	16247

## Supported Fields for the EMI Protocol

Table B–4 lists the fields of the EMI protocol that the **mipt** utility supports.

**Table B–4 Supported Fields for the EMI Protocol**

EMI Field Name	EMI Field Name
AC	ACK
AdC	AMsg
call_input	call_input_ack

**Table B-4 (Cont.) Supported Fields for the EMI Protocol**

<b>EMI Field Name</b>	<b>EMI Field Name</b>
call_input_nack	call_input_with_supplementary_services
call_input_with_supplementary_services_ack	call_input_with_supplementary_services_nack
CPg	CSUM
DCs	DD
DDT	delete_message
delete_message_ack	delete_message_nack
deliver_sm	deliver_sm_ack
deliver_sm_nack	delivery_notification
delivery_notification_ack	delivery_notification_nack
DSCTS	Dst
EC	GAs
HPLMN	inquiry_message
inquiry_message_ack	inquiry_message_nack
LAdC	LEN
LNPI	LPID
LPR	LRAd
LRC	LRq
LTON	LUR
MCLs	MMS
modify_sm	modify_sm_ack
modify_sm_nack	ms_message_transfer
ms_message_transfer_ack	ms_message_transfer_nack
MT	mt_alert
mt_alert_ack	mt_alert_nack
multiple_address_call_input	multiple_address_call_input_ack
multiple_address_call_input_nack	MVP
NACK	NAd
NAdC	NB
NMsg	NPID
NPL	NPWD
NRq	NT
O_R	OAdC
ONPI	OPID
OT	OTOA
OTON	PID
PR	provisioning_actions

**Table B–4 (Cont.) Supported Fields for the EMI Protocol**

EMI Field Name	EMI Field Name
provisioning_actions_ack	provisioning_actions_nack
PWD	RAd
RAds	RC
RES1	RES2
RES4	RES5
response_delete_message	response_delete_message_ack
response_delete_message_nack	response_inquiry_message
response_inquiry_message_ack	response_inquiry_message_nack
RP	RPI
RPID	RPLy
Rsn	SCTS
session_management	session_management_ack
session_management_nack	SM
STYP	submit_sm
submit_sm_ack	submit_sm_nack
TMsg	TRN
UR	VERS
VP	XSer

## Supported Fields of the M3UA Protocol

Table B–5 lists the fields of the M3UA protocol that the **mipt** utility supports.

**Table B–5 Supported Fields for the M3UA Protocol**

M3UA Field Name	M3UA Field Name
affected_point_code	asp_active
asp_active_acknowledgement	asp_down
asp_down_acknowledgement	asp_identifier
asp_inactive	asp_inactive_acknowledgement
asp_up	asp_up_acknowledgement
ASPAC	ASPAC_ACK
ASPDN	ASPDN_ACK
ASPIA	ASPIA_ACK
ASPUP	ASPUP_ACK
BEAT	BEAT_ACK
concerned_destination	congestion_indications
control_word	correlation_id
DATA	DAUD
DAVA	DEREG_REQ



**Table B–5 (Cont.) Supported Fields for the M3UA Protocol**

<b>M3UA Field Name</b>	<b>M3UA Field Name</b>
DEREG_RSP	deregistration_request
deregistration_response	deregistration_result
deregistration_status	destination_available
destination_point_code	destination_restricted
destination_state_audit	destination_unavailable
destination_user_part_unavailable	diagnostic_info
DRST	DUNA
DUPU	ERR
error	error_code
heartbeat	heartbeat_acknowledgement
heartbeat_data	info_string
local_routing_key_identifier	network_appearance
notify	NTFY
originating_point_code	originating_point_code_list
payload_data	protocol_data
REG_REQ	REG_RSP
registration_request	registration_response
registration_result	registration_status
routing_context	routing_key
SCON	service_indicators
signalling_congestion	status
traffic_mode_type	user_cause

## Supported Fields of the RADIUS Protocol

Table B–6 lists the fields of the RADIUS protocol that the **mip**t utility supports.

**Table B–6 Supported Fields for the Radius Protocol**

<b>RADIUS Field Name</b>	<b>RADIUS Field Name</b>
3GGP_CAMEL_CHARGING_INFO	3GGP_CG_ADDRESS
3GGP_GGSN_ADDRESS	3GGP_IMEISV
3GGP_MS_TIMEZONE	3GGP_SGSN_ADDRESS
3GGP_USER_LOCATION_INFO	3GPP_CAMEL_CHARGING_INFO
3GPP_CG_ADDRESS	3GPP_CG_IPV6_ADDRESS
3GPP_CHARGING_CHARACTERISTICS	3GPP_CHARGING_ID
3GPP_GGSN_ADDRESS	3GPP_GGSN_IPV6_ADDRESS
3GPP_GGSN_MCC_MNC	3GPP_GPRS_QOS_PROFILE
3GPP_IMEISV	3GPP_IMSI
3GPP_IMSI_MCC_MNC	3GPP_IPV6_DNS_SERVER

**Table B-6 (Cont.) Supported Fields for the Radius Protocol**

<b>RADIUS Field Name</b>	<b>RADIUS Field Name</b>
3GPP_MS_TIMEZONE	3GPP_NSAPI
3GPP_PDP_TYPE	3GPP_QOS_PROFILE
3GPP_RAT_TYPE	3GPP_SELECTION_MODE
3GPP_SESSION_STOP_INDICATOR	3GPP_SGSN_ADDRESS
3GPP_SGSN_IPV6_ADDRESS	3GPP_SGSN_MCC_MNC
3GPP_USER_LOCATION_INFO	access_accept
access_challenge	access_reject
access_request	accounting_container
accounting_request	accounting_response
accounting_stop_triggered_by_active_stop_indication	acct_authentic
acct_delay_time	acct_input_gigawords
acct_input_octets	acct_input_packets
acct_interim_interval	acct_link_count
acct_multi_session_id	acct_output_gigawords
acct_output_octets	acct_output_packets
acct_session_id	acct_session_time
acct_status_type	acct_terminate_cause
active_time	air_priority
airlink_priority	allowed_differentiated_services_marking
allowed_differentiated_services_marking__class	allowed_differentiated_services_marking__max
allowed_differentiated_services_marking__reverse_tunnel	allowed_persistent_tfts
always_on	always_ON
arap_challenge_response	arap_features
arap_password	arap_security
arap_security_data	arap_zone_access
authenticator	bad_frame_count
bad_ppp_frame_count	begin_session
beginning_session	bsid
BSID	callback_id
callback_number	called_station_id
calling_station_id	chap_challenge
chap_password	CISCO_STRING
class	coa_ack
coa_nak	coa_request
comp_flag	compulsory_tunnel_indicator

**Table B-6 (Cont.) Supported Fields for the Radius Protocol**

<b>RADIUS Field Name</b>	<b>RADIUS Field Name</b>
configuration_token	connect_info
correlation_id	dcch_frame_size
DFSIZE	differentiated_services_class_option
disconnect_ack	disconnect_nak
disconnect_request	disconnectreason
dns_update_capability	dns_update_required
eap_message	error_cause
esn	ESN
event_timestamp	F_DCCH_MUX
F_FCH_MUX	F_PDCH_RC
FA_CoA	fch_frame_size
FDRC	FFSIZE
filter_id	foreign_agent_address
forward_dcch_mux_option	forward_dcch_rc
forward_fch_mux_option	forward_fch_rc
forward_pdch_rc	forward_traffic_type
framed_appletalk_link	framed_appletalk_network
framed_appletalk_zone	framed_compression
framed_interface_id	framed_ip_address
framed_ip_netmask	framed_ipv6_pool
framed_ipv6_prefix	framed_ipv6_route
framed_ipx_network	framed_mtu
framed_pool	framed_protocol
framed_route	framed_routing
FRC	FTYPE
HA_IP_addr	home_agent
identifier	idle_timeout
ike_pre_shared_secret_request	ip_host
ip_port	IP_QOS
ip_quality_of_service	IP_tech
ip_technology	keyid
login_ip_host	login_ipv6_host
login_lat_group	login_lat_node
login_lat_port	login_lat_service
login_service	login_tcp_port
message_authenticator	mip_lifetime
mip_lifetime__rrq_lifetime	mip_lifetime__used_lifetime

**Table B-6 (Cont.) Supported Fields for the Radius Protocol**

<b>RADIUS Field Name</b>	<b>RADIUS Field Name</b>
mn_aaa_removal_indication	mn_ha_shared_key
mn_ha_spi	MS_PRIMARY_DNS
MS_PRIMARY_NBNS	MS_SECONDARY_DNS
MS_SECONDARY_NBNS	nas_identifier
nas_ip_address	nas_ipv6_address
nas_port	nas_port_id
nas_port_type	num_active
num_bytes_received	number_of_active_transitions
number_of_hdlc_layer_octets_received	number_of_sdbb_originating
number_of_sdbb_terminating	NumSDB_input
NumSDB_output	password_retry
PCF	port_limit
PPAC	PPAC__AiC
PPAC__available_in_client	PPAC__selected_for_session
PPAC__SfS	PPAQ
PPAQ__DQ	PPAQ__DT
PPAQ__duration_quota	PPAQ__duration_threshold
PPAQ__pre_paid_server	PPAQ__QID
PPAQ__quota_identifier	PPAQ__update_reason
PPAQ__UR	PPAQ__volume_quota
PPAQ__volume_quota_overflow	PPAQ__volume_threshold
PPAQ__volume_threshold_overflow	PPAQ__VQ
PPAQ__VQO	PPAQ__VT
PPAQ__VTO	pre_paid_accounting_capability
pre_paid_accounting_quota	pre_paid_tariff_switching
pre_shared_secret	prompt
proxy_state	PTS
PTS__QID	PTS__quota_identifier
PTS__tariff_switch_interval	PTS__time_interval_after_tariff_switch_update
PTS__TITSU	PTS__TSI
PTS__volume_used_after_tariff_switch	PTS__volume_used_ats_overflow
PTS__VUATS	PTS__VUATSO
R_DCCH_MUX	R_FCH_MUX
RDRC	reason_ind
release_indicator	remote_address_table_index
remote_address_table_index__qualifier	remote_address_table_index__table_index

**Table B-6 (Cont.) Supported Fields for the Radius Protocol**

<b>RADIUS Field Name</b>	<b>RADIUS Field Name</b>
remote_ipv4_address	remote_ipv4_address__address
remote_ipv4_address__mask	remote_ipv4_address__qualifier
remote_ipv4_address_octet_count	remote_ipv4_address_octet_count__address
remote_ipv4_address_octet_count__forward_octet_count	remote_ipv4_address_octet_count__forward_overflow
remote_ipv4_address_octet_count__mask	remote_ipv4_address_octet_count__reverse_octet_count
remote_ipv4_address_octet_count__reverse_overflow	remote_ipv4_address_octet_count__table_index
remote_ipv6_address	remote_ipv6_address__address
remote_ipv6_address__prefix_length	remote_ipv6_address__qualifier
remote_ipv6_address_octet_count	remote_ipv6_address_octet_count__address
remote_ipv6_address_octet_count__forward_octet_count	remote_ipv6_address_octet_count__forward_overflow
remote_ipv6_address_octet_count__prefix_length	remote_ipv6_address_octet_count__reverse_octet_count
remote_ipv6_address_octet_count__reverse_overflow	remote_ipv6_address_octet_count__table_index
reply_message	request_message_to_the_home_radius_server
reverse_dcch_mux_option	reverse_dcch_rc
reverse_fch_mux_option	reverse_fch_rc
reverse_tunnel_specification	rn_packet_data_inactivity_timer
RRC	s_key
s_lifetime	SDB_input_octets
sdb_octet_count_originating	sdb_octet_count_terminating
SDB_output_octet	secret
security_level	service_option
service_option_profile	service_reference_id
service_type	serving_pcf
session_cont	session_continue
session_termination_capability	session_timeout
sf_access_point_id	SF_API
SO	SR_ID
SR_ID__main_si_indicator	SR_ID__sr_id
state	STC
termination_action	user_ID
user_name	user_password
user_zone	vendor_specific

## Supported Vendor-Specific Fields of the RADIUS Protocol

Table B–7 lists vendor-specific fields of the RADIUS protocol that the **mipt** utility supports. These fields are also listed in Table B–6, "Supported Fields for the Radius Protocol".

**Table B–7 Supported Vendor-Specific RADIUS Fields**

Vendor-Specific RADIUS Field	Vendor-Specific RADIUS Field
3GPP_CAMEL_CHARGING_INFO	3GPP_CG_ADDRESS
3GPP_CG_IPV6_ADDRESS	3GPP_CHARGING_CHARACTERISTICS
3GPP_CHARGING_ID	3GPP_GGSN_ADDRESS
3GPP_GGSN_IPV6_ADDRESS	3GPP_GGSN_MCC_MNC
3GPP_GPRS_QOS_PROFILE	3GPP_IMEISV
3GPP_IMSI	3GPP_IMSI_MCC_MNC
3GPP_IPV6_DNS_SERVER	3GPP_MS_TIMEZONE
3GPP_NSAPI	3GPP_PDP_TYPE
3GPP_RAT_TYPE	3GPP_SELECTION_MODE
3GPP_SESSION_STOP_INDICATOR	3GPP_SGSN_ADDRESS
3GPP_SGSN_IPV6_ADDRESS	3GPP_SGSN_MCC_MNC
3GPP_USER_LOCATION_INFO	accounting_container
accounting_stop_triggered_by_active_stop_indication	active_time
airlink_priority	allowed_differentiated_services_marking
allowed_differentiated_services_marking__class	allowed_differentiated_services_marking__max
allowed_differentiated_services_marking__reverse_tunnel	allowed_persistent_tfts
always_on	bad_ppp_frame_count
beginning_session	bsid
CISCO_STRING	compulsory_tunnel_indicator
correlation_id	dcch_frame_size
differentiated_services_class_option	disconnectreason
dns_update_capability	dns_update_required
esn	fch_frame_size
foreign_agent_address	forward_dcch_mux_option
forward_dcch_rc	forward_fch_mux_option
forward_fch_rc	forward_pdch_rc
forward_traffic_type	home_agent
ike_pre_shared_secret_request	ip_quality_of_service
ip_technology	keyid
mip_lifetime	mip_lifetime__rrq_lifetime
mip_lifetime__used_lifetime	mn_aaa_removal_indication

**Table B-7 (Cont.) Supported Vendor-Specific RADIUS Fields**

Vendor-Specific RADIUS Field	Vendor-Specific RADIUS Field
mn_ha_shared_key	mn_ha_spi
MS_PRIMARY_DNS	MS_PRIMARY_NBNS
MS_SECONDARY_DNS	MS_SECONDARY_NBNS
number_of_active_transitions	number_of_hdlc_layer_octets_received
number_of_sdbbs_originating	number_of_sdbbs_terminating
PPAC__AiC	PPAC__available_in_client
PPAC__selected_for_session	PPAC__SfS
PPAQ__DQ	PPAQ__DT
PPAQ__duration_quota	PPAQ__duration_threshold
PPAQ__pre_paid_server	PPAQ__QID
PPAQ__quota_identifier	PPAQ__update_reason
PPAQ__UR	PPAQ__volume_quota
PPAQ__volume_quota_overflow	PPAQ__volume_threshold
PPAQ__volume_threshold_overflow	PPAQ__VQ
PPAQ__VQO	PPAQ__VT
PPAQ__VTO	pre_paid_accounting_capability
pre_paid_accounting_quota	pre_paid_tariff_switching
pre_shared_secret	PTS__QID
PTS__quota_identifier	PTS__tariff_switch_interval
PTS__time_interval_after_tariff_switch_update	PTS__TITSU
PTS__TSI	PTS__volume_used_after_tariff_switch
PTS__volume_used_ats_overflow	PTS__VUATS
PTS__VUATSO	release_indicator
remote_address_table_index	remote_address_table_index__qualifier
remote_address_table_index__table_index	remote_ipv4_address
remote_ipv4_address__address	remote_ipv4_address__mask
remote_ipv4_address_octet_count	remote_ipv4_address_octet_count__address
remote_ipv4_address_octet_count__forward_octet_count	remote_ipv4_address_octet_count__forward_overflow
remote_ipv4_address_octet_count__mask	remote_ipv4_address_octet_count__reverse_octet_count
remote_ipv4_address_octet_count__reverse_overflow	remote_ipv4_address_octet_count__table_index
remote_ipv4_address__qualifier	remote_ipv6_address
remote_ipv6_address__address	remote_ipv6_address_octet_count
remote_ipv6_address_octet_count__address	remote_ipv6_address_octet_count__forward_octet_count

**Table B-7 (Cont.) Supported Vendor-Specific RADIUS Fields**

Vendor-Specific RADIUS Field	Vendor-Specific RADIUS Field
remote_ipv6_address_octet_count__forward_overflow	remote_ipv6_address_octet_count__prefix_length
remote_ipv6_address_octet_count__reverse_octet_count	remote_ipv6_address_octet_count__reverse_overflow
remote_ipv6_address_octet_count__table_index	remote_ipv6_address__prefix_length
remote_ipv6_address__qualifier	request_message_to_the_home_radius_server
reverse_dcch_mux_option	reverse_dcch_rc
reverse_fch_mux_option	reverse_fch_rc
reverse_tunnel_specification	rn_packet_data_inactivity_timer
sdb_octet_count_originating	sdb_octet_count_terminating
security_level	service_option
service_option_profile	service_reference_id
serving_pcf	session_continue
session_termination_capability	sf_access_point_id
s_key	s_lifetime
SR_ID__main_si_indicator	SR_ID__sr_id
user_zone	

## Supported Fields of the SMPP Protocol

Table B-8 lists the fields of the SMPP protocol that the **mipt** utility supports.

**Table B-8 Supported Fields of the SMPP Protocol**

SMPP Field Name	SMPP Field Name
addr_npi	addr_ton
address_range	alert_notification
application_id	auth_acc
auth_acc_resp	bind_receiver
bind_receiver_resp	bind_transceiver
bind_transceiver_resp	bind_transmitter
bind_transmitter_resp	cancel_sm
cancel_sm_resp	command_id
command_status	data_coding
data_sm	data_sm_resp
deliver_sm	deliver_sm_resp
dest_account	dest_addr
dest_addr_npi	dest_addr_ton
dest_address	dest_imsi
dest_oper_id	destination_addr



**Table B-8 (Cont.) Supported Fields of the SMPP Protocol**

<b>SMPP Field Name</b>	<b>SMPP Field Name</b>
enquire_link	enquire_link_resp
error_code	esm_class
esme_addr	esme_addr_npi
esme_addr_ton	fee_addr
fee_addr_npi	fee_addr_ton
fee_fixed	fee_flag
fee_ltd_msg_num	fee_single
fee_type	final_date
generic_nack	interface_version
is_time_message	message_id
message_length	message_pid
message_state	mo_msc_addr
mo_msc_addr_npi	mo_msc_addr_ton
mo_mt_flag	mt_msc_addr
mt_msc_addr_npi	mt_msc_addr_ton
no_unsuccess	notify_mode
number_of_dests	operation_result
orig_account	orig_imsi
original_group	outbind
password	priority_flag
protocol_id	protocol_version
query_sm	query_sm_resp
registered_delivery	replace_if_present_flag
replace_sm	replace_sm_resp
schedule_delivery_time	schedule_mode
send_result	sequence_number
service_id	service_type
short_message	sm_default_msg_id
sm_length	sm_result_notify
sm_result_notify_resp	smsc_addr
source_addr	source_addr_npi
source_addr_ton	source_oper_id
status_report_request	submit_multi
submit_multi_resp	submit_sm
submit_sm_resp	system_id
system_type	unbind
unbind_resp	unsuccess_sme

**Table B–8 (Cont.) Supported Fields of the SMPP Protocol**

SMPP Field Name	SMPP Field Name
validity_period	

## Supported SMPP TLV Fields

Table B–9 lists the TLV fields of the SMPP protocol that the **mipt** utility supports. These fields are also listed in Table B–8, "Supported Fields of the SMPP Protocol".

**Table B–9 Supported SMPP TLV Fields**

SMPP TLV Field Name	SMPP TLV Field Name
tlv_additional_status_info_text	
tlv_billing_identification	tlv_callback_num
tlv_callback_num_atag	tlv_callback_num_pres_ind
tlv_delivery_failure_reason	tlv_dest_addr_np_country
tlv_dest_addr_np_information	tlv_dest_addr_np_resolution
tlv_dest_addr_subunit	tlv_dest_bearer_type
tlv_dest_network_id	tlv_dest_network_type
tlv_dest_node_id	tlv_dest_subaddress
tlv_dest_telematics_id	tlv_destination_port
tlv_display_time	tlv_dpf_result
tlv_its_reply_type	tlv_its_session_info
tlv_language_indicator	tlv_message_payload
tlv_message_state	tlv_more_messages_to_send
tlv_ms_availability_status	tlv_ms_msg_wait_facilities
tlv_ms_validity	tlv_network_error_code
tlv_number_of_messages	tlv_payload_type
tlv_privacy_indicator	tlv_qos_time_to_live
tlv_receipted_message_id	tlv_sar_msg_ref_num
tlv_sar_segment_seqnum	tlv_sar_total_segments
tlv_sc_interface_version	tlv_set_dpf
tlv_sms_signal	tlv_source_addr_subunit
tlv_source_bearer_type	tlv_source_network_id
tlv_source_network_type	tlv_source_node_id
tlv_source_port	tlv_source_subaddress
tlv_source_telematics_id	tlv_user_message_reference
tlv_user_response_code	tlv_ussd_service_op

## Supported Fields of the SUA Protocol

Table B–10 lists the fields of the SUA protocol that the **mipt** utility supports.

**Table B–10** *Supported Fields of the SUA Protocol*

<b>SUA Field Name</b>	<b>SUA Field Name</b>
ACTIVE	ACTIVE_ACK
address_indicator	address_range
affected_point_code	asp_active
asp_active_ack	asp_capabilities
asp_down	asp_down_ack
asp_identifier	asp_inactive
asp_inactive_ack	asp_up
asp_up_ack	BEAT
BEAT_ACK	CLDR
CLDT	COAK
CODA	CODT
COERR	COIT
congestion_level	connection_acknowledge
connection_oriented_data_acknowledge	connection_oriented_data_transfer
connection_oriented_error	connection_oriented_inactivity_test
connection_refused	connection_request
connectionless_data_response	connectionless_data_transfer
CORE	COREF
correlation_id	credit
data	DAUD
DAVA	DEREG_REQ
DEREG_RSP	deregistration_request
deregistration_response	deregistration_result
deregistration_status	destination_address
destination_available	destination_reference_number
destination_restricted	destination_state_audit
destination_unavailable	destination_user_part_unavailable
diagnostic_info	DOWN
DOWN_ACK	drn_label
DRST	DUNA
DUPU	ERR
error	error_code
global_title	heartbeat
heartbeat_ack	heartbeat_data
hostname	importance
INACTIVE	INACTIVE_ACK
info_string	ipv4_address

**Table B–10 (Cont.) Supported Fields of the SUA Protocol**

<b>SUA Field Name</b>	<b>SUA Field Name</b>
ipv6_addresses	local_routing_key_identifier
message_priority	network_appearance
notify	NTFY
point_code	protocol_class
receive_sequence_number	REG_REQ
REG_RSP	registration_request
registration_response	registration_result
registration_status	RELCO
release_complete	release_request
RELRE	RESCO
reset_confirm	reset_request
RESRE	routing_context
routing_indicator	routing_key
sccp_cause	SCON
segmentation	sequence_control
sequence_number	signalling_congestion
smi	source_address
source_reference_number	ss7_hop_count
status	subsystem_number
tid_label	traffic_mode_type
UP	UP_ACK
user_cause	

---

---

# Glossary

## **access code**

A code entered by a caller to gain access to the calling system. You use ACS to configure access codes. You use the Account Code Entry feature node to accept access codes.

## **account code**

See [access code](#).

## **ACS**

See [Advanced Control Services \(ACS\)](#).

## **Advanced Control Services (ACS)**

An application used for configuring call-routing, and for managing many NCC system-related features. For example, you use ACS to assign resources to service providers, manage passwords, and set up geography sets and holiday sets used by service providers.

## **announcement**

An announcement played to a caller over the phone; for example, "Enter the number you wish to call." Announcements can be assigned to specific service providers, or available to all service providers.

## **announcement set**

A set of announcements that can be used by a single service provider. You can use announcement sets to organize messages; for example, welcome messages or credit messages.

## **API**

Application Programming Interface.

## **CAP3 Short Message Service (SMS) Gateway**

A SLEE application that translates Camel Application Part (CAP) v3 SMS Intelligent Network Application Part (INAP) operations to the CAP v2 equivalent. See "[The CAP Protocol](#)"

## **CCS**

1) Charging Control Services (or Prepaid Charging) component. See [Charging Control Services \(CCS\)](#).

2) Common Channel Signalling. A signalling system used in telephone networks that separates signalling information from user data.

**CDMA (U-CA-IS41)**

An NCC component that enables the IS-41 protocol to provide phone services to end users on CDMA networks.

**Charging Control Services (CCS)**

An NCC application used for setting up and managing rating, subscriber management, and voucher management.

**CLI-DN tariff**

A tariff based on the originating Calling Line Identifier (CLI) number and the Dialed Number (DN).

**closed user group (CUG)**

A group of subscribers who can make calls and receive calls only from members within the group. Any other calls are rejected.

**Connection**

Transport level link between two peers, providing for multiple sessions.

**control plan**

A flowchart defining the decisions and actions needed to process and route a call. Control plans are created and maintained using the Control Plan Editor.

**Control Plan Editor (CPE)**

A graphical user interface used for making control plans.

**Country Code**

Prefix identifying the country for a numeric international address.

**CPE**

See [Control Plan Editor \(CPE\)](#).

**customer**

See [service provider](#).

**Customer Care Portal (CCP)**

A customizable application used by Customer Services Representatives (CSRs) to manage subscribers; for example, change subscriber account details, and recharge vouchers.

**DAP**

See [Data Access Pack \(DAP\)](#).

**Data Access Pack (DAP)**

An extension module that you can use to communicate with external systems by using SOAP, XML, HPSA, and PIXML. DAP provides the capability to request data or trigger services and subscriptions on Application Service Providers (ASPs).

**DCA**

See [Diameter Control Agent \(DCA\)](#).

**DCD**

See [Diameter Charging Driver \(DCD\)](#).

**Diameter Charging Driver (DCD)**

An interface that supports prepaid charging by managing authentication, authorization, and accounting (AAA). DCD supports the RFC 3588 and RFC 4006 Diameter protocols.

**Diameter Control Agent (DCA)**

An interface run in the SLEE that handles Diameter messages. Diameter messages are used for authentication, authorization, and accounting (AAA). You use Diameter to control calls based on the caller's balance; for example, to see if there is enough cash balance to make a call.

**domain**

A network element that provides NCC functionality; for example, rating, billing, wallet management, or voucher management. For example, a domain might consist of a pair of Voucher and Wallet Server components.

**ECA**

See [EDR Control Agent \(ECA\)](#).

**EDR**

See [event detail record \(EDR\)](#).

**EDR Control Agent (ECA)**

A SLEE interface that translates event detail records (EDRs) into initial detail response (IDR) messages. NCC can use the content of the IDR messages in control plans. For example, you can find data about calls, such as the SIM that was used, and process the call differently based on the data.

**EDR element**

Defines how data is shown in field names on the EDR Details for Subscriber window.

**EDR type**

The type of EDR; for example, regular call, roaming call, recharge, or product type swap. The EDR type is defined as a number in the CDR\_TYPE field in the EDR.

**Enhanced Accounting Exchange (EAX)**

An ACS extension that provides an interface to an EAX-compatible billing system.

**event counter**

An ACS feature that counts events; for example, messages, or votes in a televoting program.

**event detail record (EDR)**

A record of NCC activity; for example, when a call is processed, an SMS message is sent or received, a recharge is attempted, or a wallet changes state.

**ENUM Control Agent**

An NCC component that uses E.164 Number Mapping (ENUM) to translate numbers from the E.164 standard to a Uniform Resource Identifier (URI) or IP address.

**feature node**

An action point or decision point in a [control plan](#). Each feature node has one input and a number of outputs, with the exceptions of the Start and End feature nodes, which have only one output or one input respectively.

**feature node set**

A set of feature nodes made available to a service provider. The service provider can use only the feature nodes in their feature node set.

**geography set**

A set of telephone prefix/location mappings assigned to a service provider to support [CLI-DN tariff](#) rating, and for call routing. For example, a service provider based in Europe might use a geography set that organizes prefixes by European countries, but a service provider in the United States might use a geography set that organizes by state.

**GPRS**

General Packet Radio Service - employed to connect mobile cellular users to PDN (Public Data Network- for example the Internet).

**holiday set**

A set of holidays assigned to a service provider. You can use holidays to override standard tariffs; for example, to provide a special tariff on New Year's Day.

**HLR**

The Home Location Register is a database within the HPLMN (Home Public Land Mobile Network). It provides routing information for MT calls and SMS. It is also responsible for the maintenance of user subscription information. This is distributed to the relevant VLR, or SGSN (Serving GPRS Support Node) through the attach process and mobility management procedures such as Location Area and Routing Area updates.

**HTML**

HyperText Markup Language, a small application of SGML used on the World Wide Web. It defines a very simple class of report-style documents, with section headings, paragraphs, lists, tables, and illustrations, with a few informational and presentational items, and some hypertext and multimedia.

**IN**

Intelligent Network.

**INAP**

Intelligent Network Application Part - a protocol offering real time communication between IN elements. See, "[The INAP Protocol](#)".

**IP**

Internet Protocol. See, "[The Internet Protocol](#)".

**IS-41 Protocol**

See "[The IS-41 Protocol](#)".

**ISDN**

Integrated Services Digital Network - set of protocols for connecting ISDN stations.



**LCP**

See [Location Capabilities Pack \(LCP\)](#).

**LDAP Control Agent**

A SLEE interface that maps billing requests between LDAP and NCC.

**Location Capabilities Pack (LCP)**

An NCC service that can be used for finding the location of the caller. This enables a caller who is making a call on a foreign network to establish a roaming call.

**LNP**

Local Number Portability.

**M3UA**

Message Transfer Part Level 3 (MTP3) User Adaptation Layer. See "[The M3UA Protocol](#)".

**MAP**

The Mobile Application Part (MAP) protocol. See "[The MAP Protocol](#)".

**Messaging Manager**

Messaging Manager provides a messaging system for mobile networks. Messaging Manager components operating at the network layer can route traffic and perform protocol translation between different services.

**MFile**

A file that holds rating data used by the NCC system. You compile the MFile after you configure tariffs. The MFile is then loaded into memory, which allows faster access than if the data was held in the database.

**MM**

See [Messaging Manager](#).

**MT**

Mobile terminated.

**MTP**

Message Transfer Part (part of the SS7 protocol stack).

**named event**

An activity other than a call that can be charged for; for example, a one-time subscription charge, or sending an SMS. Also called a billable event.

**MSISDN**

Mobile Station ISDN number. Uniquely defines the mobile station as an ISDN terminal. It consists of three parts; the country code (CC), the national destination code (NDC) and the subscriber number (SN).

**notification**

Any short message sent to a subscriber's handset. NCC generates notifications about events such as balance expiration, service expiration, and recharges.

**Number Portability Service Pack**

Provides call routing based on number portability. You can configure number portability in control plans.

**Open Services Development (OSD)**

A service that enables control plans to read from WSDL files.

**OSD**

See [Open Services Development \(OSD\)](#).

**PCST**

See [Prepaid Charging Service Template \(PCST\)](#).

**periodic charge**

A charge that occurs repeatedly at a defined interval. For example, you can define periodic charges for providing a phone service, or for rental of services and equipment.

**PI**

See [provisioning interface \(PI\)](#).

**power charge scenario**

See [scenario](#).

**prefix tree**

A data type for a [profile tag](#) that holds a list of numbers.

**Prepaid Charging Service Template (PCST)**

An NCC product that provides a prebuilt NCC configuration that you can customize

**profile**

A method of storing and managing data in NCC. Profiles contain profile tags, which hold data such as phone numbers. NCC includes standard profiles, such as a subscriber profiles. Profiles can also be held only in memory, such as in session data, or in temporary profiles used by control plans.

**profile tag**

A location for data in a [profile](#). For example, a profile tag in a session data profile might hold the originating number.

**promotion**

A method of rewarding subscribers; for example, give free minutes or a reduced tariff, based on the subscriber's usage. See [Promotion Manager](#).

**Promotion Manager**

An NCC service used for setting up promotions; for example, setting up counters to track subscriber usage. See [promotion](#).

**provisioning interface (PI)**

An API used for manipulating data in the SMF database. You can create custom programs by using the provisioning interface to perform many NCC functions.

**Radius Control Agent (RCA)**

A SLEE interface that enables integration between a Radius server and NCC. RCA can also provide an integration with Cisco Gateway GGSN.

**rate**

The amount that a call can be charged, based on the defined cost of the event being rated, the length of the call, the maximum cost, and other factors such as location and holidays.

**rate table**

A way to map CLI-DN tariffs to geography sets and holiday sets, and to specify whether to rate by duration or volume.

**rating**

Applying a charge to an event, such as a phone call.

**RCA**

See [Radius Control Agent \(RCA\)](#).

**recharge promotion**

A [promotion](#) given when a subscriber recharges a [wallet](#).

**reservation**

An amount of money paid in advance for pre-paid calls.

**reservation chunk**

The amount that the [Voucher and Wallet Server \(VWS\)](#) returns in response to a reservation request.

**resource**

A configuration property that you can assign to service providers, or set as a global resource. Resources include such properties as termination number ranges, number of control plans allowed, holiday sets, geography sets, and announcements.

**resource limit**

Defines limitations on service providers for such properties as how many control plans they can configure, which feature nodes they can use, and so on.

**resource set**

The resources made available to a customer; for example, geography sets, announcement sets, and holiday sets.

**reward**

A method of granting cash or a product type change based on subscriber usage. For example, you can upgrade a product type after a subscriber sends 1000 messages. You use CCS to configure rewards.

**Roaming Applications**

A set of applications that enable subscribers to make and receive calls while roaming. The applications are Unstructured Supplementary Service Data (USSD), Returned Accounts Procedure (RAP), and TRANS.

**SCA**

See [Session Control Agent \(SCA\)](#).

**SCCP**

Signalling Connection Control Part (part of the SS7 protocol stack). See "[The SCCP Protocol](#)".

**SCTP**

The Stream Control Transmission Protocol. See "[The SCTP Protocol](#)".

**SEI**

See [SMS Email Interface \(SEI\)](#).

**scenario**

A set of balances that a subscriber can choose when redeeming a voucher. For example, one scenario might be 120 free minutes, and another scenario might be 200 free minutes made within 30 days.

**service key**

A parameter in an incoming INAP message, which identifies the service. (Other parameters include the calling party and the called party.) NCC runs a specific service loader based on the value of the service key.

**service loader**

A shared library that is loaded by `slee_acs` that is responsible for initializing the right service for a call and loading its control plan, profiles, and so on. A service loader also acts as a mediation layer between the inbound SLEE interface and the service, and performs the final manipulation of data that is returned to the network interface when a triggering interface sends back a network event.

**Service Logic Execution Environment (SLEE)**

The execution environment for NCC applications and services, including ACS, CCS, and Messaging Manager.

**Service Management System (SMS)**

The platform that support NCC applications such as ACS and CCS. The SMS GUI is the primary GUI interface for NCC. From SMS, you can configure ACS and CSS data, and start the Control Plan Editor.

**service number**

A number that subscribers call to get customer service.

**service provider**

A company that has subscribers that are charged and managed by using NCC. If you an MVNO or MVNE, service providers are your customers. Also called *customer* in the NCC user interface.

**SES**

See [Subscriber Event Service \(SES\)](#).

**Session Control Agent (SCA)**

A SIP transparent back-to-back user agent (B2BUA), redirect server, proxy server and registrar. It provides support for SIP/SIMPLE messaging and integrated triggering

capabilities. The SCA enables real-time charging, instant messaging and personal mobility in SIP-based Next Generation Networks (IETF/ETSI NGNs) and in the IP Multimedia Subsystem (3GPP IMS, 3GPP2 MMD).

**session rating**

Rating based on duration.

**SGSN**

Serving GPRS Support Node.

**Short Message Charging Bundle (SMCB)**

An NCC service that enables billing of SMS messages.

**Short Message Services (SMS) Center**

A SLEE interface that enables applications to send messages to an SMS center on the network.

**SIGTRAN Transaction Capabilities Application Part (TCAP) Interface**

A SLEE interface that integrates NCC with a TCAP stack.

**single-use debit wallet**

A wallet that can be used once. Used for non-rechargeable pre-paid accounts.

**SLEE**

See [Service Logic Execution Environment \(SLEE\)](#).

**SMCB**

See [Short Message Charging Bundle \(SMCB\)](#).

**SMF database**

The main database on the [Service Management System \(SMS\)](#). This database holds data for [Charging Control Services \(CCS\)](#) and the other NCC applications.

**SMS**

Depending on context, can be:

Short Message Service. See [Service Management System \(SMS\)](#).

Service Management System platform

NCC Service Management System application

**SMSC**

See [Short Message Services \(SMS\) Center](#).

**SMS Email Interface (SEI)**

Enables sending and receiving email on a mobile phone by using Short Message Service (SMS).

**SN**

Service Number.

**SNFK**

See [Social Networking Foundation Kit \(SNFK\)](#).

**SNST**

See [Social Networking Service Template \(SNST\)](#).

**Social Networking Foundation Kit (SNFK)**

Enables discounts and special tariffs based on subscriber relationships; for example, friend groups.

**Social Networking Service Template (SNST)**

Part of the [Social Networking Foundation Kit \(SNFK\)](#), which enables discounts and special tariffs based on subscriber relationships; for example, friend groups.

**SPM**

See [Subscriber Profile Manager \(SPM\)](#).

**SS7**

A Common Channel Signalling system used in many modern telecoms networks that provides a suite of protocols which enables circuit and non circuit related information to be routed about and between networks. The main protocols include MTP, SCCP and ISUP. See "[About the SS7 Protocol Suite](#)".

**SSN**

Subsystem Number. An integer identifying applications on the SCCP layer.

For values, refer to 3GPP TS 23.003.

**Service Switching Point**

Service Switching Point.

**SUA Protocol**

The SCCP User Adaptation layer protocol. See "[The SUA Protocol](#)".

**subscriber**

A person who owns a service, such as a telephone service.

**subscriber account**

A record in the [SMF database](#) that identifies a subscriber.

**Subscriber Event Service (SES)**

An NCC service that enables service providers to send text messages to subscribers who roam in and out of the home network. For example, a service provider might greet inbound messages with a welcome message.

**Subscriber Profile Manager (SPM)**

An SMS application for customizing which elements appear on some SMS windows; for example, the CCP Dashboard Edit Subscriber window, and the Edit Product Type window.

**subscription service**

A service that is renewed at periodic intervals. See [periodic charge](#).

**Switching Point**

Anything that can send and receive SS7 messages.

**tariff code**

An ACS resource used for returning charging information to the switch. The information can be sent in a Send Charging Information (SCI) operation or in an Furnish Charging Information operation.

**tariff plan**

A mapping between product types and rate tables. When initiating a call the service loader finds the product type to use, which points to the tariff plan selector, where tariff plans are mapped to rate tables.

**tax plan**

Used for calculating taxes for charges and recharges.

**TCAP**

Transaction Capabilities Application Part – layer in protocol stack, message protocol. See "[The TCAP Protocol](#)".

**Telco**

Telecommunications Provider. This is the company that provides the telephone service to customers.

**UBE**

Obsolete name, now called Billing Engine (BE).

**UCAI**

See [Universal Call Agent for ISDN User Part \(ISUP\)](#).

**uncommitted reservation**

The reservation amount not yet committed for a balance type.

**Universal Billing Engine (UBE)**

A component name used in previous releases. Now known as Billing Engine (BE).

**Universal Call Agent for ISDN User Part (ISUP)**

An NCC component that provides intelligent network (IN) functionality by using fixed connections between incoming and outgoing calls. The prevents the need to upgrade or replace non-SS7 capable switches.

**Universal Service Management System (USMS)**

A component name used in previous releases. Now known as [Service Management System \(SMS\)](#).

**Unstructured Supplementary Service Data (USSD) Gateway**

An NCC service that enables USSD messages and International Mobile Subscriber Identity (IMSI) management.

**USMS**

See [Universal Service Management System \(USMS\)](#).

**USSD Gateway**

See [Unstructured Supplementary Service Data \(USSD\) Gateway](#).

**variable announcement rule set**

A set of rules that specify which announcement to play based on conditions. For example, a variable announcement rule might specify to play a different version of an announcement based on the amount of messages in a subscriber's balance.

**Virtual Private Network (VPN) Server**

An NCC service that enables VPN networks on an IN system.

**VLR**

Visitor Location Register - contains all subscriber data required for call handling and mobility management for mobile subscribers currently located in the area controlled by the VLR.

**voucher**

A recharge number sold to a subscriber to recharge their SIM card with money and to extend the card's availability period. Vouchers are typically sold at retail outlets, such as phone stores run by the mobile operator or by distributors, grocery stores, and gas stations.

**Voucher and Wallet Server (VWS)**

An NCC network service that manages vouchers and subscriber wallets.

**voucher scenario**

See [scenario](#).

**voucher type**

Defines the voucher properties; for example, the product type it applies to, product type swap rules, balance types, and tax plans.

**VPN**

See [Virtual Private Network \(VPN\) Server](#).

**VWS**

See [Voucher and Wallet Server \(VWS\)](#).

**wallet**

A group of balances owned by a subscriber, used for paying for services. Every subscriber has at least one wallet.

**wallet life cycle**

The states that a wallet can be in; for example, Pre-Use, Active, Dormant, Frozen, Suspended, and Terminated.

**wallet state**

The state in the [wallet life cycle](#) that defines how a wallet can be used. For example, if a wallet is in the Frozen state, all services are disabled.

**zone**

An area defined by latitude and longitude that can be used for rating. For example, you can define a geographic zone that allows discounted calls.