


wv: A General Web-based 3D Viewer

Bob Haimes (haimes@mit.edu)

Aerospace Computational Design Laboratory
Department of Aeronautics & Astronautics
Massachusetts Institute of Technology




April 2022

Objective




The objective of this work is to generate a **visual** tool targeted for the 3D needs found within the MDAO process. A **WebBrowser**-based approach is considered, in that it provides the broadest possible platform for deployment.



Outline



- **System Architecture**
 - Browser / WebGL / WebSockets
 - Server or Data Generator(s)
- **Data Model**
 - VBO based
 - Primitives
 - Graphic Objects
- **Functionality at the Viewer**
 - IO Handling
 - Rendering / GUI Loop
- **Binary Data Packets**
- **GUI Call-backs**
- **Procedural-based Server-side API**




System Architecture



Goal: Effective 3D component that can support the viewing of:

- Geometry
- Meshing
- Scientific Visualization Tools (including transient data)
- Multi-dimensional Design Space Examination
- Other 3D needs

Contains no GUI but the *hooks* (in the form of *JavaScript* call-backs) to graft a customized UI specifically designed for the task at hand.




System Architecture -- Viewer



Efficient Browser Implementation

- Must support WebGL (& *JavaScript*)
- Use of WebSockets (part of HTML5)
 - Asynchronicity
 - Segregation of data-streams (via *protocols*)
 - Data handling consistent with WebGL
- Extensive use of Vertex Buffer Objects (**VBOs**)
- IO from the *server*
 - Packed messages -- few network packets that are unpacked into typed *JavaScript* Arrays at the Browser
 - Binary -- known common types, allows avoiding the costs of serialization / deserialization (WebSocket *binary*)
 - Techniques to provide data to the GUI (WebSocket *text*)
- IO to the *server*
 - Nothing from the Viewer by default
 - Only data from the customized GUI (WebSocket *text*)




System Architecture -- Server



Data Generation and Handling

- Web server (or acts as one -- *libwebsockets*)
- Visualization state must be maintained (note: Viewer is stateless except for viewMatrix & current plotting attributes)
- **VBO** components generated and sent
- IO to the Viewer
 - Aggregated **VBOs** with metadata
 - What is sent is based on changes from the GUI or from transient data
 - Data for the GUI portion of the Viewer
- IO from the Viewer
 - Only data from the customized GUI




Data Model -- VBO Components



- **Vertices**
 - Coordinates (3 by *float* -- *Float32Array*)
 - length
- **Indices** (optional)
 - The index into the Vertex Array (*unsigned short* -- *Uint16Array*)
 - length (can be different from Vertex length)
- **Colors** (optional)
 - RGBs associated with the Vertices (3 by *unsigned byte* -- *Uint8Array*)
 - Must be same length as *Vertices*
- **Normals** (optional, used for *Triangles* or Decorated *Lines*)
 - The normal pointing vector for lighting (3 by *float* -- *Float32Array*) or Decorated *Triangles* and normals (no stripes)
 - Must be same length as *Vertices* (*Triangles*)

Note: the *unsigned short* of **Indices** limits the size of the VBO used, so larger data needs to be *striped*.




Data Model -- VBO Types



- *Points*
 - *Vertices* [*Colors* & *Indices*]
- *Lines* (2 vertices per -- disjoint segments)
 - *Vertices* [*Colors* & *Indices*]
 - Optional *Normals* for Decorations (i.e. 3D Arrows)
- *Triangles* (3 vertices per -- also disjoint)
 - *Vertices* [*Normals*, *Colors* & *Indices*]

Notes:


1. Constant element coloring of *Lines/Triangles* requires non-indexed **VBOs** and the duplication of color information (per vertex)
2. Facetted lighting requires similar treatment with *Normals*
3. Any non-planar set of *Triangles* requires *Normals* **VBO** component



Data Model -- Graphic Primitives



- *Locations* (GPType 0 -- 0D)
 - Collections of one or more *Points*
 - Foreground Color
 - Size (in pixels)
 - Coloring & Transparency Flags
- *Disjoint Lines* (GPType 1 -- 1D)
 - Optional collected Indexed *Points* into the *Lines* Vertex Array
 - Collections of one or more *Lines*
 - Line Color
 - Foreground Color for Decorations
 - Back-facing Color for Decorations
 - Line Width (in pixels)
 - Point Color
 - Point size (in pixels)
 - Coloring & Transparency Flags




Data Model -- Graphic Primitives



- *Disjoint Triangles* (GPType 2 -- 2D)
 - Optional collected Indexed *Points* into the *Triangles* Vertex Array
 - Optional collected Indexed *Lines* into the *Triangles* Vertex Array
 - Collections of one or more *Triangles*
 - Foreground Color
 - Back-facing Color
 - Planar Normal (if planar)
 - Line Color
 - Line Width (in pixels)
 - Point Color
 - Point size (in pixels)
 - Coloring, Transparency, Orientation & *Point/Line* Flags

Note: Simple two-sided (ambient & diffuse) lighting is applied by default (modification to **wv_render.js** is required for other lighting models)



Data Model -- Graphic Objects




- **Graphic Object**

- ID -- Unique character string assigned by the server
- GPType
- Number of *Striped* Primitives in the Collection
- GPType specific metadata
- Graphic Primitive data

- **VBO Internal Reference**

- ID string
- Stripe # 24bits
- One of *Point*, *Line*, *Triangle* Data (3) byte
- One of *Vertices*, *Indices*, *Colors*, *Normals* (4) byte



Functionality at the Viewer



IO Handling

- Initialize (connect to *server*)
- Handshake to ensure compatibility
- Arrays generated by “unpacking” received **VBOs** (with metadata) via *binary protocol*
- Handle any GUI related data (*text protocol*) via the call-back **ServerMessage**
- Continue until End-of-Frame marker
- Inform *Rendering Loop* that there is new data and accept no new data until released

Asynchronously performed by WebSocket event handling




Functionality at the Viewer



Rendering / GUI Loop

- Initialize (generate canvas on WebGL context)
- Execute GUI setup call-back *InitUI*
- 1. Setup scene
 - Blank canvas and depth buffer
 - Adjust viewMatrix (*UpdateView* call-back)
- 2. Render any *Graphics Objects*
- 3. Add custom renderings by call-back *UpdateCanvas*
- 4. Execute GUI call-back *UpdateUI*
- 5. Do we have an End-of-Frame marker?
 - If **no** -- has anything changed in the GUI?
 - No -- Wait then goto 4
 - Yes -- goto 1
- 6. Handshake with IO Handling, update the *Graphics Objects* & release the IO hold
- 7. goto 1




Functionality at the Viewer



Rendering Model


- WebGL requires fragment & vertex shaders
- Lighting & texture mapping done in the shaders
- The supplied shaders support:
 - Two-sided lighting
 - Ambient & Diffuse lighting model
 - Back-face coloring
 - Constant and/or linearly interpolated color-space mapping
 - Simple transparency
 - Picking
 - Bumping of lines forward (in screen Z)
- Any other requirements will involve modifying the shaders (which can be found in **wv-render.js**)



Binary Data Packets




- Individual data collections should be aggregated to reduce network latencies -- large packets
- All data is tightly packed and **VBO** “ready”
- Data collections begin with an Opcode (1 byte):
 - 0 -- end of packet (but not End-of-Frame)
 - 1 -- new Graphic Object
 - 2 -- delete Graphic Object
 - 3 -- new Data for Graphic Object
 - 4 -- update Data in Graphic Object
 - 7 -- End-of-Frame Marker (must be last in total packet)
 - 8 -- Initialize Packet
- All data is aligned on 4-byte boundaries
 - Colors are *unsigned byte*
 - Indices are *unsigned short*
 - The ID is a *string*



Binary Data Packets



- Each collection starts with:
 - Opcode (MSB)
 - Stripe # or Number of Stripes (3 bytes -- LSB)
 - Complete for Opcode 0 & 7
- Next 32 bits (all but Opcode 0, 7 & 8):
 - GPType (1 byte -- MSB)
 - vflag -- bits can be summed (1 byte):
 - Vertices 1
 - Indices 2
 - Colors 4
 - Normals 8
 - Point Indices 16
 - Line Indices 32
 - ID character Length (integer factor of 4) (2 bytes -- LSB)
- ID Character string (number of bytes above)




Opcode 2 (delete) requires no more data

Binary Data Packets



- Opcode 1 (new Graphic Object)
 - Plotting Attributes (bit flag -- *int*):
 - 1 - Render On
 - 2 - Transparent
 - 4 - Color Interpolation
 - 8 - Show orientation
 - 16 - Plot Points
 - 32 - Plot Lines
 - Point size (*float*)
 - Point color (3**float*)
[Done for Point Objects]
 - Line width (*float*)
 - Line color (3**float*)
 - Foreground constant color (3**float*)
 - Background color (3**float*)
[Done for Line Objects]
 - Constant Normal (3**float*)




Binary Data Packets



- Opcode 3 (new data) & 4 (update data)
 - Number of data elements for the Graphic Primitive stripe (*int*):
 - Total number of primitive *words* is found by multiplying by 3 for Vertices (xyz), Colors (rgb) & Normals
 - Applying “*sizeof()*” to the above provides the total byte length (plus any required padding)
 - The **VBO** data (type based on bit in *vflag*)
 - *Repeated for each bit in vflag in LSB order (Opcode 3), i.e. vertices always first*

Notes:


- Opcode 4 can only have a single bit in *vflag* set
- Data types shorter than 32 bits must be padded at the end so that the next read can be 4-byte aligned



Binary Data Packets




- Opcode 8 (Initialize) -- 56 bytes long
 - Opcode field (4**bytes*)
 - Field of View (*float*)
 - zNear (*float*)
 - zFar (*float*)
 - Eye location (3**float*)
 - Focus position (3**float*)
 - Up direction (3**float*)
 - End-of-Frame (4**bytes*)



Binary Data Packets




- Opcode 9 (Color Key Definition)
 - Opcode field ($4 \times \text{bytes}$), Stripe # is the number of characters in title – nLen (integer factor of 4)
 - # of Colors – nCol (*int*)
 - The title ($\text{nLen} \times \text{bytes}$)
 - Scale for bottom (*float*)
 - Scale for top (*float*)
 - rgb Colors ($3 \times \text{nCol} \times \text{float}$)
- Examples of IO routines:
 - Reading in **wv-socket.js**
 - Writing in **wsServer/wv.c**



GUI Call-back Signatures



- function **InitUI()**
 - Invoked once to initialize the UI variables and state
- function **UpdateUI()**
 - Called in the rendering loop so that the state of the UI can be adjusted
 - Note: if the state is modified directly in an event handler the rendering for that frame may be corrupted
- function **UpdateView()**
 - Allows for the adjustment of the viewMatrix before the scene is rendered again
- function **UpdateCanvas(gl)**
 - Allows for the customization of what is rendered by additional WebGL calls
 - **gl** is the WebGL context




GUI Call-back Signatures



- function **Reshape(*gl*)**
 - Checks if the *canvas* has been resized or moved
 - If so, reestablishes the WebGL viewport in *gl*
- function **ServerMessage(*text*)**
 - Called when an ASCII *text* message has been received from the server (*UI text protocol*)
 - Note: this is invoked from a WebSocket event handler


Usage examples can be found in **SimpleUI.js**



Other Useful Functions



- **wvServerDown()**
 - a required call-back function that is invoked when the server has closed down
 - this can be because the server has aborted or the server was taken down gracefully
- **wv.socketUt.send(*text*)**
 - wv (**wv** globals), socketUt (*UI text* interface)
 - Send the string ***text*** to the server using WebSockets
 - Communicates GUI information to the server
 - Can be used from within any call-back (except **wvServerDown**)



Registering GUI Call-backs



- **wv.setCallback(*cbName*, *cbFn*)**
 - This sets the specified call-back to the function ***cbFn*** (which has a signature as described in the previous slides)
 - ***cbName*** can be one of the following strings: “InitUI”, “UpdateCanvas”, “UpdateUI”, “UpdateView”, “ServerMessage”, or “Reshape”. Any other string is an error.
 - There are useful defaults for both “UpdateView” and “Reshape” (see **wv-cbManage.js**). All other call-backs should be specified for a fully functional UI.




Example usage can be found in **wv.js**

- **Viewer**

- Tested against:
 - Google Chrome
 - Mozilla FireFox (& SeaMonkey)
 - Apple Safari (at Rev 6.0 or higher)
- Greater than 18 MegaTriangles per second for large **VBOs** on a MacBook Pro i7 2.8MHz 15" Mid-2010 (Chrome about 20% slower than SeaMonkey)

- **Server-like Implementation**

- Python options:
 - pywebsockets
 - ws4py
 - gevent-websocket
- Use of **libwebsockets** open source project (<http://git.warmcat.com/cgi-bin/cgit/libwebsockets>)
 - C API to specify data and allow for GUI IO
 - Used to generate the *Procedural-based Server-side API*



Procedural-based Server-side API




- **createContext**

```
wvContext *context =  
    wv_createContext(int bias,    float fov, float zNear,  
                    float zFar, float *eye, float *center,  
                    float *up )  
  
call iv_createContext(I*4 bias,    R*4    fov,    R*4    zNear,  
                     R*4    zFar, R*4    eye,    R*4    center,  
                     R*4    up,   I*8    context)
```

Initializes a WebViewer Context.

bias	the offset used for indexing (usually either 0 or 1)
fov	the field of view for the perspective (angles)
zNear	the Z value for the clipping plane closest to the observer
zFar	the Z value for the clipping plane farthest from the observer
eye	the position of the observer (X,Y,Z)
center	the focus for the viewing matrix
up	a normalized vector referring to positive Y
context	the returned WebViewer context



Procedural-based Server-side API



- **setCallback**

```
wv_setCallback(wvContext *context, callbackFn)
```

Sets the message handling routine, where the function has the same calling sequence as **browserMessage**.

context the WebViewer context (from **wv_createContext**)
callbackFn the function to use for **browserMessage**


This is required when using the dynamic version of the library

- **setUserPtr**

```
wv_setUserPtr(wvContext *context, int index)  
call iv_setUserPtr(I*8                      context, I*8 pointer)
```

Sets a user defined pointer that can be used to pass data through to the message handling routine.

context the WebViewer context (from **wv_createContext**)
pointer the C pointer to pass to **browserMessage**



Procedural-based Server-side API




- **startServer**

```
status = ww_startServer(int port, char *dev, char *path,  
                        char *key, int opts, wwContext *context)  
status = iv_startServer(I*4 port, C** dev, C** path,  
                        C** key, I*4 opts, I*8 context)
```

Starts a server thread on the WebViewer Context. The calling thread of execution continues. Use **statusServer** to determine the state of the connections.

port	the socket port to use for communication
dev	the network interface device name (can be NULL)
path	the path to locate certificate (if secure transmissions are used) *
key	the file path for the private key (if secure transmissions are used) *
opts	0, or 1 (Defeat the client mask)
context	the WebViewer context (from createContext)
status	the server instance/return status (negative is an error)

* Note: see building with SSL



Procedural-based Server-side API



- **statusServer**

```
status = wv_statusServer(int server)
status = iv_statusServer(I*4 server)
```

Checks the state of the server connections.

server the server instance (from **startServer**)

status the state (negative is an error):


0 - all clients have disconnected

1 - active

- **cleanupServers**

```
wv_cleanupServers()
call iv_cleanupServers()
```

Cleans up all memory associated with this API. Should be used as the last function in this suite.



Procedural-based Server-side API




- **setData**

```
status = wv_setData(int dtype, int len, void *data,  
                   int VBOcomp, wvData *item)  
status = iv_setData(I*4 dtype, I*4 len, ANY data,  
                   I*4 VBOcomp, I*8 item)
```

Sets the data associated with an item to be used with **addGPrim** and **modGPrim**. Striping is internally performed where necessary.

dtype	the type of the data array (see wsss.h or wsserver.inc)
len	the number of elements in the data array (Vertices , Normals , and Colors require 3 words per element)
data	the data array of type dtype
VBOcomp	the type of the VBO component (see wsss.h or wsserver.inc)
item	the output placement for the item
status	the return status (negative is an error)



Procedural-based Server-side API




- **adjustVerts**

```
wv_adjustVerts(wvData *item, float *focus)
call iv_adjustVerts(I*8      item, R*4      focus)
```

Allows for the adjustment of the vertex coordinates so they fit into screen coordinates (not clipped away).

item	the <i>Vertices</i> component (from setData)
focus	a vector of length 4 that is used to adjust the coordinates
	the first is subtracted from the X coordinate
	the second is subtracted from the Y coordinate
	the third is subtracted from the Z coordinate
	the forth is used to normalize (divide) all coordinates



Procedural-based Server-side API




- **addGPrim**

```
status = wv_addGPrim(wvContext *context, char *name, int gtype,  
                    int attrs, int nItems, wvData *items)  
status = iv_addGPrim(I*8 context, C** name, I*4 gtype,  
                    I*4 attrs, I*4 nItems, I*8 items)
```

Creates and adds this Graphics Primitive to the scene graph associated with this context.

context	the WebViewer context (from <code>createContext</code>)
name	unique (in the scene graph) name of the primitive
gtype	the graphics primitive type: <i>Point</i> , <i>Line</i> , <i>Triangle</i> (see <code>wsss.h</code> or <code>wsserver.inc</code>)
attrs	the initial plotting attributes (see <code>wsss.h</code> or <code>wsserver.inc</code>)
nItems	the number of components used to define the primitive
items	the components (from <code>setData</code>)
status	the index created for the primitive (where negative is an error)



Procedural-based Server-side API




- **modGPrim**

```
status = wv_modGPrim(wvContext *context, int index,  
                    int nItems, wvData *items)  
status = iv_modGPrim(I*8 context, I*4 index,  
                    I*4 nItems, I*8 items)
```

Modifies an existing Graphics Primitive in scene graph associated with this context.

context	the WebViewer context (from createContext)
index	the index created for the primitive (from addGPrim)
nItems	the number of components to modify in the primitive
items	the components (from setData)
status	the return status (where negative is an error)



Procedural-based Server-side API




- **addArrowHeads**

```
status = wv_addArrowHeads(wvContext *context, int index,  
                           float size, int nHeads, int *heads)  
status = iv_addArrowHeads(I*8 context, I*4 index,  
                           R*4 size, I*4 nHeads, I*4 heads)
```

Add Arrow Head decorations (in the foreground color) to an existing *Line* Graphics Primitive associated with this context.

context	the WebViewer context (from createContext)
index	the index created for the primitive (from addGPrim)
size	the size of the arrow head if adjustVerts is in use, the size should be divided by focus[3]
nHead	the number of head definitions
heads	the head definitions (index into the line segments -- if negative the head position (and direction) is associated with the first point in the segment, otherwise it is the second position. This is always bias 1.
status	the return status (where negative is an error)



Procedural-based Server-side API




- **setKey**

```
status = ww_setKey(wwContext *context, int nCol, float *colors,  
                  float beg, float end, char *title)  
status = iv_setKey(I*8 context, I*4 nCol, R*4 colors,  
                  R*4 beg, R*4 end, C** title)
```

Specifies the color key that gets drawn at the browser.

context	the WebViewer context (from <code>createContext</code>)
nCol	the number of colors found in the key – a 0 removes the key
colors	the colors for each entry (rgb) – $nCol \times 3$ in length
beg	the key value for the first color
end	the key value for the last color
title	the text written above the colors in the key
status	the return status (where negative is an error)



Procedural-based Server-side API



- **removeGPrim**

```
wv_removeGPrim(wvContext *context, int index)
call iv_removeGPrim(I*8 context, I*4 index)
```

Removes an existing Graphics Primitive in scene graph associated with this context.


context the WebViewer context (from `createContext`)
index the index created for the primitive (from `addGPrim`)

- **removeAll**

```
wv_removeAll(wvContext *context)
call iv_removeAll(I*8 context)
```

Removes all Graphics Primitive from the scene graph associated with this context.

context the WebViewer context (from `createContext`)



Procedural-based Server-side API



- **indexGPrim**

```
status = wv_indexGPrim(wvContext *context, char *name)
status = iv_indexGPrim(I*8 context, C** name)
```

Finds the index given the name for an existing Graphics Primitive in scene graph associated with this context.


context the WebViewer context (from **createContext**)
name the name of the GPrim in the scene graph
status the index (where a negative value is an error)

- **printGPrim**

```
wv_printGPrim(wvContext *context, int index)
call iv_printGPrim(I*8 context, I*4 index)
```

Prints the Graphics Primitive to standard output.

context the WebViewer context (from **createContext**)
index the index created for the primitive (from **addGPrim**)



Procedural-based Server-side API



- **nClientServer**

```
status = wv_nClientServer(int server)
status = iv_nClientServer(I*4 server)
```

Returns the number of clients connected to the server.

server the server instance (from **startServer**)
status the number of clients (negative is an error)


- **activeInterfaces**

```
status = wv_activeInterfaces(int server, int *nws, void ***wsi)
status = iv_activeInterfaces(I*4 server, I*4 nws, I*8 wsi)
```

Returns the active *text* interfaces for each attached client.

server the server instance (from **startServer**)
nws the number of *text* interfaces (the number of clients)
wsi a returned pointer to the list of active interfaces

FORTTRAN note: nws must be the length of wsi on input, -999 is error flag for not large enough.



Procedural-based Server-side API



- **killInterface**

```
wv_killInterface(int server, void *wsi)
call iv_killInterface(I*4 server, I*8 wsi)
```

Aborts the client associated with the *text* Interface.


server the server instance (from **startServer**)
wsi the interfaces (client) to shutdown

- **handShake**

```
status = wv_handShake(wvContext *context)
status = iv_handShake(I*8 context)
```

Performs coarse-level handshaking. Both **addGPrim** and **modGPrim** will do fine-level handshaking, but to fully synchronize a larger suite of updates use this function.

context the WebViewer context (from **createContext**)
status 0 – the data is released to send, 1 – the data is grabbed until invoked again when the updated GPrims will be sent



Procedural-based Server-side API



- **postMessage**

```
status = wv_postMessage(int server, char *text)
status = iv_postMessage(I*4 server, C** text)
```

Allows the server to post messages that will be intercepted by the **browserMessage** call-back.


server the server instance (from **startServer**)
text the ASCII text to be sent to **browserMessage**.
status a negative value is an error

- **makeMessage**

```
status = wv_makeMessage(void *wsi, char *text)
status = iv_makeMessage(I*8 wsi, C** text)
```

Allows **browserMessage** to post messages to itself.

wsi a pointer to the WebSocket Interface Structure
text the ASCII text to be sent to **browserMessage** when it returns
status a negative value is an error



Procedural-based Server-side API



Callback Required to *catch* Client Messages


- **browserMessage**

```
void      browserMessage(void *uPtr, void *wsi, char *text, int len)
subroutine browserMessage(I*8  uPtr, I*8  wsi, C**  text)
```

This required routine gets called for each message sent from a client (or a server instance).

uPtr	the user pointer set by wv_setUserPtr
wsi	a pointer to the WebSocket Interface Structure NULL if coming from a Server instance
text	the ASCII text received from the Browser (or internally)
len	the length of the text

- Notes:
- (1) invoking **wv_makeMessage** from within this routine defers reentry until **browserMessage** (or appropriate callback) returns.
 - (2) call **wv_setCallBack** with this function before **wv_startServer** (even if it has this name) when using the dynamic library (the default).
 - (3) FORTRAN requires the use of the static library.



Procedural-based Server-side API



Text based communication to the Client(s)

- **broadcastText**

```
wv_broadcastText(char *text)
call iv_broadcastText(C** text)
```

Sends the text to all active clients (Browsers).


text the text to send

- **sendText**

```
wv_sendText(void *wsi, char *text)
call iv_sendText(I*8 wsi, C** text)
```

Sends the text to the specific client designated by wsi.

wsi the WebSocket Interface Structure (from **browserMessage**)
text the text to send



Procedural-based Server-side API



FORTRAN Only Utility Functions

- **setPsize**

```
call iv_setPsize(I*8 context, I*4 index, R*4 size)
```

Sets the Point Size in an existing Graphics Primitive in scene graph associated with this context.


context	the WebViewer context (from createContext)
index	the index created for the primitive (from addGPrim)
size	the point size in pixels

- **setLwidth**

```
call iv_setLwidth(I*8 context, I*4 index, R*4 width)
```

Sets the Line Width in an existing Graphics Primitive.

context	the WebViewer context (from createContext)
index	the index created for the primitive (from addGPrim)
width	the line width in pixels



Procedural-based Server-side API




- **usleep**

`call iv_usleep(I*4 micsec)`

Suspends the calling thread for the specified number of microseconds

micsec the number of microseconds



Building with SSL (for secure IO)



- **In the wvServer directory:**
 - Type: “make cleanall” (or “nmake -f NMakefile cleanall”)
- **Modify the MAKE (SSL.make or SLL.mak):**
 - Specify the include and lib locations for OpenSSL
- **MAKE:**
 - Type: “make” (or “nmake -f NMakefile”)
- **Modify the server code:**
 - Fill in `path` and `key` of `wv_startServer`
- **Modify other MAKEs that build servers:**
 - Link in OpenSSL and Crypto libraries (see SSL makes)
- **In the HTML (top level script):**
 - Use `wv.getSockets("wss:actualURL");`

