

10.2.1.9 Lab – Configure a Site-to-Site IPsec VPN Using ISR CLI and ASA 5505 ASDM Answers


 itexamanswers.net/10-2-1-9-lab-configure-a-site-to-site-ipsec-vpn-using-isr-cli-and-asa-5505-asdm-answers.html

June 6, 2022

10.2.1.9 Lab – Configure a Site-to-Site IPsec VPN Using ISR CLI and ASA 5505 ASDM (Instructor Version)

Instructor Note: Red font color or gray highlights indicate text that appears in the instructor copy only.

Topology



Note: ISR G2 devices use GigabitEthernet interfaces instead of FastEthernet interfaces.

IP Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway	Switch Port
R1	G0/0	209.165.200.225	255.255.255.248	N/A	ASA E0/0
	S0/0/0 (DCE)	10.1.1.1	255.255.255.252	N/A	N/A

Device	Interface	IP Address	Subnet Mask	Default Gateway	Switch Port
R2	S0/0/0	10.1.1.2	255.255.255.252	N/A	N/A
	S0/0/1 (DCE)	10.2.2.2	255.255.255.252	N/A	N/A
R3	G0/1	172.16.3.1	255.255.255.0	N/A	S3 F0/5
	S0/0/1	10.2.2.1	255.255.255.252	N/A	N/A
ASA	VLAN 1 (E0/1)	192.168.1.1	255.255.255.0	NA	S2 Fa0/24
	VLAN 2 (E0/0)	209.165.200.226	255.255.255.248	NA	R1 F0/0
	VLAN 3 (E0/2)	192.168.2.1	255.255.255.0	NA	S1 F0/24
PC-A	NIC	192.168.2.3	255.255.255.0	192.168.2.1	S1 F0/6
PC-B	NIC	192.168.1.3	255.255.255.0	192.168.1.1	S2 F0/18
PC-C	NIC	172.16.3.3	255.255.255.0	172.16.3.1	S3 F0/18

Objectives

Part 1: Basic Router/Switch/PC Configuration

- Cable the network and clear previous device settings, as shown in the topology.
- Configure basic settings for routers.
- Configure PC host IP settings.
- Verify connectivity.
- Save the basic running configuration for each router and switch.

Part 2: Accessing the ASA Console and ASDM

- Access the ASA console.
- Clear the previous ASA configuration settings.
- Bypass Setup mode.
- Use the CLI command script to configure the ASA.
- Verify HTTP ASDM access.

Part 3: Configuring the ISR as a Site-to-Site IPsec VPN Endpoint Using the CLI

- Configure basic VPN connection information settings.

- Specify IKE policy parameters.
- Configure a transform set.
- Specify traffic to protect.
- Review the summary of the configuration.
- Review the site-to-site VPN tunnel configuration.

Part 4: Configuring the ASA as a Site-to-Site IPsec VPN Endpoint Using ASDM

- Access ASDM.
- Review the ASDM Home screen.
- Start the VPN wizard.
- Configure peer device identification.
- Specify the traffic to protect.
- Configure authentication.
- Configure miscellaneous settings.
- Review the configuration summary and deliver the commands to the ASA.
- Verify the ASDM VPN connection profile.
- Test the VPN configuration from R3.
- Use ASDM monitoring to verify the tunnel.

Background/Scenario

In addition to acting as a remote access VPN concentrator, the ASA can provide site-to-site IPsec VPN tunneling. The tunnel can be configured between two ASAs or between an ASA and another IPsec VPN-capable device, such as an ISR, as is the case with this lab.

Your company has two locations connected to an ISP. R1 represents a customer-premise equipment (CPE) device managed by the ISP. R2 represents an intermediate Internet router. R3 connects users at the remote branch office to the ISP. The ASA is an edge security device that connects the internal corporate network and DMZ to the ISP while providing NAT services to inside hosts.

Management has asked you to provide a dedicated site-to-site IPsec VPN tunnel between the ISR router at the remote branch office and the ASA device at the corporate site. This tunnel will protect traffic between the branch office LAN and the corporate LAN, as it passes through the Internet. The site-to-site VPN does not require a VPN client on the remote or corporate site host computers. Traffic from either LAN to other Internet destinations is routed by the ISP and is not protected by the VPN tunnel. The VPN tunnel will pass through R1 and R2; both routers are not aware of the tunnel's existence.

In Part 1 of this lab, you will configure the topology and non-ASA devices. In Part 2, you will prepare the ASA for ASDM access. In Part 3, you will use the CLI to configure the R3 ISR as a site-to-site IPsec VPN endpoint. In Part 4, you will configure the ASA as a site-to-site IPsec VPN endpoint using the ASDM VPN wizard.

Note: The router commands and output in this lab are from a Cisco 1941 router with Cisco IOS Release 15.4(3)M2 (with a Security Technology Package license). Other routers and Cisco IOS versions can be used. See the Router Interface Summary Table at the end of this lab to determine which interface identifiers to use based on the equipment in the lab. Depending on the router model and Cisco IOS version, the commands available and the output produced might vary from what is shown in this lab.

The ASA used with this lab is a Cisco model 5505 with an 8-port integrated switch, running OS version 9.2(3) and ASDM version 7.4(1) and comes with a Base license that allows a maximum of three VLANs.

Note: Before beginning, ensure that the routers and switches have been erased and have no startup configurations.

Instructor Note: Instructions for erasing switches and routers are provided in Chapter 0.0.0.0. Instructions for erasing the ASA, accessing the console, and accessing ASDM are provided in this lab.

Required Resources

- 1 ASA 5505 (OS version 9.2(3) and ASDM version 7.4(1) and Base license or comparable)
- 3 routers (Cisco 1941 with Cisco IOS Release 15.4(3)M2 image with a Security Technology package license)
- 3 switches (Cisco 2960 or comparable) (not required)
- 3 PCs (Windows 7 or Windows 8.1, with SSH Client software installed)
- Serial and Ethernet cables, as shown in the topology
- Console cables to configure Cisco networking devices

Instructor Notes:

- This lab has four main parts. Part 1 and 2 can be performed separately but must be performed before parts 3 and 4. Part 2 prepares the ASA for ASDM access. Part 3 configures the R3 ISR as a site-to-site IPsec VPN endpoint using the CLI. Part 4 configures the opposite end of the tunnel on the ASA using ASDM. Parts 3 and 4 should be performed sequentially. Each part will use CLI and ASDM as required to verify the configuration.
- The main goal is to configure a site-to-site IPsec VPN between two sites using an ISR at one end of the tunnel and an ASA at the other end.
- The final running configs for all devices are found at the end of the lab.

Part 1: Basic Router/Switch/PC Configuration

In Part 1, you will set up the network topology and configure basic settings on the routers, such as interface IP addresses and static routing.

Note: Do not configure any ASA settings at this time.

Step 1: Cable the network and clear previous device settings.

Attach the devices shown in the topology diagram and cable as necessary. Ensure that the routers and switches have been erased and have no startup configurations.

Step 2: Configure R1 using the CLI script.

In this step, you will use the following CLI script to configure basic settings on R1. Copy and paste the basic configuration script commands listed below. Observe the messages as the commands are applied to ensure that there are no warnings or errors.

Note: Depending on the router model, interfaces might be numbered differently than those listed. You might need to alter the designations accordingly.

Note: Passwords in this task are set to a minimum of 10 characters and are relatively simple for the purposes of performing the lab. More complex passwords are recommended in a production network.

```
hostname R1
security passwords min-length 10
enable algorithm-type scrypt secret cisco12345
username admin01 algorithm-type scrypt secret admin01pass
ip domain name ccnasecurity.com
line con 0
  login local
  exec-timeout 5 0
  logging synchronous
exit
line vty 0 4
  login local
  transport input ssh
  exec-timeout 5 0
  logging synchronous
exit
interface gigabitethernet 0/0
  ip address 209.165.200.225 255.255.255.248
  no shut
exit
int serial 0/0/0
  ip address 10.1.1.1 255.255.255.252
  clock rate 2000000
  no shut
exit
ip route 0.0.0.0 0.0.0.0 Serial0/0/0
crypto key generate rsa general-keys modulus 1024
```

Step 3: Configure R2 using the CLI script.

In this step, you will use the following CLI script to configure basic settings on R2. Copy and paste the basic configuration script commands listed below. Observe the messages as the commands are applied to ensure that there are no warnings or errors.

```
hostname R2
security passwords min-length 10
enable algorithm-type scrypt secret cisco12345
username admin01 algorithm-type scrypt secret admin01pass
ip domain name ccnasecurity.com
line con 0
  login local
  exec-timeout 5 0
  logging synchronous
exit
line vty 0 4
  login local
  transport input ssh
  exec-timeout 5 0
  logging synchronous
exit
interface serial 0/0/0
  ip address 10.1.1.2 255.255.255.252
  no shut
exit
interface serial 0/0/1
  ip address 10.2.2.2 255.255.255.252
  clock rate 2000000
  no shut
exit
ip route 209.165.200.224 255.255.255.248 Serial0/0/0
ip route 172.16.3.0 255.255.255.0 Serial0/0/1
crypto key generate rsa general-keys modulus 1024
```

Step 4: Configure R3 using the CLI script.

In this step, you will use the following CLI script to configure basic settings on R3. Copy and paste the basic configuration script commands listed below. Observe the messages as the commands are applied to ensure that there are no warnings or errors.

```
hostname R3
security passwords min-length 10
enable algorithm-type scrypt secret cisco12345
username admin01 algorithm-type scrypt secret admin01pass
ip domain name ccnasecurity.com
line con 0
  login local
  exec-timeout 5 0
  logging synchronous
exit
line vty 0 4
  login local
  transport input ssh
  exec-timeout 5 0
  logging synchronous
exit
interface gigabitethernet 0/1
  ip address 172.16.3.1 255.255.255.0
  no shut
exit
int serial 0/0/1
  ip address 10.2.2.1 255.255.255.252
  no shut
exit
ip route 0.0.0.0 0.0.0.0 Serial0/0/1
crypto key generate rsa general-keys modulus 1024
```

Step 5: Configure PC host IP settings.

Configure a static IP address, subnet mask, and default gateway for PC-A, PC-B, and PC-C as shown in the IP Addressing table.

Step 6: Verify connectivity.

Because the ASA is the focal point for the network zones, and it has not yet been configured, there will be no connectivity between devices that are connected to it. However, PC-C should be able to ping the R1 interface Go/o. From PC-C, ping the R1 Go/o IP address (209.165.200.225). If these pings are unsuccessful, troubleshoot the basic device configurations before continuing.

Note: If you can ping from PC-C to R1 Go/o and So/o/o, you have demonstrated that static routing is configured and functioning correctly.

Save the **running configuration** for each router.

Part 2: Accessing the ASA Console and ASDM

Step 1: Clear the previous ASA configuration settings.

- a. Use the write erase command to remove the startup-config file from flash memory.

Note: The erase startup-config IOS command is not supported on the ASA.

- b. Use the reload command to restart the ASA. This causes the ASA to display in CLI Setup mode. If you see the System config has been modified. Save? [Y]es/[N]o: message, type n, and press Enter.

Step 2: Bypass Setup mode.

When the ASA completes the reload process, it should detect that the startup configuration file is missing and go into Setup mode. If it does go into Setup mode, repeat Step 2.

- a. When prompted to preconfigure the firewall through interactive prompts (Setup mode), respond with no.
- b. Enter privileged EXEC mode with the enable command. The password should be kept blank (no password).

Step 3: Configure the ASA by using the CLI script.

In this step, you will use a CLI script to configure basic settings, the firewall, and the DMZ.

- a. Use the show run command to confirm that there is no previous configuration in the ASA other than the defaults that the ASA automatically inserts.
- b. Enter global configuration mode. When prompted to enable anonymous call-home reporting, respond no.
- c. Copy and paste the Pre-VPN Configuration Script commands listed below at the ASA global configuration mode prompt to start configuring the SSL VPNs.
- d. Observe the messages as the commands are applied to ensure that there are no warnings or errors. If prompted to replace the RSA key pair, respond yes.

```

hostname CCNAS-ASA
domain-name ccnasecurity.com
enable password cisco12345
!
interface Ethernet0/0
  switchport access vlan 2
  no shut
!
interface Ethernet0/1
  switchport access vlan 1
  no shut
!
interface Ethernet0/2
  switchport access vlan 3
  no shut
!
interface Vlan1
  nameif inside
  security-level 100
  ip address 192.168.1.1 255.255.255.0
!
interface Vlan2
  nameif outside
  security-level 0
  ip address 209.165.200.226 255.255.255.248
!
interface Vlan3
  no forward interface Vlan1
  nameif dmz
  security-level 70
  ip address 192.168.2.1 255.255.255.0
!
object network inside-net
  subnet 192.168.1.0 255.255.255.0
!
object network dmz-server
  host 192.168.2.3
!
access-list OUTSIDE-DMZ extended permit ip any host 192.168.2.3
!
object network inside-net
  nat (inside,outside) dynamic interface
!
object network dmz-server
  nat (dmz,outside) static 209.165.200.227
!
access-group OUTSIDE-DMZ in interface outside
!
route outside 0.0.0.0 0.0.0.0 209.165.200.225 1
!
username admin01 password admin01pass
!

```

```
aaa authentication ssh console LOCAL
aaa authentication http console LOCAL
!
http server enable
http 192.168.1.0 255.255.255.0 inside
ssh 192.168.1.0 255.255.255.0 inside
ssh timeout 10
!
class-map inspection_default
  match default-inspection-traffic
policy-map global_policy
  class inspection_default
    inspect icmp
!
crypto key generate rsa modulus 1024
```

e. At the privileged EXEC mode prompt, issue the write mem (or copy run start) command to save the running configuration to the startup configuration and the RSA keys to non-volatile memory.

Part 3: Configuring the ISR as a Site-to-Site IPsec VPN Endpoint Using the CLI

In Part 3 of this lab, you will configure R3 as an IPsec VPN endpoint for the tunnel between R3 and the ASA. R1 and R2 are unaware of the tunnel.

Step 1: Verify connectivity from the R3 LAN to the ASA.

In this step, you will verify that PC-C on the R3 LAN can ping the ASA outside interface.

Ping the ASA IP address of 209.165.200.226 from PC-C.

```
PC-C:\> ping 209.165.200.226
```

If the pings are unsuccessful, troubleshoot the basic device configurations before continuing.

Step 2: Enable IKE policies on R3.

IPsec is an open framework that allows for the exchange of security protocols as new technologies and encryption algorithms are developed.

There are two central configuration elements in the implementation of an IPsec VPN:

- Implement Internet Key Exchange (IKE) parameters.
- Implement IPsec parameters.

a. Verify that IKE is supported and enabled.

IKE Phase 1 defines the key exchange method used to pass and validate IKE policies between peers. In IKE Phase 2, the peers exchange and match IPsec policies for the authentication and encryption of data traffic.

IKE must be enabled for IPsec to function. IKE is enabled, by default, on IOS images with cryptographic feature sets. If it is disabled, you can enable it with the `crypto isakmp enable` command. Use this command to verify that the router IOS supports IKE and that it is enabled.

```
R3(config)# crypto isakmp enable
```

Note: If you cannot execute this command on the router, you must upgrade to the IOS image that includes the Cisco cryptographic services.

b. Establish an ISAKMP policy and view the available options.

To allow IKE Phase 1 negotiation, you must create an ISAKMP policy and configure a peer association involving that ISAKMP policy. An ISAKMP policy defines the authentication and encryption algorithms, and the hash function used to send control traffic between the two VPN endpoints. When an ISAKMP security association has been accepted by the IKE peers, IKE Phase 1 has been completed. IKE Phase 2 parameters will be configured later.

Issue the `crypto isakmp policy number global configuration mode` command on R1 for policy 10.

```
R1(config)# crypto isakmp policy 10
```

c. View the various IKE parameters available using Cisco IOS help by typing a question mark (?).

```
R1(config-isakmp)# ?
```

ISAKMP commands:

<code>authentication</code>	Set authentication method for protection suite
<code>default</code>	Set a command to its defaults
<code>encryption</code>	Set encryption algorithm for protection suite
<code>exit</code>	Exit from ISAKMP protection suite configuration mode
<code>group</code>	Set the Diffie-Hellman group
<code>hash</code>	Set hash algorithm for protection suite
<code>lifetime</code>	Set lifetime for ISAKMP security association
<code>no</code>	Negate a command or set its defaults

Step 3: Configure ISAKMP policy parameters on R3.

The encryption algorithm determines how confidential the control channel between the endpoints is. The hash algorithm controls data integrity, which ensures that the data received from a peer has not been tampered with in transit. The authentication type ensures that the

packet was sent and signed by the remote peer. The Diffie-Hellman group is used to create a secret key shared by the peers that has not been sent across the network.

a. Configure an ISAKMP policy with a priority of 10. Use pre-shared key as the authentication type, 3des for the encryption algorithm, sha as the hash algorithm, and the Diffie-Hellman group 2 key exchange.

Note: Older versions of Cisco IOS do not support AES 256 encryption and SHA as a hash algorithm. Substitute whatever encryption and hashing algorithm your router supports. Ensure that the same changes are made on R3 in order to be in sync.

```
R3(config)# crypto isakmp policy 10
R3(config-isakmp)# authentication pre-share
R3(config-isakmp)# encryption 3des
R3(config-isakmp)# hash sha
R3(config-isakmp)# group 2
R3(config-isakmp)# end
```

b. Verify the IKE policy with the show crypto isakmp policy command.

```
R3# show crypto isakmp policy
```

```
Global IKE policy
Protection suite of priority 10
    encryption algorithm:   Three key triple DES
    hash algorithm:         Secure Hash Standard
    authentication method:  Pre-Shared Key
    Diffie-Hellman group:   #2 (1024 bit)
    lifetime:               3600 seconds, no volume limit
```

Step 4: Configure pre-shared keys.

Because pre-shared keys are used as the authentication method in the IKE policy, a key must be configured on each router that points to the other VPN endpoint. These keys must match for authentication to be successful. The global configuration mode `crypto isakmp key key-string address ip-address` command is used to enter a pre-shared key. Use the IP address of the remote peer. The IP address is the remote interface that the peer would use to route traffic to the local router.

Which IP address should you use to configure the IKE peer, given the topology diagram and IP addressing table?

The IP address should be the ASA outside IP address of 209.165.200.226.

Each IP address that is used to configure the IKE peers is also referred to as the IP address of the remote VPN endpoint. Configure the pre-shared key of SECRET-KEY on R3. Production networks should use a complex key. This command points to the remote ASA outside IP address.

```
R3(config)# crypto isakmp key SECRET-KEY address 209.165.200.226
```

Step 5: Configure the IPsec transform set and lifetime.

a. The IPsec transform set is another crypto configuration parameter that routers negotiate to form a security association. It is configured using the `crypto ipsec transform-set tag global` configuration command. Configure the transform set with the tag `ESP-TUNNEL`. Use `?` to see which parameters are available.

```
R3(config)# crypto ipsec transform-set ESP-TUNNEL ?
  ah-md5-hmac      AH-HMAC-MD5 transform
  ah-sha-hmac      AH-HMAC-SHA transform
  ah-sha256-hmac   AH-HMAC-SHA256 transform on R3
  ah-sha384-hmac   AH-HMAC-SHA384 transform
  ah-sha512-hmac   AH-HMAC-SHA512 transform
  comp-lzs        IP Compression using the LZS compression algorithm
  esp-3des        ESP transform using 3DES(EDE) cipher (168 bits)
  esp-aes         ESP transform using AES cipher
  esp-des         ESP transform using DES cipher (56 bits)
  esp-gcm         ESP transform using GCM cipher
  esp-gmac        ESP transform using GMAC cipher
  esp-md5-hmac    ESP transform using HMAC-MD5 auth
  esp-null        ESP transform w/o cipher
  esp-seal        ESP transform using SEAL cipher (160 bits)
  esp-sha-hmac    ESP transform using HMAC-SHA auth
  esp-sha256-hmac ESP transform using HMAC-SHA256 auth
  esp-sha384-hmac ESP transform using HMAC-SHA384 auth
  esp-sha512-hmac ESP transform using HMAC-SHA512 auth
```

b. In our Site-to-site VPN with the ASA, we will use the two highlighted parameters. Complete the command by entering the two highlighted parameters.

```
R3(config)# crypto ipsec transform-set ESP-TUNNEL esp-3des esp-sha-hmac
```

What is the function of the IPsec transform set?

The IPsec transform set specifies the cryptographic algorithms and functions (transforms) that a router employs on the data packets sent through the IPsec tunnel. These algorithms include the encryption, encapsulation, authentication, and data integrity services that IPsec can apply.

Step 6: Define interesting traffic.

To make use of the IPsec encryption with the VPN, it is necessary to define extended access lists to tell the router which traffic to encrypt. A packet that is permitted by an access list used for defining IPsec traffic is encrypted if the IPsec session is configured correctly. A packet that is denied by one of these access lists is not dropped. The packet is sent

unencrypted. Also, like any other access list, there is an implicit deny at the end, which means the default action is to not encrypt traffic. If there is no IPsec security association correctly configured, no traffic is encrypted and traffic is forwarded unencrypted.

In this scenario, from the perspective of R3, the traffic you want to encrypt is traffic going from R3's Ethernet LAN to the ASA inside LAN or vice versa from the perspective of the ASA.

Configure the IPsec VPN interesting traffic ACL on R3.

```
R3(config)# ip access-list extended VPN-ACL
R3(config-ext-nacl)# remark Link to the CCNAS-ASA
R3(config-ext-nacl)# permit ip 172.16.3.0 0.0.0.255 192.168.1.0 0.0.0.255
R3(config-ext-nacl)# exit
```

Does IPsec evaluate whether the access lists are mirrored as a requirement to negotiate its security association?

Yes. IPsec does evaluate whether access lists are mirrored. IPsec does not form a security association if the peers do not have mirrored access lists to select interesting traffic.

Step 7: Create and apply a crypto map.

A crypto map associates traffic that matches an access list to a peer and various IKE and IPsec settings. After the crypto map is created, it can be applied to one or more interfaces. The interfaces that it is applied to should be the interfaces facing the IPsec peer.

To create a crypto map, use the crypto map name sequence-num type global configuration command to enter crypto map configuration mode for that sequence number. Multiple crypto map statements can belong to the same crypto map and are evaluated in ascending numerical order.

a. Create the crypto map on R3, name it S2S-MAP, and use 10 as the sequence number. Use a type of ipsec-isakmp, which means IKE is used to establish IPsec security associations. A message displays after the command is issued.

```
R3(config)# crypto map S2S-MAP 10 ipsec-isakmp
% NOTE: This new crypto map will remain disabled until a peer
        and a valid access list have been configured.
R3(config-crypto-map)#
```

b. Use the match address access-list command to specify which access list defines which traffic to encrypt.

```
R3(config-crypto-map)# match address VPN-ACL
```

c. Setting a peer IP or hostname is required. Set it to the ASA remote VPN endpoint interface using the following command.

```
R3(config-crypto-map)# set peer 209.165.200.226
```

d. Use the set transform-set tag command to hard code the transform set to be used with this peer.

```
R3(config-crypto-map)# set transform-set ESP-TUNNEL
R3(config-crypto-map)# exit
```

e. Apply the crypto map to interfaces.

Note: The SAs are not established until the crypto map has been activated by interesting traffic. The router generates a notification that crypto is now on.

Apply the crypto maps to the R3 Serial 0/0/1 interface.

```
R3(config)# interface Serial0/0/1
R3(config-if)# crypto map S2S-MAP
R3(config-if)# end
R3#
*Mar 9 06:23:03.863: %CRYPTO-6-ISAKMP_ON_OFF: ISAKMP is ON
R3#
```

Part 4: Configuring the ASA as a Site-to-Site IPsec VPN Endpoint Using ASDM

In Part 4 of this lab, you will configure the ASA as an IPsec VPN tunnel endpoint. The tunnel between the ASA and R3 passes through R1 and R2.

Step 1: Access ASDM.


a. Open a browser on PC-B and test the HTTPS access to the ASA by entering <https://192.168.1.1>. After entering the <https://192.168.1.1> URL, you should see a security warning about the website security certificate. Click Continue to this website. Click Yes for any other security warnings.

Note: Specify the HTTPS protocol in the URL.

b. At the ASDM welcome page, click Run ASDM. The ASDM-IDM Launcher will display.




c. Log in as user admin01 with the password admin01pass.




Step 2: Review the ASDM Home screen.

The Home screen displays and shows the current ASA device configuration and traffic flow statistics. Note the inside, outside, and dmz interfaces that were configured in Part 2 of this lab.



Step 3: Start the VPN wizard.


a. On the ASDM main menu, click Wizards > VPN Wizards > Site-to-Site VPN Wizard to open the Site-to-Site VPN Connection Setup Wizard Introduction window.



b. Review the on-screen text and topology diagram and click Next to continue.


Step 4: Configure peer device identification.

In the Peer Device Identification window, enter the IP address of the R3 Serial0/0/1 interface (10.2.2.1) as the Peer IP Address. Leave the default VPN Access Interface set to outside. The VPN tunnel will be between R3 So/o/1 and the ASA outside interface (VLAN 2 Eo/o). Click Next to continue.



Step 5: Specify the traffic to protect.


In the Traffic to protect window, enter inside-network/24 (192.168.1.0/24) as the Local Network and type 172.16.3.0/24 to add the R3 LAN as the Remote Network. Click Next to continue. A message may display stating that the certificate information is being retrieved.



Note: If the ASA does not respond, you may need to close the window and continue to the next step. If prompted to authenticate, log in again as admin01 with the password admin01pass.


Step 6: Configure authentication.

On the Security window, enter a pre-shared key of SECRET-KEY. You will not be using a device certificate. Click Next to continue.



Step 7: Configure miscellaneous settings.


In the NAT Exempt window, click the Exempt ASA check box for the inside interface. Click Next to continue.



Step 8: Review the configuration summary and deliver the commands to the ASA.


The Summary page is displayed next. Verify that the information configured is correct. You can click Back to make changes, or click Cancel and restart the VPN wizard (recommended). Click Finish to complete the process and deliver the commands to the ASA.

Note: If prompted to authenticate, log in again as admin01 with the password admin01pass.




Step 9: Verify the ASDM VPN connection profile.

The ASDM Configurations > Site-to-Site VPN > Connection Profiles screen displays the settings you configured. From this window, the VPN configuration can be verified and edited.



Step 10: Use ASDM monitoring to verify the tunnel.

On the ASDM menu bar, click Monitoring > VPN from the panels at the lower left of the screen. Click VPN Statistics > Sessions. Notice how there is no active session. This is because the VPN tunnel has not been established.



Step 11: Test the VPN configuration from PC-B.

a. To establish the VPN tunnel, interesting traffic must be generated. From PC-B, ping PC-C.

```

C:\Windows\system32\cmd.exe
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\NetAcad>ping 172.16.3.3

Pinging 172.16.3.3 with 32 bytes of data:
Request timed out.
Request timed out.
Reply from 172.16.3.3: bytes=32 time=40ms TTL=127
Reply from 172.16.3.3: bytes=32 time=41ms TTL=127

Ping statistics for 172.16.3.3:
    Packets: Sent = 4, Received = 2, Lost = 2 (50% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 40ms, Maximum = 41ms, Average = 40ms

C:\Users\NetAcad>

```

b. This generates interesting traffic. Notice how two pings failed before being successful. This is because the tunnel first had to be negotiated and established before the ICMP packets could be successful.

c. The VPN information is now being displayed on the ASDM Monitoring > VPN > VPN Statistics > Sessions page.

Note: You may need to click Refresh before the statistics will display.

The screenshot shows the Cisco ASDM 7.4 interface for ASA - 192.168.1.1. The left sidebar shows the navigation tree with 'Monitoring > VPN > VPN Statistics > Sessions' selected. The main content area displays the 'Sessions' page with the following data:

Type	Active	Cumulative	Peak Concurrent	Inactive
Site-to-Site VPN		1	1	1
IKEv1 IPsec		1	1	1

Below this is a 'Filter By' section with 'IPsec Site-to-Site' and '-- All Sessions --' selected. The main table shows active sessions:

Connection Profile	Protocol	Login Time	Bytes Tx
IP Address	Encryption	Duration	Bytes Rx
10.2.2.1	IKEv1 IPsec	20:22:46 UTC Tue May 12 2015	3382
10.2.2.1	IKEv1: (1)3DES IPsec: (1)3DES	0h:09m:49s	1704

The interface includes buttons for 'Details', 'Logout', 'Ping', and 'Refresh'. A status bar at the bottom indicates 'Data Refreshed Successfully.' and 'Last Updated: 5/12/15 1:33:48 PM'.

d. Click Encryption Statistics. You should see one or more sessions using the 3DES encryption algorithm.

Cisco ASDM 7.4 for ASA - 192.168.1.1

File View Tools Wizards Window Help

Home Configuration Monitoring Save Refresh Back Forward Help

VPN

VPN Statistics
Sessions
Crypto Statistics
Compression Statistics
Encryption Statistics
Global IKE/IPsec Statistics
Protocol Statistics
VLAN Mapping Sessions
Clientless SSL VPN
Easy VPN Client
VPN Connection Graphs
WSA Sessions

Interfaces
VPN
Routing
Properties
Logging

Monitoring > VPN > VPN Statistics > Encryption Statistics

Encryption Statistics

Each row represents one encryption algorithm type.

Show Statistics For: -- All Connection Profiles --

Encryption Algorithm	Sessions	Percentage
none	0	0%
DES	0	0%
3DES	2	100%
RC4	0	0%
AES 128	0	0%
AES 192	0	0%
AES 256	0	0%
AES-GCM-128	0	0%
AES-GCM-192	0	0%
AES-GCM-256	0	0%
AES-GMAC-128	0	0%
AES-GMAC-192	0	0%
AES-GMAC-256	0	0%

Refresh


Last Updated: 5/12/15 1:29:13 PM

Data Refreshed Successfully.

admin01 2

5/12/15 8:28:56 PM UTC

e. Click Crypto Statistics. You should see values for the number of packets encrypted and decrypted, security association (SA) requests, etc.



Reflection

Describe a situation where a site-to-site IPsec VPN would be preferable over other VPN options.

When a large number of hosts exist at a remote office and traffic between the office and a central site needs to be protected. One disadvantage of the site-to-site VPN is that traffic on the remote network (connecting host) is not protected. Only the traffic between the site-to-site tunnel endpoints is protected.

Router Interface Summary Table

Router Interface Summary

Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)

Router Interface Summary

2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.

Device Configs

ASA 5505 Config

```

CCNAS-ASA# show run
: Saved
:
: Hardware:   ASA5505, 512 MB RAM, CPU Geode 500 MHz
:
ASA Version 9.2(3)
!
hostname CCNAS-ASA
domain-name ccnasecurity.com
enable password 9D8jmmmgkfNZLETh encrypted
xlate per-session deny tcp any4 any4
xlate per-session deny tcp any4 any6
xlate per-session deny tcp any6 any4
xlate per-session deny tcp any6 any6
xlate per-session deny udp any4 any4 eq domain
xlate per-session deny udp any4 any6 eq domain
xlate per-session deny udp any6 any4 eq domain
xlate per-session deny udp any6 any6 eq domain
names
!
interface Ethernet0/0
  switchport access vlan 2
!
interface Ethernet0/1
!
interface Ethernet0/2
  switchport access vlan 3
!
interface Ethernet0/3
  shutdown
!
interface Ethernet0/4
  shutdown
!
interface Ethernet0/5
  shutdown
!
interface Ethernet0/6
  shutdown
!
interface Ethernet0/7
  shutdown
!
interface Vlan1
  nameif inside
  security-level 100
  ip address 192.168.1.1 255.255.255.0
!
interface Vlan2
  nameif outside
  security-level 0
  ip address 209.165.200.226 255.255.255.248

```

```

!
interface Vlan3
  no forward interface Vlan1
  nameif dmz
  security-level 70
  ip address 192.168.2.1 255.255.255.0
!
ftp mode passive
dns server-group DefaultDNS
  domain-name ccnasecurity.com
object network inside-net
  subnet 192.168.1.0 255.255.255.0
object network dmz-server
  host 192.168.2.3
object network NETWORK_OBJ_172.16.3.0_24
  subnet 172.16.3.0 255.255.255.0
object network NETWORK_OBJ_192.168.1.0_24
  subnet 192.168.1.0 255.255.255.0
access-list OUTSIDE-DMZ extended permit ip any host 192.168.2.3
access-list outside_cryptomap extended permit ip 192.168.1.0 255.255.255.0 172.16.3.0
255.255.255.0
pager lines 24
mtu inside 1500
mtu outside 1500
mtu dmz 1500
icmp unreachable rate-limit 1 burst-size 1
no asdm history enable
arp timeout 14400
no arp permit-nonconnected
nat (inside,outside) source static NETWORK_OBJ_192.168.1.0_24
NETWORK_OBJ_192.168.1.0_24 destination static NETWORK_OBJ_172.16.3.0_24
NETWORK_OBJ_172.16.3.0_24 no-proxy-arp route-lookup
!
object network inside-net
  nat (inside,outside) dynamic interface
object network dmz-server
  nat (dmz,outside) static 209.165.200.227
access-group OUTSIDE-DMZ in interface outside
route outside 0.0.0.0 0.0.0.0 209.165.200.225 1
timeout xlate 3:00:00
timeout pat-xlate 0:00:30
timeout conn 1:00:00 half-closed 0:10:00 udp 0:02:00 icmp 0:00:02
timeout sunrpc 0:10:00 h323 0:05:00 h225 1:00:00 mgcp 0:05:00 mgcp-pat 0:05:00
timeout sip 0:30:00 sip_media 0:02:00 sip-invite 0:03:00 sip-disconnect 0:02:00
timeout sip-provisional-media 0:02:00 uauth 0:05:00 absolute
timeout tcp-proxy-reassembly 0:01:00
timeout floating-conn 0:00:00
dynamic-access-policy-record DfltAccessPolicy
user-identity default-domain LOCAL
aaa authentication telnet console LOCAL
aaa authentication ssh console LOCAL
aaa authentication http console LOCAL

```

```

http server enable
http 192.168.1.0 255.255.255.0 inside
no snmp-server location
no snmp-server contact
crypto ipsec ikev1 transform-set ESP-AES-128-SHA esp-aes esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-128-MD5 esp-aes esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-SHA esp-aes-192 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-MD5 esp-aes-192 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-SHA esp-aes-256 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-MD5 esp-aes-256 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-128-SHA-TRANS esp-aes esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-128-SHA-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-AES-128-MD5-TRANS esp-aes esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-128-MD5-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-AES-192-SHA-TRANS esp-aes-192 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-SHA-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-AES-192-MD5-TRANS esp-aes-192 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-192-MD5-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-AES-256-SHA-TRANS esp-aes-256 esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-SHA-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-AES-256-MD5-TRANS esp-aes-256 esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-AES-256-MD5-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-3DES-SHA esp-3des esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-3DES-MD5 esp-3des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-3DES-SHA-TRANS esp-3des esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-3DES-SHA-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-3DES-MD5-TRANS esp-3des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-3DES-MD5-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-DES-SHA esp-des esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-DES-MD5 esp-des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-DES-SHA-TRANS esp-des esp-sha-hmac
crypto ipsec ikev1 transform-set ESP-DES-SHA-TRANS mode transport
crypto ipsec ikev1 transform-set ESP-DES-MD5-TRANS esp-des esp-md5-hmac
crypto ipsec ikev1 transform-set ESP-DES-MD5-TRANS mode transport
crypto ipsec ikev2 ipsec-proposal DES
  protocol esp encryption des
  protocol esp integrity sha-1 md5
crypto ipsec ikev2 ipsec-proposal 3DES
  protocol esp encryption 3des
  protocol esp integrity sha-1 md5
crypto ipsec ikev2 ipsec-proposal AES
  protocol esp encryption aes
  protocol esp integrity sha-1 md5
crypto ipsec ikev2 ipsec-proposal AES192
  protocol esp encryption aes-192
  protocol esp integrity sha-1 md5
crypto ipsec ikev2 ipsec-proposal AES256
  protocol esp encryption aes-256
  protocol esp integrity sha-1 md5
crypto ipsec security-association pmtu-aging infinite
crypto map outside_map 1 match address outside_cryptomap
crypto map outside_map 1 set peer 10.2.2.1

```

```
crypto map outside_map 1 set ikev1 transform-set ESP-AES-128-SHA ESP-AES-128-MD5 ESP-
AES-192-SHA ESP-AES-192-MD5 ESP-AES-256-SHA ESP-AES-256-MD5 ESP-3DES-SHA ESP-3DES-MD5
ESP-DES-SHA ESP-DES-MD5
crypto map outside_map 1 set ikev2 ipsec-proposal AES256 AES192 AES 3DES DES
crypto map outside_map interface outside
crypto ca trustpool policy
crypto ikev2 policy 1
  encryption aes-256
  integrity sha
  group 5 2
  prf sha
  lifetime seconds 86400
crypto ikev2 policy 10
  encryption aes-192
  integrity sha
  group 5 2
  prf sha
  lifetime seconds 86400
crypto ikev2 policy 20
  encryption aes
  integrity sha
  group 5 2
  prf sha
  lifetime seconds 86400
crypto ikev2 policy 30
  encryption 3des
  integrity sha
  group 5 2
  prf sha
  lifetime seconds 86400
crypto ikev2 policy 40
  encryption des
  integrity sha
  group 5 2
  prf sha
  lifetime seconds 86400
crypto ikev2 enable outside
crypto ikev1 enable outside
crypto ikev1 policy 10
  authentication crack
  encryption aes-256
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 20
  authentication rsa-sig
  encryption aes-256
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 30
  authentication pre-share
```


encryption aes-256
hash sha
group 2
lifetime 86400
crypto ikev1 policy 40
authentication crack
encryption aes-192
hash sha
group 2
lifetime 86400
crypto ikev1 policy 50
authentication rsa-sig
encryption aes-192
hash sha
group 2
lifetime 86400
crypto ikev1 policy 60
authentication pre-share
encryption aes-192
hash sha
group 2
lifetime 86400
crypto ikev1 policy 70
authentication crack
encryption aes
hash sha
group 2
lifetime 86400
crypto ikev1 policy 80
authentication rsa-sig
encryption aes
hash sha
group 2
lifetime 86400
crypto ikev1 policy 90
authentication pre-share
encryption aes
hash sha
group 2
lifetime 86400
crypto ikev1 policy 100
authentication crack
encryption 3des
hash sha
group 2
lifetime 86400
crypto ikev1 policy 110
authentication rsa-sig
encryption 3des
hash sha
group 2
lifetime 86400

```

crypto ikev1 policy 120
  authentication pre-share
  encryption 3des
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 130
  authentication crack
  encryption des
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 140
  authentication rsa-sig
  encryption des
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 150
  authentication pre-share
  encryption des
  hash sha
  group 2
  lifetime 86400
crypto ikev1 policy 65535
  authentication pre-share
  encryption 3des
  hash sha
  group 2
  lifetime 86400
telnet 192.168.1.0 255.255.255.0 inside
telnet timeout 10
ssh stricthostkeycheck
ssh 192.168.1.0 255.255.255.0 inside
ssh timeout 10
ssh key-exchange group dh-group1-sha1
console timeout 0

threat-detection basic-threat
threat-detection statistics access-list
no threat-detection statistics tcp-intercept
group-policy GroupPolicy_10.2.2.1 internal
group-policy GroupPolicy_10.2.2.1 attributes
  vpn-tunnel-protocol ikev1 ikev2
username admin01 password UsMZmktANM6Z2Y9I encrypted
tunnel-group 10.2.2.1 type ipsec-l2l
tunnel-group 10.2.2.1 general-attributes
  default-group-policy GroupPolicy_10.2.2.1
tunnel-group 10.2.2.1 ipsec-attributes
  ikev1 pre-shared-key *****
  ikev2 remote-authentication pre-shared-key *****
  ikev2 local-authentication pre-shared-key *****

```

```

!
class-map inspection_default
  match default-inspection-traffic
!
policy-map type inspect dns preset_dns_map
  parameters
    message-length maximum client auto
    message-length maximum 512
policy-map global_policy
  class inspection_default
    inspect dns preset_dns_map
    inspect ftp
    inspect h323 h225
    inspect h323 ras
    inspect ip-options
    inspect netbios
    inspect rsh
    inspect rtsp
    inspect skinny
    inspect esmtp
    inspect sqlnet
    inspect sunrpc
    inspect tftp
    inspect sip
    inspect xdmcp
    inspect icmp
!
service-policy global_policy global
prompt hostname context
no call-home reporting anonymous
call-home
  profile CiscoTAC-1
    no active
    destination address http
https://tools.cisco.com/its/service/oddce/services/DDCEService
  destination address email callhome@cisco.com
  destination transport-method http
  subscribe-to-alert-group diagnostic
  subscribe-to-alert-group environment
  subscribe-to-alert-group inventory periodic monthly
  subscribe-to-alert-group configuration periodic monthly
  subscribe-to-alert-group telemetry periodic daily
Cryptochecksum:8d83dd856f98a0f1e574fba6c6bfc478
: end

```

Router R1

Building configuration...

Current configuration : 1713 bytes

```
!  
version 15.4  
service timestamps debug datetime msec  
service timestamps log datetime msec  
no service password-encryption  
!  
hostname R1  
!  
boot-start-marker  
boot-end-marker  
!  
security passwords min-length 10  
enable secret 9 $9$xKxfXtYW7haqI.$gLUXyPBS.RKfwGx.5Nc/yaDEMxvUD9HmhyqDqqwRGWE  
!  
no aaa new-model  
memory-size iomem 15  
!  
ip domain name ccnasecurity.com  
ip cef  
no ipv6 cef  
!  
multilink bundle-name authenticated  
!  
cts logging verbose  
!  
!  
username admin01 secret 9  
$9$5ShIv6PMmhCYyk$0cVgPgvKu80EKQWTWAj2Cwy0kwyl2BHh1PlgxShL/8s  
!  
redundancy  
!  
interface Embedded-Service-Engine0/0  
no ip address  
shutdown  
!  
interface GigabitEthernet0/0  
ip address 209.165.200.225 255.255.255.248  
duplex auto  
speed auto  
!  
interface GigabitEthernet0/1  
no ip address  
shutdown  
duplex auto  
speed auto  
!  
interface Serial0/0/0  
ip address 10.1.1.1 255.255.255.252  
clock rate 2000000
```

```

!
interface Serial0/0/1
  no ip address
  shutdown
!
ip forward-protocol nd
!
no ip http server
no ip http secure-server
!
ip route 0.0.0.0 0.0.0.0 Serial0/0/0
!
control-plane
!
line con 0
  exec-timeout 5 0
  logging synchronous
  login local
line aux 0
line 2
  no activation-character
  no exec
  transport preferred none
  transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
  stopbits 1
line vty 0 4
  exec-timeout 5 0
  logging synchronous
  login local
  transport input ssh
!
scheduler allocate 20000 1000
!
end

```

Router R2

```

R2# show run
Building configuration...

Current configuration : 1678 bytes
!
version 15.4
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname R2
!
boot-start-marker
boot-end-marker
!
security passwords min-length 10
enable secret 9 $9$Nb4BPAMsmT24y.$4bn2kyZCwulndKiaU1453lzF4n3ge95hfoFIKrucvpI
!
no aaa new-model
memory-size iomem 15
!
ip cef
no ipv6 cef
!
multilink bundle-name authenticated
!
cts logging verbose
!
username admin01 secret 9
$9$6PSI5.sujsergN.$LFz4TeeqS/1FtxvK23Le8jxUAY9sjeedVmyF/PA9sPo
!
redundancy
!
interface Embedded-Service-Engine0/0
 no ip address
interface Embedded-Service-Engine0/0
 no ip address
 shutdown
!
interface GigabitEthernet0/0
 no ip address
 shutdown
 duplex auto
 speed auto
!
interface GigabitEthernet0/1
 no ip address
 shutdown
 duplex auto
 speed auto
!
interface Serial0/0/0

```

```

    ip address 10.1.1.2 255.255.255.252
    !
interface Serial0/0/1
    ip address 10.2.2.2 255.255.255.252
    clock rate 2000000
    !
ip forward-protocol nd
    !
no ip http server
no ip http secure-server
    !
ip route 172.16.3.0 255.255.255.0 Serial0/0/1
ip route 209.165.200.224 255.255.255.248 Serial0/0/0
    !
control-plane
    !
line con 0
    exec-timeout 5 0
    logging synchronous
    login local
line aux 0
line 2
    no activation-character
    no exec
    transport preferred none
    transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
    stopbits 1
line vty 0 4
    exec-timeout 5 0
    logging synchronous
    login local
    transport input telnet
    !
scheduler allocate 20000 1000
end

```

Router R3

```

R3# show run
Building configuration...

Current configuration : 2120 bytes
!
version 15.4
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname R3
!
boot-start-marker
boot-end-marker
!
security passwords min-length 10
enable secret 9 $9$bkZXrRtRQF6uqE.$MenFawyYEn642ALi3kGNBttfJxB0Yk3fScLmu0F09Tg
!
no aaa new-model
memory-size iomem 15
!
ip domain name ccnasecurity.com
ip cef
no ipv6 cef
!
multilink bundle-name authenticated
!
cts logging verbose
!
vtp domain TSHOOT
vtp mode transparent
username admin01 secret 9
$9$3gQ5keGlFNmNx.$YmVC/1GkYSErJRHSxRZ13xek9HBYHOASaKmQjYeHx36
!
redundancy
!
crypto isakmp policy 10
  encr 3des
  authentication pre-share
  group 2
crypto isakmp key SECRET-KEY address 209.165.200.226
!
crypto ipsec transform-set ESP-TUNNEL esp-3des esp-sha-hmac
  mode tunnel
!
crypto map S2S-MAP 10 ipsec-isakmp
  set peer 209.165.200.226
  set transform-set ESP-TUNNEL
  match address VPN-ACL
!
interface Embedded-Service-Engine0/0
  no ip address

```



```

shutdown
!
interface GigabitEthernet0/0
  no ip address
  shutdown
  duplex auto
  speed auto
!
interface GigabitEthernet0/1
  ip address 172.16.3.1 255.255.255.0
  duplex auto
  speed auto
!
interface Serial0/0/0
  no ip address
  shutdown
  clock rate 125000
!
interface Serial0/0/1
  ip address 10.2.2.1 255.255.255.252
  crypto map S2S-MAP
!
ip forward-protocol nd
!
no ip http server
no ip http secure-server
!
ip route 0.0.0.0 0.0.0.0 Serial0/0/1
!
ip access-list extended VPN-ACL
  permit ip 172.16.3.0 0.0.0.255 192.168.1.0 0.0.0.255
!
control-plane
!
line con 0
  exec-timeout 5 0
  logging synchronous
  login local
line aux 0
line 2
  no activation-character
  no exec
  transport preferred none
  transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
  stopbits 1
line vty 0 4
  exec-timeout 5 0
  logging synchronous
  login local
  transport input ssh
!
scheduler allocate 20000 1000

```

```
!  
end
```

Switches S1, S2 and S3 – Use default configs, except for host name