

CCNA 2 v7.0 Curriculum: Module 1 – Basic Device Configuration

 itexamanswers.net/ccna-2-v7-0-curriculum-module-1-basic-device-configuration.html

April 8, 2020

Contents

1.0. Introduction

1.0.1. Why should I take this module?

Welcome to Basic Device Configuration!

Welcome to the first module in CCNA Switching, Routing, and Wireless Essentials! You know that switches and routers come with some built-in configuration, so why would you need to learn to further configure switches and routers?

Imagine that you purchased a model train set. After you had set it up, you realized that the track was just a simple oval shape and that the train cars only ran clockwise. You might want the track to be a figure eight shape with an overpass. You might want to have two trains that operate independently of each other and are able to move in different directions. How could you make that happen? You would need to reconfigure the track and the controls. It is the same with network devices. As a network administrator you need detailed control of the devices in your network. This means precisely configuring switches and routers so that your network does what you want it to do. This module has many Syntax Checker and Packet Tracer activities to help you develop these skills. Let's get started!

1.0.2. What will I learn to do in this module?

Module Title: Basic Device Configuration

Module Objective: Configure devices using security best practices.

Topic Title	Topic Objective
Configure a Switch with Initial Settings	Configure initial settings on a Cisco switch.
Configure Switch Ports	Configure switch ports to meet network requirements.
Secure Remote Access	Configure secure management access on a switch.
Basic Router Configuration	Configure basic settings on a router to route between two directly-connected networks, using CLI.

**Verify Directly
Connected Networks**

Verify connectivity between two networks that are directly connected to a router.

1.0.5 Packet Tracer – Logical and Physical Mode Exploration

The network model in this Packet Tracer Physical Mode (PTPM) activity incorporates many of the technologies that you can master in Cisco Networking Academy courses. It represents a simplified version of how a small to medium-sized business network might look.

Most of the devices in the Seward branch office and Warrenton data center are already deployed and configured. You have just been hired to review the devices and networks deployed. It is not important that you understand everything you see and do in this activity. Feel free to explore the network on your own. If you wish to proceed more systematically, follow the steps below. Answer the questions to the best of your ability.

1.0.5 Packet Tracer – Logical and Physical Mode Exploration

1.1. Configure a Switch with Initial Settings

1.1.1. Switch Boot Sequence

Before you can configure a switch, you need to turn it on and allow it to go through the five-step boot sequence. This topic covers the basics of configuring a switch and includes a lab at the end.

After a Cisco switch is powered on, it goes through the following five-step boot sequence:

Step 1: First, the switch loads a power-on self-test (POST) program stored in ROM. POST checks the CPU subsystem. It tests the CPU, DRAM, and the portion of the flash device that makes up the flash file system.

Step 2: Next, the switch loads the boot loader software. The boot loader is a small program stored in ROM that is run immediately after POST successfully completes.

Step 3: The boot loader performs low-level CPU initialization. It initializes the CPU registers, which control where physical memory is mapped, the quantity of memory, and its speed.

Step 4: The boot loader initializes the flash file system on the system board.

Step 5: Finally, the boot loader locates and loads a default IOS operating system software image into memory and gives control of the switch over to the IOS.

1.1.2 – The boot system Command

The switch attempts to automatically boot by using information in the BOOT environment variable. If this variable is not set, the switch attempts to load and execute the first executable file it can find. On Catalyst 2960 Series switches, the image file is normally contained in a directory that has the same name as the image file (excluding the .bin file extension).

The IOS operating system then initializes the interfaces using the Cisco IOS commands found in the startup-config file. The startup-config file is called **config.text** and is located in flash.

In the example, the BOOT environment variable is set using the **boot system** global configuration mode command. Notice that the IOS is located in a distinct folder and the folder path is specified. Use the command **show boot** to see what the current IOS boot file is set to.

```
S1(config)# boot system flash:/c2960-lanbasek9-mz.150-2.SE/c2960-lanbasek9-mz.150-2.SE.bin
```

The table defines each part of the boot system command.


The table defines each part of the **boot system** command.

Command	Definition
boot system	The main command
flash:	The storage device
c2960-lanbasek9-mz.150-2.SE/	The path to the file system
c2960-lanbasek9-mz.150-2.SE.bin	The IOS file name

1.1.3 – Switch LED Indicators

Cisco Catalyst switches have several status LED indicator lights. You can use the switch LEDs to quickly monitor switch activity and performance. Switches of different models and feature sets will have different LEDs and their placement on the front panel of the switch may also vary.

The figure shows the switch LEDs and the Mode button for a Cisco Catalyst 2960 switch.



The Mode button (7 in the figure) is used to toggle through port status, port duplex, port speed, and if supported, the Power over Ethernet (PoE) status of the port LEDs (8 in the figure).

Click each button to learn the purpose of the LED indicators (1-6 in the figure), and the meaning of their colors:

System LED

Shows whether the system is receiving power and is functioning properly. If the LED is off, it means the system is not powered on. If the LED is green, the system is operating normally. If the LED is amber, the system is receiving power but is not functioning properly.

1.1.4. Recovering from a System Crash

The boot loader provides access into the switch if the operating system cannot be used because of missing or damaged system files. The boot loader has a command-line that provides access to the files stored in flash memory.

The boot loader can be accessed through a console connection following these steps:

Step 1. Connect a PC by console cable to the switch console port. Configure terminal emulation software to connect to the switch.

Step 2. Unplug the switch power cord.

Step 3. Reconnect the power cord to the switch and, within 15 seconds, press and hold down the **Mode** button while the System LED is still flashing green.

Step 4. Continue pressing the **Mode** button until the System LED turns briefly amber and then solid green; then release the Mode button.

Step 5. The boot loader **switch:** prompt appears in the terminal emulation software on the PC.

Type the **help** or **?** at the boot loader prompt to view a list of available commands.

By default, the switch attempts to automatically boot up by using information in the **BOOT** environment variable. To view the path of the switch **BOOT** environment variable type the **set** command. Then, initialize the flash file system using the **flash_init** command to view the current files in flash, as shown in the output.

```
switch: set
BOOT=flash:/c2960-lanbasek9-mz.122-55.SE7/c2960-lanbasek9-mz.122-55.SE7.bin
(output omitted)
switch: flash_init
Initializing Flash...
flashfs[0]: 2 files, 1 directories
flashfs[0]: 0 orphaned files, 0 orphaned directories
flashfs[0]: Total bytes: 32514048
flashfs[0]: Bytes used: 11838464
flashfs[0]: Bytes available: 20675584
flashfs[0]: flashfs fsck took 10 seconds.
...done Initializing Flash.
```

After flash has finished initializing you can enter the **dir flash:** command to view the directories and files in flash, as shown in the output.

```
switch: dir flash:
Directory of flash:/
  2  -rw-   11834846                c2960-lanbasek9-mz.150-2.SE8.bin
  3  -rw-    2072                  multiple-fs
```

Enter the **BOOT=flash** command to change the **BOOT** environment variable path the switch uses to load the new IOS in flash. To verify the new **BOOT** environment variable path, issue the **set** command again. Finally, to load the new IOS type the **boot** command without any arguments, as shown in the output.


```
switch: BOOT=flash:c2960-lanbasek9-mz.150-2.SE8.bin
switch: set
BOOT=flash:c2960-lanbasek9-mz.150-2.SE8.bin
(output omitted)
switch: boot
```

The boot loader commands support initializing flash, formatting flash, installing a new IOS, changing the **BOOT** environment variable and recovery of lost or forgotten passwords.

1.1.5. Switch Management Access

To prepare a switch for remote management access, the switch must be configured with an IP address and a subnet mask. Keep in mind that to manage the switch from a remote network, the switch must be configured with a default gateway. This is very similar to configuring the IP address information on host devices. In the figure, the switch virtual interface (SVI) on S1

should be assigned an IP address. The SVI is a virtual interface, not a physical port on the switch. A console cable is used to connect to a PC so that the switch can be initially configured.



1.1.6. Switch SVI Configuration Example

By default, the switch is configured to have its management controlled through VLAN 1. All ports are assigned to VLAN 1 by default. For security purposes, it is considered a best practice to use a VLAN other than VLAN 1 for the management VLAN, such as VLAN 99 in the example.

The steps to configure switch management access:

Step 1: Configure the Management Interface

From VLAN interface configuration mode, an IPv4 address and subnet mask is applied to the management SVI of the switch.

Note: The SVI for VLAN 99 will not appear as “up/up” until VLAN 99 is created and there is a device connected to a switch port associated with VLAN 99.

Note: The switch may need to be configured for IPv6. For example, before you can configure IPv6 addressing on a Cisco Catalyst 2960 running IOS version 15.0, you will need to enter the global configuration command **sdm prefer dual-ipv4-and-ipv6 default** and then

reload the switch.

Task	IOS Commands
Enter global configuration mode.	S1# configure terminal
Enter interface configuration mode for the SVI.	S1(config)# interface vlan 99
Configure the management interface IPv4 address.	S1(config-if)# ip address 172.17.99.11 255.255.255.0
Configure the management interface IPv6 address	S1(config-if)# ipv6 address 2001:db8:acad:99::1/64
Enable the management interface.	S1(config-if)# no shutdown
Return to the privileged EXEC mode.	S1(config-if)# end
Save the running config to the startup config.	S1# copy running-config startup-config

Step 2: Configure the Default Gateway

The switch should be configured with a default gateway if it will be managed remotely from networks that are not directly connected.

Note: Because, it will receive its default gateway information from a router advertisement (RA) message, the switch does not require an IPv6 default gateway.

Task	IOS Commands
Enter global configuration mode.	S1# configure terminal
Configure the default gateway for the switch.	S1(config)# ip default-gateway 172.17.99.1
Return to the privileged EXEC mode.	S1(config-if)# end
Save the running config to the startup config.	S1# copy running-config startup-config

Step 3. Verify Configuration

The `show ip interface brief` and `show ipv6 interface brief` commands are useful for determining the status of both physical and virtual interfaces. The output shown confirms that interface VLAN 99 has been configured with an IPv4 and IPv6 address.

Note: An IP address applied to the SVI is only for remote management access to the switch; this does not allow the switch to route Layer 3 packets.

```

S1# show ip interface brief
Interface      IP-Address      OK? Method      Status      Protocol
Vlan99         172.17.99.11    YES manual      down        down
(output omitted)
S1# show ipv6 interface brief
Vlan99         [down/down]
FE80::C27B:BCFF:FEC4:A9C1
2001:DB8:ACAD:99::1
(output omitted)

```

1.1.7 Lab – Basic Switch Configuration

In this lab, you will complete the following objectives:

- Part 1: Cable the Network and Verify the Default Switch Configuration
- Part 2: Configure Basic Network Device Settings
- Part 3: Verify and Test Network Connectivity
- Part 4: Manage the MAC Address Table

You can practice these skills using the Packet Tracer or lab equipment, if available.

Packet Tracer – Physical Mode (PTPM)

1.1.7 Packet Tracer – Basic Switch Configuration – Physical Mode

Lab Equipment

1.1.7 Lab – Basic Switch Configuration

1.2 – Configure Switch Ports

1.2.1 Duplex Communication


The ports of a switch can be configured independently for different needs. This topic covers how to configure switch ports, how to verify your configurations, common errors, and how to troubleshoot switch configuration issues.

Full-duplex communication increases bandwidth efficiency by allowing both ends of a connection to transmit and receive data simultaneously. This is also known as bidirectional communication and it requires microsegmentation. A microsegmented LAN is created when a switch port has only one device connected and is operating in full-duplex mode. There is no collision domain associated with a switch port operating in full-duplex mode.

Unlike full-duplex communication, half-duplex communication is unidirectional. Half-duplex communication creates performance issues because data can flow in only one direction at a time, often resulting in collisions. Half-duplex connections are typically seen in

older hardware, such as hubs. Full-duplex communication has replaced half-duplex in most hardware.

The figure illustrates full-duplex and half-duplex communication.



Full-Duplex Communication




Half-Duplex Communication

Gigabit Ethernet and 10 Gb NICs require full-duplex connections to operate. In full-duplex mode, the collision detection circuit on the NIC is disabled. Full-duplex offers 100 percent efficiency in both directions (transmitting and receiving). This results in a doubling of the potential use of the stated bandwidth.

1.2.2 Configure Switch Ports at the Physical Layer

Switch ports can be manually configured with specific duplex and speed settings. Use the duplex interface configuration mode command to manually specify the duplex mode for a switch port. Use the speed interface configuration mode command to manually specify the speed. For example, both switches in the topology should always operate in full-duplex at 100 Mbps.



The table shows the commands for S1. The same commands can be applied to S2.

Task	IOS Commands
Enter global configuration mode.	S1# configure terminal
Enter interface configuration mode.	S1(config)# interface FastEthernet 0/1
Configure the interface duplex.	S1(config-if)# duplex full
Configure the interface speed.	S1(config-if)# speed 100
Return to the privileged EXEC mode.	S1(config-if)# end
Save the running config to the startup config.	S1# copy running-config startup-config

The default setting for both duplex and speed for switch ports on Cisco Catalyst 2960 and 3560 switches is auto. The 10/100/1000 ports operate in either half- or full-duplex mode when they are set to 10 or 100 Mbps and operate only in full-duplex mode when it is set to 1000 Mbps (1 Gbps). Autonegotiation is useful when the speed and duplex settings of the device connecting to the port are unknown or may change. When connecting to known devices such as servers, dedicated workstations, or network devices, a best practice is to manually set the speed and duplex settings.

When troubleshooting switch port issues, it is important that the duplex and speed settings should be checked.

Note: Mismatched settings for the duplex mode and speed of switch ports can cause connectivity issues. Autonegotiation failure creates mismatched settings.

All fiber-optic ports, such as 1000BASE-SX ports, operate only at one preset speed and are always full-duplex

1.2.3 Auto-MDIX

Until recently, certain cable types (straight-through or crossover) were required when connecting devices. Switch-to-switch or switch-to-router connections required using different Ethernet cables. Using the automatic medium-dependent interface crossover (auto-MDIX) feature on an interface eliminates this problem. When auto-MDIX is enabled, the interface automatically detects the required cable connection type (straight-through or crossover) and configures the connection appropriately. When connecting to switches without the auto-MDIX feature, straight-through cables must be used to connect to devices such as servers, workstations, or routers. Crossover cables must be used to connect to other switches or repeaters.

With auto-MDIX enabled, either type of cable can be used to connect to other devices, and the interface automatically adjusts to communicate successfully. On newer Cisco switches, the `mdix auto` interface configuration mode command enables the feature. When using auto-MDIX on an interface, the interface speed and duplex must be set to auto so that the feature operates correctly.

The command to enable auto-MDIX is issued in interface configuration mode on the switch as shown:

```
S1(config-if)# mdix auto
```

Note: The auto-MDIX feature is enabled by default on Catalyst 2960 and Catalyst 3560 switches but is not available on the older Catalyst 2950 and Catalyst 3550 switches.

To examine the auto-MDIX setting for a specific interface, use the `show controllers ethernet-controller` command with the `phy` keyword. To limit the output to lines referencing auto-MDIX, use the `include Auto-MDIX` filter. As shown the output indicates On or Off for the feature.

```
S1# show controllers ethernet-controller fa0/1 phy | include MDIX
Auto-MDIX           : On   [AdminState=1   Flags=0x00052248]
```

1.2.4 Switch Verification Commands

The table summarizes some of the more useful switch verification commands.

Task	IOS Commands
Display interface status and configuration.	S1# show interfaces [interface-id]
Display current startup configuration.	S1# show startup-config
Display current running configuration.	S1# show running-config
Display information about flash file system.	S1# show flash

Display system hardware and software status.	S1# show version
Display history of command entered.	S1# show history
Display IP information about an interface.	S1# show ip interface [interface-id] OR S1# show ipv6 interface [interface-id]
Display the MAC address table.	S1# show mac-address-table OR S1# show mac address-table

1.2.5 Verify Switch Port Configuration

The `show running-config` command can be used to verify that the switch has been correctly configured. From the sample abbreviated output on S1, some important information is shown in the figure:

- Fast Ethernet 0/18 interface is configured with the management VLAN 99
- VLAN 99 is configured with an IPv4 address of 172.17.99.11 255.255.255.0
- The default gateway is set to 172.17.99.1

```
S1# show running-config
Building configuration...
Current configuration : 1466 bytes
!
interface FastEthernet0/18
  switchport access vlan 99
  switchport mode access
!
(output omitted)
!
interface Vlan99
  ip address 172.17.99.11 255.255.255.0
  ipv6 address 2001:DB8:ACAD:99::1/64
!
ip default-gateway 172.17.99.1
```

The `show interfaces` command is another commonly used command, which displays status and statistics information on the network interfaces of the switch. The `show interfaces` command is frequently used when configuring and monitoring network devices.

The first line of the output for the `show interfaces fastEthernet 0/18` command indicates that the FastEthernet 0/18 interface is up/up, meaning that it is operational. Further down, the output shows that the duplex is full and the speed is 100 Mbps.

```
S1# show interfaces fastEthernet 0/18
FastEthernet0/18 is up, line protocol is up (connected)
  Hardware is Fast Ethernet, address is 0025.83e6.9092 (bia 0025.83e6.9092)
  MTU 1500 bytes, BW 1000000 Kbit/sec, DLY 100 usec,
    reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
  Keepalive set (10 sec)
  Full-duplex, 100Mb/s, media type is 10/100BaseTX
```

1.2.6 Network Access Layer Issues

The output from the `show interfaces` command is useful for detecting common media issues. One of the most important parts of this output is the display of the line and data link protocol status, as shown in the example.

```
S1# show interfaces fastEthernet 0/18
FastEthernet0/18 is up, line protocol is up (connected)
Hardware is Fast Ethernet, address is 0025.83e6.9092 (bia 0025.83e6.9092)MTU 1500
bytes, BW 1000000 Kbit/sec, DLY 100 usec,
```

The first parameter (FastEthernet0/18 is up) refers to the hardware layer and indicates whether the interface is receiving a carrier detect signal. The second parameter (line protocol is up) refers to the data link layer and indicates whether the data link layer protocol keepalives are being received.

Based on the output of the `show interfaces` command, possible problems can be fixed as follows:

- If the interface is up and the line protocol is down, a problem exists. There could be an encapsulation type mismatch, the interface on the other end could be error-disabled, or there could be a hardware problem.
- If the line protocol and the interface are both down, a cable is not attached, or some other interface problem exists. For example, in a back-to-back connection, the other end of the connection may be administratively down.
- If the interface is administratively down, it has been manually disabled (the shutdown command has been issued) in the active configuration.

The `show interfaces` command output displays counters and statistics for the FastEthernet0/18 interface, as highlighted in the example.

```

S1# show interfaces fastEthernet 0/18
FastEthernet0/18 is up, line protocol is up (connected)
  Hardware is Fast Ethernet, address is 0025.83e6.9092 (bia 0025.83e6.9092)
  MTU 1500 bytes, BW 1000000 Kbit/sec, DLY 100 usec,
    reliability 255/255, txload 1/255, rxload 1/255
  Encapsulation ARPA, loopback not set
  Keepalive set (10 sec)
  Full-duplex, 100Mb/s, media type is 10/100BaseTX
  input flow-control is off, output flow-control is unsupported
  ARP type: ARPA, ARP Timeout 04:00:00
  Last input never, output 00:00:01, output hang never
  Last clearing of "show interface" counters never
  Input queue: 0/75/0/0 (size/max/drops/flushes); Total output drops: 0
  Queueing strategy: fifo
  Output queue: 0/40 (size/max)
  5 minute input rate 0 bits/sec, 0 packets/sec
  5 minute output rate 0 bits/sec, 0 packets/sec
    2295197 packets input, 305539992 bytes, 0 no buffer
    Received 1925500 broadcasts (74 multicasts)
    0 runs, 0 giants, 0 throttles
    3 input errors, 3 CRC, 0 frame, 0 overrun, 0 ignored
    0 watchdog, 74 multicast, 0 pause input
    0 input packets with dribble condition detected
  3594664 packets output, 436549843 bytes, 0 underruns
  8 output errors, 1790 collisions, 10 interface resets
  0 unknown protocol drops
  0 babbles, 235 late collision, 0 deferred

```

Some media errors are not severe enough to cause the circuit to fail but do cause network performance issues. The table explains some of these common errors which can be detected using the `show interfaces` command.

Error Type	Description
Input Errors	Total number of errors. It includes runs, giants, no buffer, CRC, frame, overrun, and ignored counts.
Runs	Packets that are discarded because they are smaller than the minimum packet size for the medium. For instance, any Ethernet packet that is less than 64 bytes is considered a runt.
Giants	Packets that are discarded because they exceed the maximum packet size for the medium. For example, any Ethernet packet that is greater than 1,518 bytes is considered a giant.
CRC	CRC errors are generated when the calculated checksum is not the same as the checksum received.
Output Errors	Sum of all errors that prevented the final transmission of datagrams out of the interface that is being examined.

Collisions	Number of messages retransmitted because of an Ethernet collision.
Late Collisions	A collision that occurs after 512 bits of the frame have been transmitted.

1.2.7 Interface Input and Output Errors

“Input errors” is the sum of all errors in datagrams that were received on the interface being examined. This includes runs, giants, CRC, no buffer, frame, overrun, and ignored counts. The reported input errors from the **show interfaces** command include the following:

- **Runt Frames** – Ethernet frames that are shorter than the 64-byte minimum allowed length are called runs. Malfunctioning NICs are the usual cause of excessive runt frames, but they can also be caused by collisions.
- **Giants** – Ethernet frames that are larger than the maximum allowed size are called giants.
- **CRC errors** – On Ethernet and serial interfaces, CRC errors usually indicate a media or cable error. Common causes include electrical interference, loose or damaged connections, or incorrect cabling. If you see many CRC errors, there is too much noise on the link and you should inspect the cable. You should also search for and eliminate noise sources.


“Output errors” is the sum of all errors that prevented the final transmission of datagrams out the interface that is being examined. The reported output errors from the **show interfaces** command include the following:

- **Collisions** – Collisions in half-duplex operations are normal. However, you should never see collisions on an interface configured for full-duplex communication.
- **Late collisions** – A late collision refers to a collision that occurs after 512 bits of the frame have been transmitted. Excessive cable lengths are the most common cause of late collisions. Another common cause is duplex misconfiguration. For example, you could have one end of a connection configured for full-duplex and the other for half-duplex. You would see late collisions on the interface that is configured for half-duplex. In that case, you must configure the same duplex setting on both ends. A properly designed and configured network should never have late collisions.

1.2.8 Troubleshooting Network Access Layer Issues

Most issues that affect a switched network are encountered during the original implementation. Theoretically, after it is installed, a network continues to operate without problems. However, cabling gets damaged, configurations change, and new devices are connected to the switch that require switch configuration changes. Ongoing maintenance and troubleshooting of the network infrastructure is required.

To troubleshoot scenarios involving no connection, or a bad connection, between a switch and another device, follow the general process shown in the figure.



Use the **show interfaces** command to check the interface status.

If the interface is down:

- Check to make sure that the proper cables are being used. Additionally, check the cable and connectors for damage. If a bad or incorrect cable is suspected, replace the cable.
- If the interface is still down, the problem may be due to a mismatch in speed setting. The speed of an interface is typically autonegotiated; therefore, even if it is manually applied to one interface, the connecting interface should autonegotiate accordingly. If a speed mismatch does occur through misconfiguration, or a hardware or software issue, then that may result in the interface going down. Manually set the same speed on both connection ends if a problem is suspected.

If the interface is up, but issues with connectivity are still present:

- Using the **show interfaces** command, check for indications of excessive noise. Indications may include an increase in the counters for runs, giants, and CRC errors. If there is excessive noise, first find and remove the source of the noise, if possible. Also, verify that the cable does not exceed the maximum cable length and check the type of cable that is used.

- If noise is not an issue, check for excessive collisions. If there are collisions or late collisions, verify the duplex settings on both ends of the connection. Much like the speed setting, the duplex setting is usually autonegotiated. If there does appear to be a duplex mismatch, manually set the duplex to full on both ends of the connection.

1.2.9 Syntax Checker – Configure Switch Ports

Enter configuration mode and set FastEthernet0/1 duplex, speed, and MDIX to auto and save the configuration to NVRAM.

```
S1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
S1(config)#interface FastEthernet0/1
S1(config-if)#duplex auto
S1(config-if)#speed auto
S1(config-if)#mdix auto
End out of interface configuration mode and save the configuration to NVRAM.


S1(config-if)#end
%SYS-5-CONFIG:_I: Configured from console by console
S1#copy running-config startup-config
You have successfully configured duplex, speed, and Auto-MDIX settings on a switch
interface and saved the configuration to NVRAM.
```

1.3 – Secure Remote Access

1.3.1 Telnet Operation

You might not always have direct access to your switch when you need to configure it. You need to be able to access it remotely and it is imperative that your access is secure. This topic discusses how to configure Secure Shell (SSH) for remote access. A Packet Tracer activity gives you the opportunity to try this yourself.


Telnet uses TCP port 23. It is an older protocol that uses unsecure plaintext transmission of both the login authentication (username and password) and the data transmitted between the communicating devices. A threat actor can monitor packets using Wireshark. For example, in the figure the threat actor captured the username admin and password ccna from a Telnet session.



1.3.2 SSH Operation

Secure Shell (SSH) is a secure protocol that uses TCP port 22. It provides a secure (encrypted) management connection to a remote device. SSH should replace Telnet for management connections. SSH provides security for remote connections by providing strong encryption when a device is authenticated (username and password) and also for the transmitted data between the communicating devices.

For example, the figure shows a Wireshark capture of an SSH session. The threat actor can track the session using the IP address of the administrator device. However, unlike Telnet, with SSH the username and password are encrypted.



1.3.3 Verify the Switch Supports SSH

To enable SSH on a Catalyst 2960 switch, the switch must be using a version of the IOS software including cryptographic (encrypted) features and capabilities. Use the **show version** command on the switch to see which IOS the switch is currently running. An IOS filename that includes the combination “k9” supports cryptographic (encrypted) features and capabilities. The example shows the output of the **show version** command.

```
S1# show version
Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE7, RELEASE SOFTWARE (fc1)
```

1.3.4 Configure SSH

Before configuring SSH, the switch must be minimally configured with a unique hostname and the correct network connectivity settings.

The steps to configure SSH:

- [Step 1](#)
- [Step 2](#)
- [Step 3](#)
- [Step 4](#)
- [Step 5](#)
- [Step 6](#)

Step 1: Verify SSH support.

Use the `show ip ssh` command to verify that the switch supports SSH. If the switch is not running an IOS that supports cryptographic features, this command is unrecognized.


```
S1# show ip ssh
```

1.3.5 Verify SSH is Operational

On a PC, an SSH client such as PuTTY, is used to connect to an SSH server. For example, assume the following is configured:

- SSH is enabled on switch S1
- Interface VLAN 99 (SVI) with IPv4 address 172.17.99.11 on switch S1
- PC1 with IPv4 address 172.17.99.21

The figure shows the PuTTY settings for PC1 to initiate an SSH connection to the SVI VLAN IPv4 address of S1.



When connected, the user is prompted for a username and password as shown in the example. Using the configuration from the previous example, the username **admin** and password **ccna** are entered. After entering the correct combination, the user is connected via SSH to the command line interface (CLI) on the Catalyst 2960 switch.

```
Login as: admin
Using keyboard-interactive
Authentication.
Password:
S1> enable
Password:
S1#
```

To display the version and configuration data for SSH on the device that you configured as an SSH server, use the `show ip ssh` command. In the example, SSH version 2 is enabled.

```
S1# show ip ssh
SSH Enabled - version 2.0
Authentication timeout: 120 secs; Authentication retries: 3
To check the SSH connections to the device, use the show ssh command as shown.
S1# show ssh
%No SSHv1 server connections running.
Connection Version Mode Encryption Hmac State Username
0 2.0 IN aes256-cbc hmac-sha1 Session started admin
0 2.0 OUT aes256-cbc hmac-sha1 Session started admin
S1#
```

1.3.6 Packet Tracer – Configure SSH

SSH should replace Telnet for management connections. Telnet uses insecure plaintext communications. SSH provides security for remote connections by providing strong encryption of all transmitted data between devices. In this activity, you will secure a remote switch with password encryption and SSH.

1.3.6 Packet Tracer – Configure SSH

1.4 – Basic Router Configuration

Up to now, this module has only covered switches. If you want devices to be able to send and receive data outside of your network, you will have to configure routers. This topic teaches you basic router configuration and provides two Syntax Checkers and a Packet Tracer activity so you can practice these skills.

Cisco routers and Cisco switches have many similarities. They support a similar modal operating system, similar command structures, and many of the same commands. In addition, both devices have similar initial configuration steps. For example, the following

configuration tasks should always be performed. Name the device to distinguish it from other routers and configure passwords, as shown in the example.

```
Router# configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)# hostname R1
R1(config)# enable secret class
R1(config)# line console 0
R1(config-line)# password cisco
R1(config-line)# login
R1(config-line)# exit
R1(config)# line vty 0 4
R1(config-line)# password cisco
R1(config-line)# login
R1(config-line)# exit
R1(config)# service password-encryption
R1(config)#
```

Configure a banner to provide legal notification of unauthorized access, as shown in the example.

```
R1(config)# banner motd $ Authorized Access Only! $
R1(config)#
```

Save the changes on a router, as shown in the example.

```
R1# copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
```

1.4.2 Syntax Checker – Configure Basic Router Settings

Enter global configuration mode and name the router R2.

```
Router#configure terminal
```

Enter configuration commands, one per line. End with CNTL/Z.

```
Router(config)#hostname R2
```

Configure class as the secret password.

```
R1(config)#enable secret class
```

Configure cisco as the console line password and require users to login. Then exit line configuration mode.

```
R1(config)#line console 0
```

```
R1(config-line)#password cisco
```

```
R1(config-line)#login
```

```
R1(config-line)#exit
```

Configure cisco as the vty password for lines 0 through 4 and require users to login.

```
R1(config)#line vty 0 4
```

```
R1(config-line)#password cisco
```

```
R1(config-line)#login
```

Exit line configuration mode and encrypt all plaintext passwords.

```
R1(config-line)#exit
```

```
R1(config)#service password-encryption
```

Enter the banner Authorized Access Only! and use # as the delimiting character.

```
R1(config)#banner motd #Authorized Access Only!#
```

Exit global configuration mode and save the configuration.

```
R1(config)#exit
```

```
R1#copy running-config startup-config
```

```
Destination filename \[startup-config\]?
```


```
Building configuration...
```

```
\[OK\]
```

You successfully configured R2 with initial settings.

1.4.3 Dual Stack Topology

One distinguishing feature between switches and routers is the type of interfaces supported by each. For example, Layer 2 switches support LANs; therefore, they have multiple FastEthernet or Gigabit Ethernet ports. The dual stack topology in the figure is used to demonstrate the configuration of router IPv4 and IPv6 interfaces.



1.4.4 Configure Router Interfaces

Routers support LANs and WANs and can interconnect different types of networks; therefore, they support many types of interfaces. For example, G2 ISRs have one or two integrated Gigabit Ethernet interfaces and High-Speed WAN Interface Card (HWIC) slots to accommodate other types of network interfaces, including serial, DSL, and cable interfaces.

To be available, an interface must be:

- **Configured with at least one IP address** – Use the `ip address ip-address subnet-mask` and the `ipv6 address ipv6-address/prefix` interface configuration commands.
- **Activated** – By default, LAN and WAN interfaces are not activated (**shutdown**). To enable an interface, it must be activated using the `no shutdown` command. (This is similar to powering on the interface.) The interface must also be connected to another device (a hub, a switch, or another router) for the physical layer to be active.
- **Description** – Optionally, the interface could also be configured with a short description of up to 240 characters. It is good practice to configure a description on each interface. On production networks, the benefits of interface descriptions are quickly realized as they are helpful in troubleshooting and in identifying a third-party connection and contact information.

The following example shows the configuration for the interfaces on R1.


```

R1(config)# interface gigabitethernet 0/0/0
R1(config-if)# ip address 192.168.10.1 255.255.255.0
R1(config-if)# ipv6 address 2001:db8:acad:1::1/64
R1(config-if)# description Link to LAN 1
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)# interface gigabitethernet 0/0/1
R1(config-if)# ip address 192.168.11.1 255.255.255.0
R1(config-if)# ipv6 address 2001:db8:acad:2::1/64
R1(config-if)# description Link to LAN 2
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)# interface serial 0/0/0
R1(config-if)# ip address 209.165.200.225 255.255.255.252
R1(config-if)# ipv6 address 2001:db8:acad:3::225/64
R1(config-if)# description Link to R2
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)#

```

1.4.5 Syntax Checker – Configure Router Interfaces

In this Syntax Checker activity, you will configure R2 with its IPv4 and IPv6 interfaces.

Configure GigabitEthernet 0/0/0.

Use `go/o/o` to enter interface configuration mode.

Configure the IPv4 address 10.1.1.1 and subnet mask 255.255.255.0.

Configure the IPv6 address 2001:db8:acad:4::1/64.

Describe the link as Link to LAN 3.

Activate the interface.

```

Router(config)#interface go/o/o Router(config-if)#ip address 10.1.1.1 255.255.255.0
Router(config-if)#ipv6 address 2001:db8:acad:4::1/64 Router(config-if)#Description Link to
LAN 3 Router(config-if)#no shutdown %LINK-3-UPDOWN: Interface
GigabitEthernet0/o/o, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on
Interface GigabitEthernet0/o/o, changed state to up Configure GigabitEthernet o/o/1.

```

Use `go/o/1` to enter interface configuration mode.

Configure the IPv4 address 10.1.2.1 and subnet mask 255.255.255.0.

Configure the IPv6 address 2001:db8:acad:5::1/64.

Describe the link as Link to LAN 4.

Activate the interface.

```
Router(config-if)#interface g0/0/1 Router(config-if)#ip address 10.1.2.1 255.255.255.0
Router(config-if)#ipv6 address 2001:db8:acad:5::1/64 Router(config-if)#description Link to
LAN 4 Router(config-if)#no shutdown %LINK-3-UPDOWN: Interface GigabitEthernet0/0/1,
changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface
GigabitEthernet0/0/1, changed state to up Configure Serial 0/0/0.
```

Use s0/0/0 to enter interface configuration mode.

Configure the IPv4 address 209.165.200.226 and subnet mask 255.255.255.252.

Configure the IPv6 address 2001:db8:acad:3::226/64.

Describe the link as Link to R1.

Activate the interface.

```
Router(config-if)#interface s0/0/0 Router(config-if)#ip address 209.165.200.226
255.255.255.0 Router(config-if)#ipv6 address 2001:db8:acad:3::226/64 Router(config-
if)#description Link to R1 Router(config-if)#no shutdown %LINK-3-UPDOWN: Interface
Serial0/0/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface
Serial0/0/0, changed state to up You successfully configured the R2 router interfaces.
```

1.4.6 IPv4 Loopback Interfaces

Another common configuration of Cisco IOS routers is enabling a loopback interface.

The loopback interface is a logical interface that is internal to the router. It is not assigned to a physical port and can never be connected to any other device. It is considered a software interface that is automatically placed in an “up” state, as long as the router is functioning.

The loopback interface is useful in testing and managing a Cisco IOS device because it ensures that at least one interface will always be available. For example, it can be used for testing purposes, such as testing internal routing processes, by emulating networks behind the router.

Loopback interfaces are also commonly used in lab environments to create additional interfaces. For example, you can create multiple loopback interfaces on a router to simulate more networks for configuration practice and testing purposes. In this curriculum, we often use a loopback interface to simulate a link to the internet.

Enabling and assigning a loopback address is simple:

```
Router(config)# interface loopback number
Router(config-if)# ip address ip-address subnet-mask
```

Multiple loopback interfaces can be enabled on a router. The IPv4 address for each loopback interface must be unique and unused by any other interface, as shown in the example configuration of loopback interface 0 on R1.

```
R1(config)# interface loopback 0
R1(config-if)# ip address 10.0.0.1 255.255.255.0
R1(config-if)# exit
R1(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
```

1.4.7 Packet Tracer – Configure Router Interfaces

In this Packet Tracer activity, you will configure routers with IPv4 and IPv6 addressing.


1.4.7 Packet Tracer – Configure Router Interfaces

1.5 – Verify Directly Connected Networks

1.5.1 Interface Verification Commands

There is no point in configuring your router unless you verify the configuration and connectivity. This topic covers the commands to use to verify directly connected networks. It includes two Syntax Checkers and a Packet Tracer.

There are several show commands that can be used to verify the operation and configuration of an interface. The topology in the figure is used to demonstrate the verification of router interface settings.



The following commands are especially useful to quickly identify the status of an interface:

- **show ip interface brief** and **show ipv6 interface brief** – These display a summary for all interfaces including the IPv4 or IPv6 address of the interface and current operational status.
- **show running-config interface *interface-id*** – This displays the commands applied to the specified interface.
- **show ip route** and **show ipv6 route** – These display the contents of the IPv4 or IPv6 routing table stored in RAM. In Cisco IOS 15, active interfaces should appear in the routing table with two related entries identified by the code ‘C’ (Connected) or ‘L’ (Local). In previous IOS versions, only a single entry with the code ‘C’ will appear.

1.5.2 Verify Interface Status

The output of the **show ip interface brief** and **show ipv6 interface brief** commands can be used to quickly reveal the status of all interfaces on the router. You can verify that the interfaces are active and operational as indicated by the Status of “up” and Protocol of “up”, as shown in the example. A different output would indicate a problem with either the configuration or the cabling.

```
R1# show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
GigabitEthernet0/0/0    192.168.10.1    YES manual up              up
GigabitEthernet0/0/1    192.168.11.1    YES manual up              up
Serial0/1/0             209.165.200.225 YES manual up              up
Serial0/1/1             unassigned      YES unset  administratively down down
R1# show ipv6 interface brief
GigabitEthernet0/0/0    [up/up]
FE80::7279:B3FF:FE92:3130
2001:DB8:ACAD:1::1
GigabitEthernet0/0/1    [up/up]
FE80::7279:B3FF:FE92:3131
2001:DB8:ACAD:2::1
Serial0/1/0             [up/up]
FE80::7279:B3FF:FE92:3130
2001:DB8:ACAD:3::1
Serial0/1/1             [down/down]    Unassigned
```

1.5.3 Verify IPv6 Link Local and Multicast Addresses

The output of the **show ipv6 interface brief** command displays two configured IPv6 addresses per interface. One address is the IPv6 global unicast address that was manually entered. The other address, which begins with FE80, is the link-local unicast address for the interface. A link-local address is automatically added to an interface whenever a global unicast address is assigned. An IPv6 network interface is required to have a link-local address, but not necessarily a global unicast address.

The `show ipv6 interface gigabitethernet 0/0/0` command displays the interface status and all of the IPv6 addresses belonging to the interface. Along with the link local address and global unicast address, the output includes the multicast addresses assigned to the interface, beginning with prefix FF02, as shown in the example.

```
R1# show ipv6 interface gigabitethernet 0/0/0
GigabitEthernet0/0/0 is up, line protocol is up
  IPv6 is enabled, link-local address is FE80::7279:B3FF:FE92:3130
  No Virtual link-local address(es):
  Global unicast address(es):
    2001:DB8:ACAD:1::1, subnet is 2001:DB8:ACAD:1::/64
  Joined group address(es):
    FF02::1
    FF02::1:FF00:1
    FF02::1:FF92:3130
  MTU is 1500 bytes
  ICMP error messages limited to one every 100 milliseconds
  ICMP redirects are enabled
  ICMP unreachables are sent
  ND DAD is enabled, number of DAD attempts: 1
  ND reachable time is 30000 milliseconds (using 30000)
  ND advertised reachable time is 0 (unspecified)
  ND advertised retransmit interval is 0 (unspecified)
  ND router advertisements are sent every 200 seconds
  ND router advertisements live for 1800 seconds
  ND advertised default router preference is Medium
```

1.5.4 Verify Interface Configuration

The output of the `show running-config interface` command displays the current commands applied to the specified interface as shown.

```
R1 show running-config interface gigabitethernet 0/0/0
Building configuration...
Current configuration : 158 bytes
!
interface GigabitEthernet0/0/0
  description Link to LAN 1
  ip address 192.168.10.1 255.255.255.0
  negotiation auto
  ipv6 address 2001:DB8:ACAD:1::1/64
end
R1#
```

The following two commands are used to gather more detailed interface information:

- **show interfaces**— Displays interface information and packet flow count for all interfaces on the device.
- **show ip interface** and **show ipv6 interface** – Displays the IPv4 and IPv6 related information for all interfaces on a router.

1.5.5 Verify Routes

The output of the **show ip route** and **show ipv6 route** commands reveal the three directly connected network entries and the three local host route interface entries, as shown in the example. The local host route has an administrative distance of 0. It also has a /32 mask for IPv4, and a /128 mask for IPv6. The local host route is for routes on the router that owns the IP address. It is used to allow the router to process packets destined to that IP.

```
R1# show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

Gateway of last resort is not set
    192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.10.0/24 is directly connected, GigabitEthernet0/0/0
L       192.168.10.1/32 is directly connected, GigabitEthernet0/0/0
    192.168.11.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.11.0/24 is directly connected, GigabitEthernet0/0/1
L       192.168.11.1/32 is directly connected, GigabitEthernet0/0/1
    209.165.200.0/24 is variably subnetted, 2 subnets, 2 masks
C       209.165.200.224/30 is directly connected, Serial0/1/0
L       209.165.200.225/32 is directly connected, Serial0/1/0
R1# show ipv6 route
IPv6 Routing Table - default - 7 entries
Codes: C - Connected, L - Local, S - Static, U - Per-user Static route

C  2001:DB8:ACAD:1::/64 [0/0]
    via GigabitEthernet0/0/0, directly connected
L  2001:DB8:ACAD:1::1/128 [0/0]
    via GigabitEthernet0/0/0, receive
C  2001:DB8:ACAD:2::/64 [0/0]
    via GigabitEthernet0/0/1, directly connected
L  2001:DB8:ACAD:2::1/128 [0/0]
    via GigabitEthernet0/0/1, receive
C  2001:DB8:ACAD:3::/64 [0/0]
    via Serial0/1/0, directly connected
L  2001:DB8:ACAD:3::1/128 [0/0]
    via Serial0/1/0, receive
L  FF00::/8 [0/0]
    via Null0, receive
R1#
```

A ‘C’ next to a route within the routing table indicates that this is a directly connected network. When the router interface is configured with a global unicast address and is in the “up/up” state, the IPv6 prefix and prefix length are added to the IPv6 routing table as a connected route.

The IPv6 global unicast address applied to the interface is also installed in the routing table as a local route. The local route has a /128 prefix. Local routes are used by the routing table to efficiently process packets with the interface address of the router as the destination.

The **ping** command for IPv6 is identical to the command used with IPv4 except that an IPv6 address is used. As shown in the example, the **ping** command is used to verify Layer 3 connectivity between R1 and PC1.

```
R1# ping 2001:db8:acad:1::10
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 2001:DB8:ACAD:1::10, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
```

1.5.6 Filter Show Command Output

Commands that generate multiple screens of output are, by default, paused after 24 lines. At the end of the paused output, the **–More–** text displays. Pressing **Enter** displays the next line and pressing the spacebar displays the next set of lines. Use the **terminal length** command to specify the number of lines to be displayed. A value of 0 (zero) prevents the router from pausing between screens of output.

Another very useful feature that improves the user experience in the CLI is the filtering of **show** output. Filtering commands can be used to display specific sections of output. To enable the filtering command, enter a pipe (|) character after the **show** command and then enter a filtering parameter and a filtering expression.

There are four filtering parameters that can be configured after the pipe.

Click each button to learn about the filtering commands.

- [section](#)
- [include](#)
- [exclude](#)
- [begin](#)

section: Shows the entire section that starts with the filtering expression, as shown in the example.

```
R1# show running-config | section line vty
line vty 0 4
 password 7 110A1016141D
 login
 transport input all
```

Note: Output filters can be used in combination with any **show** command.

1.5.7 Syntax Checker – Filter Show Command Output

In this Syntax Checker activity, you will filter output for show commands.

Enter the command to filter the show running-config output for the 'line con' section.

```
R1#show running-config | section line con
line con 0
  password 7 05080F1C2243
  transport input none
```

Enter the command to filter for 'down' interfaces in the brief listing.

```
R1#show ip interface brief | include down
Serial0/1/1    unassigned    NO    unset    down    down
```

Enter the command to exclude 'up' interfaces in the brief listing.

```
R1#show ip interface brief | exclude up
```

Interface	IP-Address	OK?	Method	Status	Protocol
Serial0/1/1	unassigned	NO	unset	down	down

Enter the command to filter the show running-config output to begin at the word 'line'.

```
R1#show running-config | begin line
line con 0
  password 7 05080F1C2243
  transport input none
  stopbits 1
line vty 0 4
  password 7 110A1016141D
  login
  transport input all
```

You have successfully executed the filtered show commands.

1.5.8 Command History Feature

The command history feature is useful because it temporarily stores the list of executed commands to be recalled.

To recall commands in the history buffer, press **Ctrl+P** or the **Up Arrow** key. The command output begins with the most recent command. Repeat the key sequence to recall successively older commands. To return to more recent commands in the history buffer, press **Ctrl+N** or the **Down Arrow** key. Repeat the key sequence to recall successively more recent commands.

By default, command history is enabled and the system captures the last 10 command lines in its history buffer. Use the **show history** privileged EXEC command to display the contents of the buffer.

It is also practical to increase the number of command lines that the history buffer records during the current terminal session only. Use the **terminal history size** user EXEC command to increase or decrease the size of the buffer.

An example of the **terminal history size** and **show history** commands is shown in the figure.

```
R1# terminal history size 200
R1# show history
  show ip int brief
  show interface g0/0/0
  show ip route
  show running-config
  show history
  terminal history size 200
```

1.5.9 Syntax Checker – Command History Features

In this Syntax Check activity, you will use the command history feature.

Enter the command to set the number of lines in command history to 200.

```
R1>terminal history size 200
```

Enter the command to display command history.

```
R1>show history
  show running-config | section line con
  show ip interface brief | include down
  show ip interface brief | exclude up
  show running-config | begin line
  terminal history size 200
  show history
```

```
R1>
```

You have successfully set and displayed command history.

1.5.10 Packet Tracer – Verify Directly Connected Networks

In this Packet Tracer activity, routers R1 and R2 each have two LANs. Your task is to verify the addressing on each device and verify connectivity between the LANs.

1.5.10 Packet Tracer – Verify Directly Connected Networks

1.6 – Module Practice and Quiz

1.6.1 Packet Tracer – Implement a Small Network

In this Packet Tracer activity, routers R1 and R2 each have two LANs. Your task is to verify the addressing on each device and verify connectivity between the LANs.

1.6.1 Packet Tracer – Implement a Small Network

1.6.2 Lab – Configure Basic Router Settings

Skills Practice Opportunity

You have the opportunity to practice the following skills:

- Part 1: Set Up the Topology and Initialize Devices
- Part 2: Configure Devices and Verify Connectivity
- Part 3: Display Router Information

You can practice these skills using the Packet Tracer or lab equipment, if available.

Packet Tracer – Physical Mode (PTPM)

1.6.2 Packet Tracer – Configure Basic Router Settings – Physical Mode

Lab Equipment

1.6.2 Lab – Configure Basic Router Settings (Instructor Version)

1.6.3 What did I learn in this module?

Configure a Switch with Initial Settings

After a Cisco switch is powered on, it goes through a five-step boot sequence. The BOOT environment variable is set using the **boot system** global configuration mode command. The IOS is located in a distinct folder and the folder path is specified. Use the switch LEDs to monitor switch activity and performance: SYST, RPS, STAT, DUPLX, SPEED, and PoE. The boot loader provides access into the switch if the operating system cannot be used because of missing or damaged system files. The boot loader has a command line that provides access to the files stored in flash memory. To prepare a switch for remote management access, the switch must be configured with an IP address and a subnet mask. To manage the switch from a remote network, the switch must be configured with a default gateway. To configure the switch SVI, you must first configure the management interface, then configure the default gateway, and finally, verify your configuration.

Configure Switch Ports

Full-duplex communication increases effective bandwidth by allowing both ends of a connection to transmit and receive data simultaneously. Half-duplex communication is unidirectional. Switch ports can be manually configured with specific duplex and speed settings. Use autonegotiation when the speed and duplex settings of the device connecting to the port are unknown or may change. When auto-MDIX is enabled, the interface automatically detects the required cable connection type (straight-through or crossover) and configures the connection appropriately. There are several **show** commands to use when verifying switch configurations. Use the **show running-config** command and the **show interfaces** command to verify a switch port configuration. The output from the **show**

interfaces command is also useful for detecting common network access layer issues because it displays the line and data link protocol status. The reported input errors from the **show interfaces** command include: runt frames, giants, CRC errors, along with collisions and late collisions. Use **show interfaces** to determine if your network has no connection or a bad connection between a switch and another device.

Secure Remote Access

Telnet (using TCP port 23) is an older protocol that uses unsecure plaintext transmission of both the login authentication (username and password) and the data transmitted between the communicating devices. SSH (using TCP port 22) is a secure protocol that provides an encrypted management connection to a remote device. SSH provides security for remote connections by providing strong encryption when a device is authenticated (username and password) and also for the transmitted data between the communicating devices. Use the **show version** command on the switch to see which IOS the switch is currently running. An IOS filename that includes the combination “k9” supports cryptographic features and capabilities. To configure SSH you must verify that the switch supports it, configure the IP domain, generate RSA key pairs, configure user authentication, configure the VTY lines, and enable SSH version 2. To verify that SSH is operational, use the **show ip ssh** command to display the version and configuration data for SSH on the device.

Basic Router Configuration

The following initial configuration tasks should always be performed: name the device to distinguish it from other routers and configure passwords, configure a banner to provide legal notification of unauthorized access, and save the changes on a router. One distinguishing feature between switches and routers is the type of interfaces supported by each. For example, Layer 2 switches support LANs and, therefore, have multiple FastEthernet or Gigabit Ethernet ports. The dual stack topology is used to demonstrate the configuration of router IPv4 and IPv6 interfaces. Routers support LANs and WANs and can interconnect different types of networks; therefore, they support many types of interfaces. For example, G2 ISRs have one or two integrated Gigabit Ethernet interfaces and High-Speed WAN Interface Card (HWIC) slots to accommodate other types of network interfaces, including serial, DSL, and cable interfaces. The IPv4 loopback interface is a logical interface that is internal to the router. It is not assigned to a physical port and can never be connected to any other device.

Verify Directly Connected Networks

Use the following commands to quickly identify the status of an interface: **show ip interface brief** and **show ipv6 interface brief** to see summary all interfaces (IPv4 and IPv6 addresses and operational status), **show running-config interface interface-id** to see the commands applied to a specified interface, and **show ip route** and **show ipv6**

route to see the contents of the IPv4 or IPv6 routing table stored in RAM. The output of the **show ip interface brief** and **show ipv6 interface brief** commands can be used to quickly reveal the status of all interfaces on the router. The **show ipv6 interface gigabitethernet o/o/o** command displays the interface status and all of the IPv6 addresses belonging to the interface. Along with the link local address and global unicast address, the output includes the multicast addresses assigned to the interface. The output of the **show running-config interface** command displays the current commands applied to a specified interface. The **show interfaces** command displays interface information and packet flow count for all interfaces on the device. Verify interface configuration using the **show ip interface** and **show ipv6 interface** commands, which display the IPv4 and IPv6 related information for all interfaces on a router. Verify routes using the **show ip route** and **show ipv6 route** commands. Filter show command output using the pipe (|) character. Use filter expressions: section, include, exclude, and begin. By default, command history is enabled, and the system captures the last 10 command lines in its history buffer. Use the **show history** privileged EXEC command to display the contents of the buffer.

1.6.4 Module Quiz – Basic Device Configuration

Download Slide Powerpoint (PPT)



[CCNA 2 v7.0 Curriculum: Module 1 – Basic Device Configuration.pptx](#)

1 file(s) 1.86 MB

[Download](#)