


Videoscreen Deployment Instructions

1. Verify Internet Information Services (IIS) is Installed:


1.1. Navigate to IIS

1.1.1. Click “Start” -> “Control Panel” -> “Administrative Tools” (you may need to search for “administrative” to have this option appear. It may take a minute for the window to appear.



1.1.2. Search for “Internet Information Services (IIS) Manager


- 1.1.3. If Found skip to step 2
- 1.2. Install "Internet Information Services (IIS)"
 - 1.2.1. Navigate to "Control Panel" -> "Programs and Features"
 - 1.2.2. Click the side button "Turn Windows features on or off"



1.2.3. Select "Internet Information Services"

1.2.3.1. Select the sub folder "Web Management Tools" and all sub folders beneath "Web Management Tools"


1.2.3.2. Select "World Wide Web Services" and all folders beneath "World Wide Web Services"




1.2.4. Select "Internet Information Services Web Core"

1.2.5. Click "OK" - This will install IIS on your machine.

2. Create a Web Folder for the 2016_SingleScreenHTML files
 - 2.1. Open Windows Explorer
 - 2.2. Navigate to the root web folder (Typically this is "C:\inetpub\wwwroot")
 - 2.3. Create a new folder for 2016_SingleScreenHTML



- 2.4. Copy and Paste the supplied Web Files into the 2016_SingleScreenHTML folder.



3. Create Applications in IIS

3.1. Open Internet Information Services (IIS)

3.1.1. Navigate to “Start” -> “Control Panel” -> “Administrative Tools” -> “Internet Information Services (IIS) Manager”

3.1.2. Double click “Internet Information Services (IIS) Manager” to open IIS.

3.2. Expand the “Sites” folder under the top Treeview in the upper left.

3.3. Right Click on “Default Website”


3.3.1. Select “start” (or verify it’s already started)

3.3.2. Then select “Add Application or Add Web Site...”

3.4. Select “2016_SingleScreenHTML” for the alias of the website.

3.5. Copy and paste the path to the root of the website

(“C:\inetpub\wwwroot\2016_SingleScreenHTML” into the “Physical Path” field.



3.6. Click “OK”

4. Test the website

4.1. The website will now be setup. Open Chrome and navigate to the following url:

4.1.1. http://localhost/2016_SingleScreenHTML/index.html.

4.2. Go through all of the pages / features of the site and make sure they are working as expected.

-