

COMPAQ DeskPro 386, 4Mb RAM, IBM VGA

VGA Color Display
Caps ■ Num ■ Scroll ■ Full Screen

Starting MS-DOS...

Bad or missing C:\LUNA\WIN31\MOUSE.COM
Error in CONFIG.SYS line 5

Bad or missing C:\LUNA\WIN31\CLOCK.SYS
Error in CONFIG.SYS line 8

You cannot access any DoubleSpace compressed drives because
DBLSPACE.BIN is not loaded. (DBLSPACE.BIN is the portion of MS-DOS
that provides access to DoubleSpace compressed drives.)

A: None
Load Save Choose File Paint Added! SPA-OS... Mount Save HD

Ctrl-Alt-Del
Keys

F1	F2	~	!@	2#	3\$	4%	5^	6&	7*	8(9(0)	-_	=+	\	Back	Esc	Num	Scr	Sys
F3	F4	Tab	Q	W	E	R	T	Y	U	I	O	P	[{]}			7	↑8	9	Prt
F5	F6	Ctrl	A	S	D	F	G	H	J	K	L	;	"	↵			←4	5	→6	-
F7	F8	Shift	Z	X	C	V	B	N	M	,<	.>	/?	Shift				1	↓2	3	+
F9	F10	Alt	Space												Caps		Ins 0	Del.		

[\[Save Machine\]](#) [\[Debugger\]](#)
PCx86 v2.00 © 2012-2021 Jeff Parsons

```

<machine id="deskpro386" type="pcx86" border="1" pos="center" background="default" debugger="available">
  <name pos="center">COMPAQ DeskPro 386, 4Mb RAM, IBM VGA</name>
  <computer id="deskpro386-vga-4096k" name="COMPAQ DeskPro 386" buswidth="32"></computer>
  <cpu id="cpu386" model="80386"></cpu>
  <ram id="ramLow" addr="0x00000" test="false" size="0xa0000" comment="ROM BIOS memory test has been disabled"></ram>
  <ram id="ramCPQ" addr="0xfa0000" size="0x60000" comment="COMPAQ memory at 0xFA0000"></ram>
  <ram id="ramExt" addr="0x100000" size="0x300000" comment="Extended memory at 0x100000"></ram>
  <rom id="romBIOS" addr="0xf8000" size="0x8000" alias="[0xf0000,0xffff0000,0xffff8000]" file="/machines/pcx86/compaq/deskpro386/romBIOS" autoLock="true" pos="center" paddi
  <video id="videoVGA" model="vga" screenWidth="1280" screenHeight="960" touchScreen="mouse" autoLock="true" pos="center" paddi
  <menu>
    <title>VGA Color Display</title>
    <control type="container" pos="right">
      <control type="led" label="Caps" binding="caps-lock" padLeft="8px"></control>
      <control type="led" label="Num" binding="num-lock" padLeft="8px"></control>
      <control type="led" label="Scroll" binding="scroll-lock" padLeft="8px"></control>
      <control type="button" binding="fullScreen" padLeft="8px;line-height:1em">Full Screen</control>
    </control>
  </menu>
  <rom id="romVGA" addr="0xc0000" size="0x6000" file="/machines/pcx86/ibm/video/vga/1986-10-27/IBM-VGA.json" notify="videoVGA[0:
  </video>
  <fdc id="fdcNEC" autoMount="{A:{name:"PC DOS 2.00 (Disk 1)"}, B:{name:"PC DOS 2.00 (Disk 2)"}}" diskettes="/configs/pcx86/disk
  <control type="list" binding="listDrives"></control>
  <control type="list" binding="listDisks">
  </control>
  <control type="button" binding="loadDisk">Load</control>
  <control type="button" binding="saveDisk" padRight="8px">Save</control>
  <control type="description" binding="descDisk" padRight="8px"></control>
  <control type="file" binding="mountDisk"></control>
  </fdc>
  <hdc id="hdcAT" type="ATAPI1" drives="{name:"47Mb Hard Disk",type:5}">
  <control type="button" binding="saveHD0" padLeft="8px" padBottom="8px" padRight="8px">Save HD</control>
  <control type="list" binding="listDisks" style="display:none">
    <disk path="/disks-cds/cds005/microsoft/reference/Bookshelf-Windows-1991/cdrom">Bookshelf for Windows (1991)</disk>
    <disk path="/disks-cds/cds001/microsoft/games/Pandoras-Box/cdrom">Pandora's Box (1999)</disk>
    <disk path="/disks-cds/cds002/microsoft/tools/MSPL10/cdrom">Programmer's Library 1.0 (1988)</disk>
    <disk path="/disks-cds/cds002/others/misc/DKMMTWTW/cdrom">The Way Things Work (1994)</disk>
  </control>
  </hdc>
  <keyboard id="keyboard" model="us84" style="pointer-events:none;">
  <control type="container" style="pointer-events:auto;">
    <control type="button" binding="ctrl-alt-del" padLeft="8px" padBottom="8px">Ctrl-Alt-Del</control>
    <control type="button" binding="keyboard" padLeft="8px" padBottom="8px">Keys</control>
  </control>
  <!-- soft-keyboard -->
  <!-- soft-keyboard-mobile -->
  </keyboard>
  <chipset id="chipset" model="deskpro386" floppies="[1200,1200]" monitor="vga"></chipset>
  <serial id="com1" adapter="1"></serial>
  <serial id="com2" adapter="2"></serial>
  <mouse serial="com1"></mouse>
</machine>

```