

# Heritage Aerial Applicators

2016


Work Order  
Authorized By Brenda

5/12/2016

## BWtest3

5/12/2016

<b>Application Date &amp; Time</b>		<b>Applicators</b>	
Start Time:			
Finish Time:			
<b>Environmental</b>			
Sky Condition:		Wind Speed:	Wind Direction:
Soil Condition:		Temperature:	Humidity:
<b>Tank Information</b>			
Size:	Carrier/Area:	Total Carrier:	Tank Count:
<b>Notes</b>			



## Products

Name / Active	Reg # / Pest	REI / PHI	App. Method	App Area	Rate / ac.	Total
<b>Affinity BroadSpec Herbicide</b> <b>(with TotalSol Soluble Granules)</b> <i>Tribenuron-methyl, Thifensulfuron-methyl</i>	352-661	12 <i>REI(h)</i>		207.91 ac.	8.00 fl oz	1,735.10 dry oz.
<b>Cornbelt Defoamer</b> <i>Silicone fluid emulsion</i>		12 <i>PHI(d)</i>				
		<i>REI(h)</i> *		207.91 ac.	0.03 fl oz	0.39 pt
		<i>PHI(d)</i> *				
<b>Bravo Zn</b> <i>Chlorothalonil</i>	50534-204-100	<i>REI(h)</i> *		207.91 ac.	1.50 pt	38.98 gal
		<i>PHI(d)</i> *				
<b>Vydate C-LV Insecticide-Nematicide</b> <i>Oxamyl</i>	352-532	<i>REI(h)</i> *		207.91 ac.	1.50 gal	311.87 gal
		<i>PHI(d)</i> *				

## Fields

**207.91 ac.**

# Heritage Aerial Applicators

2016

Work Order  
Authorized By Brenda

**BWtest3**

5/12/2016

5/12/2016

Farm	Field	Crop Zone	Crop	Center Lat/Long	WO. Area	Actual Area
Chad Main	CM1	Wheat	Wheat	43.51482, -84.96148	75.44	
Chad Main	CM2	Wheat	Wheat	43.51064, -84.96507	6.07	
Chad Main	CM3	Wheat	Wheat	43.51611, -84.95414	18.15	
Chad Main	CM4	Wheat	Wheat	43.52182, -84.95172	108.26	

**Signature** \_\_\_\_\_

**Date** \_\_\_\_\_

**Worker Protection****Affinity BroadSpec Herbicide (with TotalSol Soluble Granules)**

<b>Signal Word</b>	CAUTION	<b>RUP</b>	False
<b>PPE</b>	PERSONAL PROTECTIVE EQUIPMENT (PPE) Some materials that are chemical resistant to this product are listed below. If you want more options follow the instructions for Category A on an EPA chemical resistance category selection chart. Applicators and other handlers must wear: Long-sleeved shirt and long pants. Chemical Resistant Gloves Category A (such as butyl rubber, natural rubber, neoprene rubber or nitrile rubber) >= 14 mls. Shoes plus socks. Follow manufacturer's instructions for cleaning/maintaining PPE. If no such instructions for washables exist, use detergent and hot water. Keep and wash PPE separately from other laundry.		
<b>ReEntry</b>	PPE required for early entry to treated areas that is permitted under the Worker Protection Standard and that involves contact with anything that has been treated, such as plants, soil, or water, is: Coveralls. Chemical-resistant gloves made of any waterproof material. Shoes plus socks.		

**Cornbelt Defoamer**

<b>Signal Word</b>		<b>RUP</b>	False
<b>PPE</b>	Eye Protection: Proper eye protection should be worn in any type of industrial operation.		
<b>ReEntry</b>			

**Bravo Zn**

<b>Signal Word</b>	WARNING	<b>RUP</b>	False
<b>PPE</b>	Personal Protective Equipment (PPE) Some materials that are chemical-resistant to this product are made of any waterproof material. If you want more options, follow the instructions for Category A on an EPA chemical resistance category selection chart. Mixers, Loaders, Applicators and all other handlers must wear: - long-sleeved shirt and long pants - chemical resistant gloves made of any waterproof material - shoes plus socks Discard clothing and other absorbent materials that have been drenched or heavily contaminated with this product's concentrate. Do not reuse them. Follow manufacturer's instructions for cleaning/ maintaining PPE. If no such instructions for washables, use detergent and hot water. Keep and wash PPE separately from other laundry.		
<b>ReEntry</b>	PPE required for early entry to treated areas that is permitted under the Worker Protection Standard and that involves contact with anything that has been treated, such as plants, soil, or water, is: - coveralls - chemical resistant gloves made of any waterproof material - shoes plus socks - protective eyewear Special Eye Irritation Provisions: This product is a severe eye irritant. Although the restricted-entry interval expires after 12 hours, for the next 6.5 days entry is permitted only when the following safety measures are provided: (1) At least one container designed specifically for flushing eyes must be available in operating condition at the WPS-required decontamination site intended for workers entering the treated area. (2) Workers must be informed, in a manner they can understand: - that residues in the treated area may be highly irritating to their eyes - that they should take precautions, such as refraining from rubbing their eyes to keep the residues out of their eyes - that if they do get residues in their eyes, they should immediately flush their eyes using the eyeflush container that is located at the decontamination site, or using other readily available clean water - how to operate the eyeflush container		

**Vydate C-LV Insecticide-Nematicide**

<b>Signal Word</b>	DANGER	<b>RUP</b>	True
<b>PPE</b>	PERSONAL PROTECTIVE EQUIPMENT (PPE) Some materials that are chemical-resistant to this product are listed below. If you want more options, follow the instructions for category B on an EPA chemical-resistance category selection chart. Mixers, loaders, and applicators and other handlers must wear: Coveralls over long-sleeved shirt and long pants. Chemical-resistant gloves, such as barrier laminate or butyl rubber. Chemical-resistant footwear plus socks. Protective eyewear. Chemical-resistant headgear for overhead exposure. Chemical-resistant apron when cleaning equipment, mixing, or loading. A respirator with an organic vapor-removing cartridge with a prefilter approved for pesticides (MSHA/NIOSH approval number prefix TC-23C), or a canister approved for pesticides (MSHA/NIOSH approval number prefix TC-14G) or a NIOSH approved respirator with an organic vapor (OV) cartridge or canister with any R, P or HE prefilter. Discard clothing or other absorbent materials that have been drenched or heavily contaminated with this product's concentrate. Do not reuse them. Follow manufacturer's instructions for cleaning/maintaining PPE. If no such instructions for washables, use detergent and hot water. Keep and wash PPE separately from other laundry.		
<b>ReEntry</b>	PPE required for early entry to treated areas that is permitted under the Worker Protection Standard and that involves contact with anything that has been treated, such as plants, soil, or water, is: Coveralls. Chemical-resistant gloves, made of any waterproof material. Socks and shoes.		