

Shop By Brand Extension for Magento 2.0

USER GUIDE

Magecan Inc.

Table of Contents

1.Admin Configuration.....	3
1.1 System Configuration	4
1.2 Add the Widget to the Page.....	5

1.Admin Configuration

1. Go to Admin Panel → Stores → Attributes → Product.
2. Click on the Add New Attribute button.

Attribute Settings

- Default Label: `Brand`
 - Catalog Input Type for Store Owner: `Visual Swatch`

Manage Swatch Options

1. Scroll down to the Manage Swatch (values of your attribute) section.
2. Click on Add Swatch for each brand you want to add.
3. For each option:
 - Label: Enter the brand name (e.g., Nike, Adidas, Puma).
 - Swatch Type: Choose `Image`.
 - Upload Image: Add the brand logo or representative image.
4. Click Save.

Assign the Attribute to the Appropriate Attribute Set

1. Go to Admin Panel → Stores → Attributes → Attribute Set.
2. Select the Attribute Set where you want to add the `Brand` attribute (e.g., `Default`).
3. Drag the `Brand` attribute from the Unassigned Attributes list to the appropriate group (e.g., `General`, `Product Details`, or create a new group called `Brand`).
4. Click Save.

Assign Brands to Products

1. Go to Admin Panel → Catalog → Products.
2. Edit or create a product.
3. Find the `Brand` attribute in the product settings.

4. Select the appropriate brand swatch.
5. Click Save.

1.1 System Configuration

Go to: Admin → Stores → Configuration → Sales → Shop By BrandAdd the “Brand` Product Attribute Add the `Brand` Product Attribute Prod

Infinite Loop

- Enables or disables infinite looping of the brand carousel.
- Options:
 - `Yes`: The carousel will loop infinitely.
 - `No`: The carousel will stop after the last brand.

Autoplay

- Enables or disables autoplay for the brand carousel.
- Options:
 - `Yes`: The carousel will play automatically.
 - `No`: Manual navigation is required.

Autoplay Speed

- Sets the speed for autoplay (in milliseconds).
- Must be a number greater than zero
- Example:
 - `1000`: Carousel advances every 1 second.
 - `2000`: Carousel advances every 2 seconds.

Show Arrows

- Displays or hides navigation arrows on the carousel.
- Options:
 - `Yes`: Arrows are visible.
 - `No`: Arrows are hidden.

Show Dots

- Displays or hides navigation dots on the carousel.
- Options:
 - `Yes`: Dots are visible.
 - `No`: Dots are hidden.

1.2 Add the Widget to the Page

In the Page Builder toolbar, click on the + icon to add a new content block.

Select Widget from the available content options.

In the Widget Settings panel:

Select Widget Type: Choose the Brand Carousel widget from the dropdown list.

You may have additional settings to configure, such as layout or custom CSS classes, depending on the widget's functionality.

Click Insert Widget to add it to the page.