

```
(kali@kali)~$
```

```
$ msfconsole
```

```
msf6 > use auxiliary/scanner/telnet/telnet_version
msf6 auxiliary(scanner/telnet/telnet_version) > show options
```

Module options (auxiliary/scanner/telnet/telnet\_version):

Name	Current Setting	Required	Description
PASSWORD		no	The password for the specified username
RHOSTS		yes	The target host(s), see <a href="https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html">https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html</a>
RPORT	23	yes	The target port (TCP)
THREADS	1	yes	The number of concurrent threads (max one per host)
TIMEOUT	30	yes	Timeout for the Telnet probe
USERNAME		no	The username to authenticate as

View the full module info with the `info`, or `info -d` command.

```
msf6 auxiliary(scanner/telnet/telnet_version) > ser RHOSTS 192.168.50.101
[-] Unknown command: ser
msf6 auxiliary(scanner/telnet/telnet_version) > set RHOSTS 192.168.50.101
RHOSTS => 192.168.50.101
```



```
[*] exec: telnet 192.168.50.101
```

```
Trying 192.168.50.101 ...
Connected to 192.168.50.101.
Escape character is '^['.
```

Warning: Never expose this VM to an untrusted network!

Contact: [msfdev\[at\]metasploit.com](mailto:msfdev[at]metasploit.com)

Login with msfadmin/msfadmin to get started

```
metasploitable login: msfadmin
```

Password:

```
Last login: Wed Jan 17 07:02:58 EST 2024 on tty1
```

```
Linux metasploitable 2.6.24-16-server #1 SMP Thu Apr 10 13:58:00 UTC 2008 i686
```

The programs included with the Ubuntu system are free software; the exact distribution terms for each program are described in the individual files in `/usr/share/doc/*/copyright`.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by applicable law.

To access official Ubuntu documentation, please visit:

<http://help.ubuntu.com/>

No mail.

msfadmin@metasploitable:~\$