


CWSS System



Requirements / Installing

Tested System:

- Microsoft Windows 7 Profesional Notebook Computers -w- Webcam (x2)
- HooToo TripMate Nano Travel Router
- MSR90 Magnetic Strip Reader (x2)

Install:

- Run "CWSS Setup.exe", run as administrator rights will be requested. (click yes)
- Select install for a remote client machine if installing on a computer intended to only be used as a remote check in machine, otherwise leave unchecked for the host computer.
- Select install magnetic strip reader config if using the MSR90 strip readers.
- Follow the instructions below for setting up the card reader if applicable.

Magnetic Strip Reader Model MSR90 Setup:

(http://www.card-device.com/products_info.asp?Nid=37)

Copy the following settings for best compatibility with the CWSS System:

The screenshot shows the 'General' tab of the MSR90 configuration tool. The settings are as follows:

- CARD_TYPE_ENBLE**
 - ☒ ISO Format
 - ☐ AAMVA Format
 - ☐ IBM Format
 - ☐ JIS-II Format
 - ☐ CADMV Format
 - ☐ Encry
- KEYPRESS_MODE**
 - ☒ KEY_MAP (For USA Keyboard)
 - ☐ ALT_ASC (For Not_USA_Keyboard)
 - Key Delay Time (ms):
- Send Data when TrackError:**
 -
- Add ENTER:**
 -
- Beep:** ☒ Enable

On the right side of the 'General' tab:

- STRING_DEFINE**
 - PRE_CARD_STRING:
 - POST_CARD_STRING:
 - EMPTY_MSG_STRING:
 - ERROR_MSG_STRING:
- TRACK_ID_ENBLE**
 - TK1:
 - TK2:
 - TK3:

The screenshot shows the 'ISO' tab of the MSR90 configuration tool. The settings are as follows:

- TRACK1**
 - ☐ TRACK1
 - ☐ Start Sentinel
 - ☐ End Sentinel
 - ☐ LRC Data
 - PREFIX:
 - SUFFIX:
- TRACK2**
 - ☒ TRACK2
 - ☐ Start Sentinel
 - ☐ End Sentinel
 - ☐ LRC Data
 - PREFIX:
 - SUFFIX:
- TRACK3**
 - ☐ TRACK3
 - ☐ Start Sentinel
 - ☐ End Sentinel
 - ☐ LRC Data
 - PREFIX: +
 - SUFFIX: ?

Click on “Download” to configure the device to these settings. Close the config tool. (Done)

Notes:

Other Requirements:

- Adobe Acrobat Extension Required to be installed for Internet Explorer in order to view waiver documents.
- Webcam required to capture real signatures on a real .pdf waiver document. Can only be used on the host (server) computer. Client / Remote machines cannot capture signatures.
- UDP communications must be enabled through the firewall on port 2222 to allow communication between the host and remote machines.

Default Administrator Account:

- user login id: 123456
- password: abc123

Program Keyboard Shortcuts:

- Ctrl + L: Login / Logout
- Ctrl + X: Exit Program
- Ctrl + N: New User
- Ctrl + P: Postit Note
- Ctrl + F1: Enter Client Mode
- Ctrl + W: View Climbers
- Ctrl + C: Calendar
- Ctrl + A: Account Viewer
- Ctrl + R: Reports
- Ctrl + U: Users
- Ctrl + D: Log Viewer
- Ctrl + S: Settings