

## Blixt Wallet Key Features

- \* Full non-custodial LND node
- \* Bitcoin Neutrino Node
- \* Bitcoin onchain wallet (taproot support)
- \* Lightning wallet
- \* LN channels management
- \* LN channels backup (local and remote)
- \* Dunder LSP channels (receive sats right away)
- \* Auto-opening channels
- \* Inbound channel LSP option
- \* LNURL support, LN-auth support
- \* LN Address send
- \* LN Address receive soon with LN Box
- \* WebLN support
- \* Keysend and AMP support
- \* Contacts address book
- \* Integrated Tor support
- \* Advanced debug logs
- \* Advanced security options
- \* Signing messages
- \* Multi-Language support



## Blixt Wallet Resources

**Website:**

[blixtwallet.com](https://blixtwallet.com)

**Github:**

[github.com/hsjoberg/blixt-wallet](https://github.com/hsjoberg/blixt-wallet)

**Telegram:**

[t.me/blixtwallet](https://t.me/blixtwallet)

**Blixt Guides:**


[blixtwallet.github.io/guides](https://blixtwallet.github.io/guides)

**Blixt FAQ page:**

[blixtwallet.github.io/faq](https://blixtwallet.github.io/faq)

**Crowdfunding:**

[geyser.fund/project/blixt](https://geyser.fund/project/blixt)




## Blixt Wallet

Bitcoin Lightning Wallet  
LND Node with Neutrino  
non-custodial and open-source  
for Android and iOS  
with a focus on usability and user experience

## First Steps


1. Install Blixt app (Android or iOS)
2. Create new wallet / save the seed words
3. Wait for the node to sync the blocks



## “The Magic Drawer”

When you open the top left drawer you will find:

- A. Status icon for LN channels (red / green)
- B. On-chain wallet section
- C. Lightning Channels section
- D. Keysend / advanced features




## Open LN Channels

### - autopilot option -

*Autopilot = opening channels automatically once you have an onchain deposit.*

1. Go to Settings and be sure the “autopilot” option is activated.
2. Deposit sats to the BTC address displayed on the main screen. Recommended amount 500k - 1M sats for better ch. management
3. Wait for the channel to be confirmed and open. Is recommended to keep the app open until is done.



## Open LN Channels

### - Dunder option -

*Dunder channel = on demand channel openings*

1. Go to Settings and activate “Enable Dunder LSP”
2. Go to main screen and click on “Receive”
3. Put the amount of sats you want to have on your side of the channel.
  - The Blixt Dunder server will open a channel of max 400k sats capacity and will push the sats you deposit on your side. So if you use Blixt Dunder, send less than 400k sats. This is a quick option to receive sats right away in the limit of 400k sats.
  - Other Dunder servers could vary this max amount of channel capacity.
  - If you have your own desktop LN node you can also run a Dunder server and provide Dunder LSP for other users. You can set whatever limit for the channels.



## Backup LN Channels

*SCB = static channel backup*

You can save a backup of your channels in 2 ways:

- save a copy on local device
  - save an encrypted copy on Google drive
- Backups are necessary only after you open or close a channel. *No need to do it after every transaction!*

1. Go to Settings and in the “Wallet” section you will find the option “Export channel backup”.
2. Once you click it, will ask you where to save the SCB file, usually in “downloads” folder. Is a small file.
3. Send out that file (email, messenger) to yourself or if you are connected to a LAN shared location, just copy / paste that file into your safe location for storage.
  - If you choose to use the option with Google drive, it will ask you for a Google account to set. The file will be saved in a secured location in your GDrive account, from where you can restore it later when is needed.

**Save also your 24 mnemonic seed words!**

To restore a Blixt wallet completely you must provide the both: seed words + SCB file.