

OlympicCoin Window Masternode guide by ppcoin in <https://discord.gg/cB8udxs>


<http://bit.ly/2ENwBqh> (Go here get a window VPS if you dont have one)

<http://bit.ly/2FmX7DK> >> Download OlympicCoin Windows Wallet

step 1:

Quote

Open Windows wallet and go to debug---> console.



step 2:

Write the command:

Quote

`masternode genkey`

step 3:

copy the generated code to a text file


Quote

`getaccountaddress mn`

copy the generated address to a text file

step 4:

Send 1500 OlympicCoin to "address mn"




step 5:

Write the command:

Quote

masternode outputs



copy the generated code to a text file

step 6:

go to **Olympic.conf** in

Windows

[Quote](#)

C:\Users\{user}\AppData\Roaming\Olympic\Olympic.conf

Paste this (dont forget to set rpcuser and password)

[Quote](#)

rpcuser=<anything>

rpcpassword=<anything>

maxconnections=256

masternode=1

masternodeprivkey=XXXXXXXXXXXXXXXXXXXXX (paste the key you generated with the command **masternode genkey**)

masternodeaddr=xxx.xxx.xxx.xxx:26667

step 6:

Go to Masternodes and click "Creat".

The screenshot shows the Olympic wallet desktop application. On the left is a sidebar with icons for Dashboard, Receive, Send, Transactions, Addresses, Masternodes (highlighted in yellow), Messages, and Block Explorer. The main window displays a 'Create...' button at the top. Below it is a table with columns: Alias, IP/Onion, Reward %, and Reward Address. An 'Add/Edit Olympic Node' dialog box is open, showing the following fields:

- Alias*:
- Address*:
- PrivKey*:
- TxHash*:
- Output Index*:
- Reward Address:
- Reward %:

At the bottom of the dialog are 'OK' and 'Cancel' buttons. Below the table in the main window are 'Edit', 'Remove', and 'Update' buttons.

Step 7:
Click Update, you will see Masternode is come out:

	Alias	IP/Onion	Reward %	Reward Address	
1	mymn	[REDACTED]:26667	100	[REDACTED]	Not in the masternode list.


Step 8:
MUST Waiting the transaction Completely down.(the 1500 mn transaction)

Date	Type
2/22/2018 10:26	Payment to yourself
2/22/2018 10:12	Received with
2/22/2018 09:28	Received with
2/22/2018 09:24	Sent to
2/22/2018 09:20	Received with

Step 9: Unlock your Wallet and use command:

Quote

masternode start




Step 10:

use following command to check masternode:


Quote

masternode status



Step 11:
Go to

Masternode and then Click "update"



PS1. Make sure open port: 26667 in windows.

Something change like this video:
<https://www.youtube.com/watch?v=oxY81uM3yzs>

PS2. If you are using VPS window to directly run your mn, make sure backup and save the wallet.dat to your local PC. If you using cold wallet, ignore this.

If you like this, send me some btc: **15QpUkDbcxMyi8oc8Fwf5WDi7AGzutiFWT**

Thanks !!!