

THE APOCALYPTICS TOKEN VESTING

➤ Admin Console (Login with Contract Account Only)

To Create new token pool, investor vesting and cancel investor's vesting


Functions :

- Create Pool (To create new investor token pool if none exists)

Arguments to be put in as it is in this format –

1. Pool Name – **investor**
2. Pool Quantity (Token to be put in this pool) - For E.g., 150 million to be put in as **150000000**
3. TGE Percentage (Percentage Rate of TGE for claim) – For E.g., if TGE is 4% then it is to be put in as **4**
4. Release Period (Total Vesting Length for investors) – For E.g., if vesting period is 18 months, then it is to be put in as **18 Months**
5. Cliff Period (Total Cliff Duration for investors) – For E.g., if cliff period to be set is 2 months, then it is to be put in as **2 Months**
6. Pause Claim (True / False Boolean) – To pause claims for all investors, already set to default false toggle to enable claims when creating pool

Press Confirm and sign transaction to create new investor pool *if not exists before, after transaction complete the page will show token pool, current token amount in the pool and number of users vested.




- Create New Vesting (To create new vesting for investor)

Arguments to be put in as it is in this format –


1. Wallet Address (wallet address of investor)
2. Quantity (Token to be locked in) - For E.g., Token Quantity without any decimal or token name, just amount like this **100000**
3. Start Date – Select date from when the vesting would start, usually select any date except current today's date.
4. Release Frequency (period when investor can claim) – to be put in as it is out of these values with count : **Daily** , 1-30 **Days** , 1 -12 **Months**

Press Confirm and sign transaction to create new vesting of the investor and count of number of users vested would update.

- Cancel Vesting (To cancel existing vesting of an investor)
Arguments – Enter Investor Account and press confirm.
- Investor Console (Login with any account other than contract account)
To see vesting details and claim their share of tokens on regular basis as set by admin.



After the cliff period ends, investor can see a timer on regular basis depicting time to claim as per release delay set by admin, until then the console would show the cliff period ending date. Also, TGE percentage share of tokens are available for investors to claim anytime as soon as vesting starts and on each release delay investor can see their updated unlocked balance available for claim.



Investors have to simply press claim rewards and sign transaction, on each successful claim the token claimed percentage is depicted and all other info's are updated as well.