

2021 普通电脑挖矿入坑超详教程

<https://www.bilibili.com/read/cv10962997>

最近虚拟货币火热，许多人想尝试挖矿来获得虚拟货币，但很多人没有矿机矿卡，用一台普通的家用电脑怎么挖矿呢？用 CPU 挖比特币是不可能的，但是我们有这样一个虚拟货币——门罗币（Monero, XMR）。它的 RandomX 算法对 cpu 优化极高，抵制矿机，使 CPU 挖矿成为可能。（文章撰写时 xmr 价格 2316 元/个）那么，如何开始呢？


一：下载挖矿软件（xmrGuiMiner）

百度网盘 <https://pan.baidu.com/s/1EdN0ZVUCAr7TK2mGSytMw> 提取码: w33n

GitHub: <https://github.com/EntropyRiser/xmrGuiMiner/releases/download/v1.0.2/xmrGuiMiner.zip>

（GitHub 上最可以检查新版本 <https://github.com/EntropyRiser/xmrGuiMiner/releases>）


下载后解压，打开 xmrGuiMiner.exe（需要.NET Framework4），界面如图所示。





获取 XMR 钱包地址


想要保存门罗币，我们需要一个钱包，这里推荐 mymonero.com。

点 击 “ 关 于 ” ， 打 开 在 线 钱 包 链 接 。






创建一个新钱包，这里有一个口令，要保存下来，不然就无法登录了//



点击 copy 复制你的收款地址~



回 到 xmrGuiMiner ， 填 写 你 的 收 款 地 址 ， 点 击 开 始 挖 矿 ， duang~

```

XMRig 6.10.0
* ABOUT      XMRig/6.10.0 MSVC/2019
* LIBS       libuv/1.41.0 OpenSSL/1.1.1j hwloc/2.4.1
* HUGE PAGES permission granted
* 1GB PAGES  unavailable
* CPU        Intel(R) Core(TM) i5-8400 CPU @ 2.80GHz (1) 64-bit AES
              L2:1.5 MB L3:9.0 MB 6C/6T NUMA:1
              3.8/7.8 GB (48%)
              ChannelA-DIMM0: <empty>
              ChannelA-DIMM1: <empty>
              DIMM_B0: 8 GB DDR4 @ 2667 MHz M471A1K43CB1-CTD
              ChannelB-DIMM1: <empty>
* MEMORY
* MOTHERBOARD
* DONATE     1%
* ASSEMBLY   auto:intel
* POOL #1    pool.supportxmr.com:5555 algo auto
* COMMANDS   hashrate, pause, resume, results, connection
* OPENCL     disabled
* CUDA       disabled
[2021-04-20 21:25:40.515] net use pool pool.supportxmr.com:5555 91.121.140.167
[2021-04-20 21:25:40.522] net new job from pool.supportxmr.com:5555 diff 100001 algo rx/0 height 234384
[2021-04-20 21:25:40.523] cpu use argon2 implementation AVX2
[2021-04-20 21:25:40.781] msr register values for "intel" preset have been set successfully (256 ms)
[2021-04-20 21:25:40.781] randomx init dataset algo rx/0 (4 threads) seed a6514bf641e3ed07...
[2021-04-20 21:25:40.810] randomx allocated 2336 MB (2080+256) huge pages 11% 128/1168 +JIT (28 ms)
[2021-04-20 21:25:46.361] randomx dataset ready (5551 ms)
[2021-04-20 21:25:46.361] cpu use profile rx (4 threads) scratchpad 2048 KB
[2021-04-20 21:25:46.367] cpu READY threads 4/4 (4) huge pages 100% 4/4 memory 8192 KB (5 ms)

```

散热不好就直接起飞了！调节 cpu 选项下面的滑块可以调整 cpu 占用量（需要重启挖矿软件）

这个时候我们点击“关于”下的“矿池主页”，来到矿池官网，输入付款地址，就可以看到收益了！达到 0.01xmr 就可以选择提取了。

