

Zello Work client SDK for Windows

Push-to-talk SDK for your Windows or Windows Mobile application

Version: 2.12 Date: Nov 1, 2016

Introduction

Thanks for downloading Zello for Work SDK. It's designed to enable easy integration of push-to-talk function into any application. This document will guide you through the installation and use of the SDK.

Technology

Zello for Work SDK provides ActiveX wrapper exposing the required set of Zello client functions. It's designed to work with Zello Enterprise server or with Zello for Work managed service.

Installation

You need a Windows PC to use the SDK. To install the SDK launch the [ZelloWorkClientSDKSetup.exe](#) and follow the installation wizard:



The SDK installs samples, documentation and registers ActiveX control (ptt.dll). Once installed you can access SDK items from Start menu.

Samples overview

Before digging into the code you can try the compiled samples, which are located in 'Samples\bin' subfolder of the SDK.

Sample1.exe

Win32 C++ application for Windows using ActiveX control



Sample2.htm

embedding Zello ActiveX control into a web-page. Use Internet Explorer to view this sample.



Sample3.exe

.NET application for Windows using ActiveX control



Sample4.exe

Win32 C++ application for Windows Mobile. This one is a bit tricky. To test it you have to copy the file and ptt.dll from 'mobile' subfolder to the mobile device and register ptt.dll there using regsvrce.exe utility.



Sample5.exe

Win32 C++ application for Windows implementing custom GUI



Sample6.exe

.NET 2.0 C# application for Windows Mobile



Sample7.exe

Visual Basic 6 application for Windows using ActiveX control



SoundSample.exe

.NET 2.0 C# application



The samples are compiled for the use with 'default.zellowork.com' Zello for Work network. You can use any of the following login / password pairs to sign in:

test / test test2 / test test3 / test test4 / test test5 / test test6 / test test7 / test test8 / test

Please note that this network / usernames is intended for quick test only. For your development you'll need to register your own free Zello for Work network.

Exploring the code

Follow these steps to start developing with Zello for Work SDK.

Step 1. Register your development network

1. Go to zellowork.com enter desired network name, your full name and a valid e-mail address.
2. An e-mail will be sent to you with the new network admin password
3. Log-in to the newly created network web console and add some test users. You can create up to 5 users for your testing.

Step 2. Open relevant sample and modify the code to use your network

1. Sample 2 uses HTML and JavaScript only so it could viewed and edited in any text editor a. All other samples require Visual Studio 2008 or later
2. In the code replace network name 'default' with the name of the network you just registered
3. Compile and run the sample
4. Verify that you can login using the accounts you created
5. Test push-to-talk functionality

Step 3. Check out documentation

1. Explore [ZelloForWork.chm](#) installed with the SDK to see the interfaces available to your application
2. Contact us if you have any questions or can't find the API method you need

Deploying your application

When deploying your application make sure that the following conditions are met:

1. Your application installer installs and registers ptt.dll ActiveX control
2. Make sure that you use the appropriate ActiveX control for your target platform. a. ptt.dll located in the SDK root folder is intended for Windows b. ptt.dll located in the 'mobile' subfolder is intended for Windows Mobile

Additional resources

For more information visit our website at www.zello.com or send an e-mail to support@zello.com