


← → ↻ ⚠ Not secure | 3.92.126.30



# Apache2 Ubuntu Default Page

**It works!**

This is the default welcome page used to test the correct operation of the Apache2 server after installation on Ubuntu systems. It is based on the equivalent page on Debian, from which the Ubuntu Apache packaging is derived. If you can read this page, it means that the Apache HTTP server installed at this site is working properly. You should **replace this file** (located at `/var/www/html/index.html`) before continuing to operate your HTTP server.

If you are a normal user of this web site and don't know what this page is about, this probably means that the site is currently unavailable due to maintenance. If the problem persists, please contact the site's administrator.

## Configuration Overview


Ubuntu's Apache2 default configuration is different from the upstream default configuration, and split into several files optimized for interaction with Ubuntu tools. The configuration system is **fully documented in [/usr/share/doc/apache2/README.Debian.gz](#)**. Refer to this for the full documentation. Documentation for the web server itself can be found by accessing the **manual** if the `apache2-doc` package was installed on this server.

The configuration layout for an Apache2 web server installation on Ubuntu systems is as follows:

```
/etc/apache2/
|-- apache2.conf
|   |-- ports.conf
|-- mods-enabled
|   |-- *.load
|   |-- *.conf
|-- conf-enabled
|   |-- *.conf
|-- sites-enabled
|   |-- *.conf
```

- `apache2.conf` is the main configuration file. It puts the pieces together by including all remaining configuration files when starting up the web server.
- `ports.conf` is always included from the main configuration file. It is used to determine the listening ports for

← → ↻ 🔒 us-east-1.console.aws.amazon.com/ec2-instance-connect/ssh?region=us-east-1&connType=standard&instanceId=i-086e6c1cc07d11677&osUser=ubuntu&...



Services 🔍 Search [Alt+S]

IAM EC2 S3 VPC AWS Organizations

```
System load: 0.92      Processes:           107
Usage of /: 23.5% of 7.57GB   Users logged in:       0
Memory usage: 26%          IPv4 address for eth0: 10.0.0.124
Swap usage: 0%

Expanded Security Maintenance for Applications is not enabled.

9 updates can be applied immediately.

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

ubuntu@ip-10-0-0-124:~$
```

i-086e6c1cc07d11677

PublicIPs: 3.92.126.30 PrivateIPs: 10.0.0.124

CloudShell Feedback Language © 2023, Amazon Web Services, Inc. or its affiliates. Privacy

us-east-1.console.aws.amazon.com/ec2/home?region=us-east-1#Instances:

Services 🔍 Search [Alt+S]

S3 VPC AWS Organizations

## Instances (2) Info

Find Instance by attribute or tag (case-sensitive)

	Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability
<input type="checkbox"/>	-	i-086e6c1cc07d11677	Running	t2.micro	Initializing	No alarms	us-east-1a