

Basic
Accelerators
Resize presets
Margins
Help

For changes in this and other tabs to take effect - disable and enable gTile in Gnome Tweak Tool(Tweaks) -> Extensions -> gTile -> Off/On

☒ Auto close

☐ Animation

☒ Show icon

Grid sizes (like 6x4,8x6,21x11):

☒ Global resize presets (works without gTile activated)

Maximum timeout for preset cycling (ms):

☐ Debug

To see debug messages, in terminal run `journalctl /usr/bin/gnome-shell -f`

Basic	Accelerators	Resize presets	Margins	Help
Preset resize 1				Alt+Super+G
Preset resize 2				Alt+Super+T
Preset resize 3				Alt+Super+5
Preset resize 4				Alt+Super+6
Preset resize 5				Alt+Super+7
Preset resize 6				Alt+Super+U
Preset resize 7				Alt+Super+J
Preset resize 8				Alt+Super+H
Preset resize 9				Alt+Super+Y
Preset resize 10				Alt+Super+B
Preset resize 11				Alt+Super+N
Preset resize 12				Alt+Super+M

Basic
Accelerators
Resize presets
Margins
Help

Preset resize 1:	<input type="text" value="2x2 0:1 0:1"/>
Preset resize 2:	<input type="text" value="2x2 0:0 0:1"/>
Preset resize 3:	<input type="text" value="2x2 0:0 0:0"/>
Preset resize 4:	<input type="text" value="2x2 0:0 1:0"/>
Preset resize 5:	<input type="text" value="2x2 1:0 1:0"/>
Preset resize 6:	<input type="text" value="2x2 1:0 1:1"/>
Preset resize 7:	<input type="text" value="2x2 1:1 1:1"/>
Preset resize 8:	<input type="text" value="2x2 0:1 1:1"/>
Preset resize 9:	<input type="text" value="1x1 0:0 0:0"/>
Preset resize 10:	<input type="text" value="4x5 1:1 2:3"/>
Preset resize 11:	<input type="text" value="7x27 1:1 5:25"/>
Preset resize 12:	<input type="text" value="27x27 1:1 25:25"/>