



S5/L1

CONSEGNA

di Giuseppe Lupoi



General Configuration

Enable ☒ Enable interfaceDescription

LAN

Enter a description (name) for the interface here.

IPv4 Configuration Type

Static IPv4

IPv6 Configuration Type

Track Interface

MAC Address

xx:xx:xx:xx:xx:xx

This field can be used to modify ("spoof") the MAC address of this interface.
Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx or leave blank.

MTU

If this field is blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary in some circumstances.

MSS

If a value is entered in this field, then MSS clamping for TCP connections to the value entered above minus 40 for IPv4 (TCP/IPv4 header size) and minus 60 for IPv6 (TCP/IPv6 header size) will be in effect.

Speed and Duplex

Default (no preference, typically autoselect)

Explicitly set speed and duplex mode for this interface.

WARNING: MUST be set to autoselect (automatically negotiate speed) unless the port this interface connects to has its speed and duplex forced.

Static IPv4 Configuration

IPv4 Address

192.168.1.1

/ 24

IPv4 Upstream gateway

None

[+ Add a new gateway](#)

If this interface is an Internet connection, select an existing Gateway from the list or add a new one using the "Add" button.
On local area network interfaces the upstream gateway should be "none".
Selecting an upstream gateway causes the firewall to treat this interface as a [WAN type interface](#).
Gateways can be managed by [clicking here](#).

General Configuration

Enable

☒ Enable interface

Description

LAN2

Enter a description (name) for the interface here.

IPv4 Configuration Type

Static IPv4

IPv6 Configuration Type

None

MAC Address

xx:xx:xx:xx:xx:xx

This field can be used to modify ("spoof") the MAC address of this interface.
Enter a MAC address in the following format: xx:xx:xx:xx:xx:xx or leave blank.

MTU

If this field is blank, the adapter's default MTU will be used. This is typically 1500 bytes but can vary in some circumstances.

MSS

If a value is entered in this field, then MSS clamping for TCP connections to the value entered above minus 40 for IPv4 (TCP/IPv4 header size) and minus 60 for IPv6 (TCP/IPv6 header size) will be in effect.

Speed and Duplex

Default (no preference, typically autoselect)

Explicitly set speed and duplex mode for this interface.
WARNING: MUST be set to autoselect (automatically negotiate speed) unless the port this interface connects to has its speed and duplex forced.

Static IPv4 Configuration

IPv4 Address

192.168.50.1

/ 24

IPv4 Upstream gateway

None

+ Add a new gateway

If this interface is an Internet connection, select an existing Gateway from the list or add a new one using the "Add" button.
On local area network interfaces the upstream gateway should be "none".
Selecting an upstream gateway causes the firewall to treat this interface as a [WAN type interface](#).
Gateways can be managed by [clicking here](#).

Edit Firewall Rule

Action

Block

Choose what to do with packets that match the criteria specified below.
Hint: the difference between block and reject is that with reject, a packet (TCP RST or ICMP port unreachable for UDP) is returned to the sender, whereas with block the packet is dropped silently. In either case, the original packet is discarded.

Disabled

☐ Disable this rule
Set this option to disable this rule without removing it from the list.

Interface

LAN

Choose the interface from which packets must come to match this rule.

Address Family

IPv4

Select the Internet Protocol version this rule applies to.

Protocol

Any

Choose which IP protocol this rule should match.

Source

Source

☐ Invert match

Network

192.168.1.100 / 24

Destination

Destination

☐ Invert match

Network

192.168.50.101 / 24

```
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).
```

```
# The loopback network interface
auto lo
iface lo inet loopback
```

```
# The primary network interface
auto eth0
iface eth0 inet static
address 192.168.50.101
netmask 255.255.255.0
network 192.168.50.0
broadcast 192.168.50.255
gateway 192.168.50.1
```

Starting syslog...done.

Starting CRON... done.

pfSense 2.7.2-RELEASE amd64 20231206-2010

Bootup complete

FreeBSD/amd64 (pfSense.pfsense.domain) (ttyv0)

VirtualBox Virtual Machine - Netgate Device ID: 3d90e9269c14e850f12e

[Read 17 lines

^G Get Help ^O WriteOut ^R Read File ^Y Prev
^X Exit ^J Justify ^W Where Is ^V Next

*** Welcome to pfSense 2.7.2-RELEASE (amd64) on pfSense ***

WAN (wan) -> em0 -> v4: 192.168.1.2/24

LAN (lan) -> em1 -> v4: 192.168.1.1/24

0) Logout (SSH only)

9) pfTop

1) Assign Interfaces

10) Filter Logs

2) Set interface(s) IP address

11) Restart webConfigurator

3) Reset webConfigurator password

12) PHP shell + pfSense tools

4) Reset to factory defaults

13) Update from console

5) Reboot system

14) Enable Secure Shell (sshd)

6) Halt system

15) Restore recent configuration

7) Ping host

16) Restart PHP-FPM

8) Shell

Enter an option:



kali@kali: ~



```
(kali@kali)-[~]
```

```
$ ping 192.168.50.101
```

```
PING 192.168.50.101 (192.168.50.101) 56(84) bytes of data.
```

```
^C
```

```
--- 192.168.50.101 ping statistics ---
```

```
5 packets transmitted, 0 received, 100% packet loss, time 4139ms
```

```
(kali@kali)-[~]
```

```
$
```