

```
C:\Windows\system32\cmd.exe - cmd

C:\Users\gabo0>cd Documents\Launch X\Modulos\Modulo 2

C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>python3 -m venv env

C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>md src

C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>dir
El volumen de la unidad C es OS
El número de serie del volumen es: B802-9483

Directorio de C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2

12/02/2022  08:29 p. m.    <DIR>          .
12/02/2022  08:29 p. m.    <DIR>          ..
12/02/2022  07:16 p. m.    <DIR>          env
12/02/2022  08:29 p. m.    <DIR>          src
                0 archivos                0 bytes
                4 dirs 34,708,611,072 bytes libres

C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>env\Scripts\activate

(env) C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>pip install python-dateutil
Collecting python-dateutil
  Using cached python_dateutil-2.8.2-py2.py3-none-any.whl (247 kB)
Collecting six>=1.5
  Using cached six-1.16.0-py2.py3-none-any.whl (11 kB)
Installing collected packages: six, python-dateutil
Successfully installed python-dateutil-2.8.2 six-1.16.0
WARNING: You are using pip version 21.2.4; however, version 22.0.3 is available.
You should consider upgrading via the 'C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2\env\Scripts\python.exe -m
pip install --upgrade pip' command.

(env) C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>env\Scripts\python.exe -m pip install --upgrade pip
Requirement already satisfied: pip in c:\users\gabo0\documents\launch x\modulos\modulo 2\env\lib\site-packages (21.2.4)
Collecting pip
  Using cached pip-22.0.3-py3-none-any.whl (2.1 MB)
Collecting command
  Using cached Command-0.1.0.tar.gz (5.3 kB)
Requirement already satisfied: setuptools in c:\users\gabo0\documents\launch x\modulos\modulo 2\env\lib\site-packages (from command) (58.1.0)
Using legacy 'setup.py install' for command, since package 'wheel' is not installed.
Installing collected packages: pip, command
  Attempting uninstall: pip
    Found existing installation: pip 21.2.4
    Uninstalling pip-21.2.4:
      Successfully uninstalled pip-21.2.4
  Running setup.py install for command ... done
Successfully installed command-0.1.0 pip-22.0.3

(env) C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>pip freeze
Command==0.1.0
python-dateutil==2.8.2
six==1.16.0

(env) C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>deactivate
C:\Users\gabo0\Documents\Launch X\Modulos\Modulo 2>
```