

Risolvere problemi a Metasploitable 2

Come possiamo notare dal primo PDF, effettuiamo una scansione tramite « Nessus » dalla macchina Kali a Metasploitable 2 notiamo delle vulnerabilità critiche (e non) che dobbiamo risolvere per rendere la macchina Metasploitable 2 più sicura. Di seguito possiamo vedere i procedimenti necessari→



```
# /etc/exports: the access control list for filesystems which may be exported
#               to NFS clients.  See exports(5).
#
# Example for NFSv2 and NFSv3:
# /srv/homes          hostname1(rw,sync) hostname2(ro,sync)
#
# Example for NFSv4:
# /srv/nfs4           gss/krb5i(rw,sync,fsid=0,crossmnt)
# /srv/nfs4/homes     gss/krb5i(rw,sync)
#
/mnt/newdisk         192.168.50.101(rw,sync,no_root_squash,no_subtree_check)
```



meta [In esecuzione] - Oracle VM VirtualBox



File Macchina Visualizza Inserimento Dispositivi Aiuto

```
disable          Disables the firewall
default ARG      set default policy to ALLOW or DENY
logging ARG      set logging to ON or OFF
allow|deny RULE  allow or deny RULE
delete allow|deny RULE delete the allow/deny RULE
status           show firewall status
version          display version information
```

```
root@metasploitable:/home/msfadmin# ufw deny 139
```

```
Rule added
```

```
root@metasploitable:/home/msfadmin# ufw deny 445
```

```
Rule added
```

```
root@metasploitable:/home/msfadmin# ufw status
```

```
Firewall loaded
```

To	Action	From
--	-----	----
1524:tcp	DENY	Anywhere
1524:udp	DENY	Anywhere
139:tcp	DENY	Anywhere
139:udp	DENY	Anywhere
445:tcp	DENY	Anywhere
445:udp	DENY	Anywhere

```
root@metasploitable:~# ufw enable
Firewall started and enabled on system startup
root@metasploitable:~# ufw default allow
Default policy changed to 'allow'
(be sure to update your rules accordingly)
root@metasploitable:~# ufw deny 1524
Rule added
root@metasploitable:~# ufw status
Firewall loaded
```

To	Action	From
--	-----	----
1524:tcp	DENY	Anywhere
1524:udp	DENY	Anywhere

```
root@metasploitable:/home/msfadmin# vncpasswd
Using password file /root/.vnc/passwd
Password:
Warning: password truncated to the length of 8.
Verify:
Would you like to enter a view-only password (y/n)? n
root@metasploitable:/home/msfadmin#
```