

# KATA 2

## Creación del entorno

```
Administrador: Símbolo del sistema
Microsoft Windows [Versión 10.0.19042.1466]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\WINDOWS\system32>cd /


C:\>cd Users

C:\Users>cd DELL-E6440\Documents\Launch_X\Entorno_Virtual

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python3 -m venv env
Acceso denegado.

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python -m venv env

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>
```



## Activar Entorno

```
Administrador: Símbolo del sistema
Microsoft Windows [Versión 10.0.19042.1466]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\WINDOWS\system32>cd /

C:\>cd Users

C:\Users>cd DELL-E6440\Documents\Launch_X\Entorno_Virtual

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python3 -m venv env
Acceso denegado.

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python -m venv env

C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>env\Scripts\activate
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>
```

## Bibliotecas Instaladas

```
CA: Administrador: Símbolo del sistema
Microsoft Windows [Versión 10.0.19042.1466]
(c) Microsoft Corporation. Todos los derechos reservados.
C:\WINDOWS\system32>cd /
C:\>cd Users
C:\Users>cd DELL-E6440\Documents\Launch_X\Entorno_Virtual
C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python3 -m venv env
Acceso denegado.
C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>python -m venv env
C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>env\Scripts\activate
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>pip freeze
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>
```

## Instalar Biblioteca

```
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>pip install python-dateutil
Collecting python-dateutil
  Using cached python_dateutil-2.8.2-py2.py3-none-any.whl (247 kB)
Collecting six>=1.5
  Using cached six-1.16.0-py2.py3-none-any.whl (11 kB)
Installing collected packages: six, python-dateutil
Successfully installed python-dateutil-2.8.2 six-1.16.0
WARNING: You are using pip version 20.2.3; however, version 22.0.3 is available.
You should consider upgrading via the 'c:\users\dell-e6440\documents\launch_x\entorno_virtual\env\scripts\python.exe -m pip install --upgrade pip' command.
```

## Bibliotecas Instaladas 2

```
CA: Administrador: Símbolo del sistema
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>pip freeze
python-dateutil==2.8.2
six==1.16.0
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>
```

## Salir del Entorno Virtual

```
CA: Administrador: Símbolo del sistema
(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>pip freeze
python-dateutil==2.8.2
six==1.16.0

(env) C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>deactivate
C:\Users\DELL-E6440\Documents\Launch_X\Entorno_Virtual>
```