



Launch instance wizard | EC2 Ma x

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

ServicesResource GroupsJava TechleOhioSupport

1. Choose AMI2. Choose Instance Type3. Configure Instance4. Add Storage5. Add Tags6. Configure Security Group7. Review

### Step 2: Choose an Instance Type

Amazon EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications. [Learn more](#) about instance types and how they can meet your computing needs.

Filter by: All instance typesCurrent generationShow/Hide Columns

Currently selected: t2.micro (Variable ECUs, 1 vCPUs, 2.5 GHz, Intel Xeon Family, 1 GiB memory, EBS only)

	Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance	IPv6 Support
<input type="checkbox"/>	General purpose	t2.nano	1	0.5	EBS only	-	Low to Moderate	Yes
<input checked="" type="checkbox"/>	General purpose	t2.micro Free tier eligible	1	1	EBS only	-	Low to Moderate	Yes
<input type="checkbox"/>	General purpose	t2.small	1	2	EBS only	-	Low to Moderate	Yes
<input type="checkbox"/>	General purpose	t2.medium	2	4	EBS only	-	Low to Moderate	Yes

CancelPreviousReview and LaunchNext: Configure Instance Details

FeedbackEnglish (US)

© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy PolicyTerms of Use

Launch instance wizard | EC2 Ma x

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

ServicesResource GroupsJava TechleOhioSupport

1. Choose AMI2. Choose Instance Type3. Configure Instance4. Add Storage5. Add Tags6. Configure Security Group7. Review

### Step 3: Configure Instance Details

Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot instances to take advantage of the lower pricing, assign an access management role to the instance, and more.

Number of instances

1

Launch into Auto Scaling Group

Purchasing option

☐ Request Spot instances

Network

vpc-1d38e976 (default)

Create new VPC

Subnet

No preference (default subnet in any Availability Zone)

Create new subnet

Auto-assign Public IP

Use subnet setting (Enable)

Placement group

☐ Add instance to placement group

Capacity Reservation

Open

Create new Capacity Reservation

IAM role

None

Create new IAM role

CancelPreviousReview and LaunchNext: Add Storage

FeedbackEnglish (US)

© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy PolicyTerms of Use

Launch instance wizard | EC2 Ma x

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

Services Resource Groups

Java Techle Ohio Support

1. Choose AMI2. Choose Instance Type3. Configure Instance4. Add Storage5. Add Tags6. Configure Security Group7. Review

### Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. [Learn more](#) about storage options in Amazon EC2.

Volume Type ⓘ	Device ⓘ	Snapshot ⓘ	Size (GiB) ⓘ	Volume Type ⓘ	IOPS ⓘ	Throughput (MB/s) ⓘ	Delete on Termination ⓘ	Encryption ⓘ
Root	/dev/xvda	snap-022074bd3078559c6	8	General Purpose SSD (gp2)	100 / 3000	N/A	<input checked="" type="checkbox"/>	Not Encrypt

Add New Volume

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage. [Learn more](#) about free usage tier eligibility and usage restrictions.

CancelPreviousReview and LaunchNext: Add Tags

FeedbackEnglish (US)© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy PolicyTerms of Use

Launch instance wizard | EC2 Ma x

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

Services Resource Groups

Java Techle Ohio Support

1. Choose AMI2. Choose Instance Type3. Configure Instance4. Add Storage5. Add Tags6. Configure Security Group7. Review

### Step 5: Add Tags

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver. A copy of a tag can be applied to volumes, instances or both. Tags will be applied to all instances and volumes. [Learn more](#) about tagging your Amazon EC2 resources.

Key (128 characters maximum)	Value (256 characters maximum)	Instances ⓘ	Volumes ⓘ
This resource currently has no tags			
Choose the Add tag button or <a href="#">click to add a Name tag</a> . Make sure your <a href="#">IAM policy</a> includes permissions to create tags.			

Add Tag (Up to 50 tags maximum)

CancelPreviousReview and LaunchNext: Configure Security Group

FeedbackEnglish (US)© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy PolicyTerms of Use

Launch instance wizard | EC2 Ma x

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

Services Resource Groups

Java Techle Ohio Support

1. Choose AMI2. Choose Instance Type3. Configure Instance4. Add Storage5. Add Tags6. Configure Security Group7. Review

### Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one below. [Learn more](#) about Amazon EC2 security groups.

Assign a security group: ☒ Create a new security group ☐ Select an existing security group

Security group name:

Description:

Type	Protocol	Port Range	Source	Description
SSH	TCP	22	Custom 0.0.0.0/0	e.g. SSH for Admin Desktop
Custom TCP f	TCP	8080	Anywhere 0.0.0.0/0, ::/0	e.g. SSH for Admin Desktop

Add Rule

Warning

[Cancel](#) [Previous](#) [Review and Launch](#)

Feedback English (US)

© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. [Privacy Policy](#) [Terms of Use](#)

Launch instance wizard | EC2 Ma

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#LaunchInstanceWizard:

aws

Services

Resource Groups

Java Techle

Ohio

Support

1. Choose AMI

2. Choose Instance Type

3. Configure Instance

4. Add Storage

5. Add Tags

6. Configure Security Group

7. Review

### Step 7: Review Instance Launch

Please review your instance launch details. You can go back to edit changes for each section. Click **Launch** to assign a key pair to your instance and complete the launch process.

⚠

**Improve your instances' security. Your security group, launch-wizard-3, is open to the world.**  
Your instances may be accessible from any IP address. We recommend that you update your security group rules to allow access from known IP addresses only.  
You can also open additional ports in your security group to facilitate access to the application or service you're running, e.g., HTTP (80) for web servers. [Edit security groups](#)

▼ AMI Details

Free tier eligible

**Amazon Linux AMI 2018.03.0 (HVM), SSD Volume Type - ami-083ebc5a49573896a**  
The Amazon Linux AMI is an EBS-backed, AWS-supported image. The default image includes AWS command line tools, Python, Ruby, Perl, and Java. The repositories include Docker, PHP, MySQL, PostgreSQL, and other packages.  
Root Device Type: ebs    Virtualization type: hvm

[Edit AMI](#)

▼ Instance Type

Instance Type	ECUs	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance

[Edit instance type](#)

Cancel

Previous

Launch

Feedback

English (US)

© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved.    [Privacy Policy](#)    [Terms of Use](#)

Instances | EC2 Management Co

us-east-2.console.aws.amazon.com/ec2/v2/home?region=us-east-2#Instances:search=i-08a1ed348b4828bbf;sort=instancetype

aws

Services

Resource Groups

Java Techle

Ohio

Support

New EC2 Experience

Launch Instance

Connect

Actions

EC2 Dashboard

Events

Tags

Reports

Limits

INSTANCES

Instance Types

Launch Templates

Spot Requests

Savings Plans

Reserved Instances

Dedicated Hosts

Capacity Reservations

IMAGES

search: i-08a1ed348b4828bbf

1 to 1 of 1

Name	Instance ID	Instance Type	Availability Zone	Instance State	Status Checks	Alarm Status	Public DNS (IP
	i-08a1ed348b4828bbf	t2.micro	us-east-2c	running	2/2 checks ...	None	ec2-3-20-240-14

Instance: i-08a1ed348b4828bbf    Public DNS: ec2-3-20-240-14.us-east-2.compute.amazonaws.com

Description

Status Checks

Monitoring

Tags

Instance ID	i-08a1ed348b4828bbf	Public DNS (IPv4)	ec2-3-20-240-14.us-east-2.compute.amazonaws.com
Instance state	running	IPv4 Public IP	3.20.240.14

Feedback

English (US)

© 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved.    [Privacy Policy](#)    [Terms of Use](#)