

1. Command for Setup (/invite_setup or /egi_setup)

- Admin initiates setup via /invite_setup or /egi_setup command.
- The bot responds via DM to guide the admin through the setup process.

2. Initial Role and Channel Setup Questions

1. Role Setup:

- Bot asks: "Have you set up roles on the server?" (Y/N)
- If "N", bot sends a DM advising the admin to set up roles and restart the setup later.

2. Channel Setup:

- If the answer is "Y", bot asks: "Have you set up a text channel with server and/or raid rules?" (Y/N)
- If "N", bot sends a DM advising the admin to set up the text channel and restart the setup later.

3. Rules Specification:

- If both previous answers are "Y", bot asks:
"Are there server rules, raid rules, or both?" (Admin responds with a number:
1. Server Rules, 2. Raid Rules, 3. Both)

3. Admin Setup Menu

Once both roles and channels are confirmed, the bot proceeds to a more detailed setup menu. The admin can:

1. Select Roles with Invite Permissions:

- Define how many roles will be granted permission to use the bot for creating invite links.
- Admin selects which specific roles from the server have this permission.

2. Assign Roles to Invite Link Types:

- Assign server roles to different invite link types:
 - a. **Guild Invite Link**
 - b. **Pug Invite Link**

3. Choose Announcement Channel:

- Select the text channel where the bot posts details of the invitee (name of invitee, creator of the invite, date joined).

4. Specify Rules Channel:

- Define which text channel contains the server and/or raid rules.

5. Define Welcome Messages:

- Set up different welcome messages:
 - a. For **Guild Invitees**
 - b. For **Pug Invitees** who **leave** after the raid
 - c. For **Pug Invitees** who **stay** after the raid

4. Bot Invite Link Types

The bot can generate three types of invite links:

1. Guild Invite Link (Non-Expiring)

- **Role Assignment:**
Invitees receive the role defined by the admin for **Guild Invite Links**.
- **Welcome Message:**
Bot sends the **Guild Invitee Welcome Message**.
- **Rules Link:**
Bot sends a link to the defined server/raid rules channel to the invitee.
- **Logging:**
Bot registers invitee info (invitee name, invite creator, date joined) in the specified text channel.

2. Pug Invite Link (Non-Expiring)

- **Prompt for Retention:**
Bot prompts the invitee (via DM) whether they wish to stay for future raids (Y/N).
 - If "N":
 - Invitee receives the **Raid-only Welcome Message**.
 - Bot sends a link to the raid rules (or server rules, if no raid rules exist).
 - Invitee is removed from the server after 5 hours, with no record kept.
 - If "Y":
 - Invitee receives the **Pug Invitee Welcome Message**.
 - Invitee is assigned the role defined for **Pug Invite Links**.
 - Bot registers invitee info (invitee name, invite creator, date joined) in the specified text channel.

3. Pug Invite Short Link (3-hour Expiry)

- **Short-Lived Invite:**
The link expires after 3 hours. The creator is reminded about the expiry and is asked to confirm the creation of this link (Y/N).
- **Role Assignment:**
Invitees are **not assigned a role** but are granted access to voice channels.
- **Welcome Message:**
Invitees receive the **Raid-only Welcome Message**.
- **Rules Link:**
Bot sends a link to the raid rules (or server rules, if no raid rules exist).
- **Removal After 5 Hours:**
Invitees are automatically removed from the server after 5 hours. No record of their presence is kept.

Note:

Any roles with permissions to create invites (not just the admin) can create **Pug Invite Short Links**.

5. Handling Invite Links Not Generated by the Bot

- If an invitee joins with a link not generated by the bot:
 - They are removed after 5 hours **unless** they are assigned a predefined role by the admin or other authorized role.
 - If a role is assigned, the bot logs the event in the proper text channel, stating: "Username" joined on "date" from unknown link, promoted to "role" by "user".

6. Invite Creation Process for Allowed Roles

- Roles with invite permissions can use /egi_invite or /invite to create invite links.
- The bot sends the user a DM with the following:
 1. A numbered list of invite link types:
 1. **Guild Invite Link**
 2. **Pug Invite Link**
 3. **Pug Invite Short Link**
 2. The user selects the desired invite type by responding with the corresponding number.
 3. The bot continues with the previously defined invite flow for the selected link type.