



```
Microsoft Windows [Versión 10.0.19043.1526]
(c) Microsoft Corporation. Todos los derechos reservados.

C:\Users\licgt>cd d:
D:\

C:\Users\licgt>d:
D:\

D:\>cd D:\zz programacion
D:\zz programacion> python3 -m venv env
D:\zz programacion>
```






```
C:\> Símbolo del sistema
D:\zz programacion>env\Scripts\activate
(env) D:\zz programacion>
```

```
Símbolo del sistema
D:\zz programacion>env\Scripts\activate

(env) D:\zz programacion>pip install python-dateutil
Requirement already satisfied: python-dateutil in d:\zz programacion\env\lib\site-packages (2.8.2)
Requirement already satisfied: six>=1.5 in d:\zz programacion\env\lib\site-packages (from python-dateutil) (1.16.0)
WARNING: You are using pip version 21.2.4; however, version 22.0.3 is available.
You should consider upgrading via the 'D:\zz programacion\env\Scripts\python.exe -m pip install --upgrade pip' command.

(env) D:\zz programacion>_
```



```
Símbolo del sistema
D:\zz programacion>env\Scripts\activate

(env) D:\zz programacion>pip install python-dateutil
Requirement already satisfied: python-dateutil in d:\zz programacion\env\lib\site-packages (2.8.2)
Requirement already satisfied: six>=1.5 in d:\zz programacion\env\lib\site-packages (from python-dateutil) (1.16.0)
WARNING: You are using pip version 21.2.4; however, version 22.0.3 is available.
You should consider upgrading via the 'D:\zz programacion\env\Scripts\python.exe -m pip install --upgrade pip' command.

(env) D:\zz programacion>pip freeze
python-dateutil==2.8.2
six==1.16.0

(env) D:\zz programacion>
```

```
Símbolo del sistema
D:\zz programacion>env\Scripts\activate

(env) D:\zz programacion>pip install python-dateutil
Requirement already satisfied: python-dateutil in d:\zz programacion\env\lib\site-packages (2.8.2)
Requirement already satisfied: six>=1.5 in d:\zz programacion\env\lib\site-packages (from python-dateutil) (1.16.0)
WARNING: You are using pip version 21.2.4; however, version 22.0.3 is available.
You should consider upgrading via the 'D:\zz programacion\env\Scripts\python.exe -m pip install --upgrade pip' command.

(env) D:\zz programacion>pip freeze
python-dateutil==2.8.2
six==1.16.0

(env) D:\zz programacion>
(env) D:\zz programacion>deactivate
D:\zz programacion>
```