


## Cara install ioncube loader di komputer local/laptop

- download ioncube loader wizard di <https://www.ioncube.com/loaders.php> pilih loader wizard versi zip.

[Home](#)[Products](#) ▾[Purchase](#)[Testimonials](#)[Partners](#) ▾[Support](#) ▾

### Loaders for ionCube Secured Files

Using ionCube encoded and secured PHP files requires a file called the ionCube Loader to be installed on the web server and made available to PHP. PHP can use the Loader with one line a with install, as well as manual instructions.

#### Installing with the Loader Installer or Loader Wizard (*recommended*)

It is recommended to install a Loader using the Loader Installer. The Installer is a Windows application that can deploy a Loader automatically to any supported operating system over FTI on installing manually.

Loader Installer: [ZIP](#)

Loader Wizard: [ZIP](#) [TGZ](#)

To use the Wizard, 1) download and install the script into your web space, then 2) launch the script in your browser. The Wizard will give guidance on selection and installation of the corre

#### Manual Install - Which Download Do I Need?

Archives and an uploader created with the [ionCube Package Foundry](#) are available for each supported server platform. Note that the uploader runs on [Windows](#) and uploads the Loaders au architecture (e.g. x86 or x86-64), your hosting company will be able to tell you.


If you need Loaders for platforms not mentioned please [contact us](#). Note that different distributions of Linux, e.g. CentOS, SuSE, Debian, RedHat etc. are all covered by the 32 and 64 bit I

#### Loader Packages

Notes: Loaders are for 32 and 64 bit x86 based systems unless otherwise specified. The Windows non-TS Loaders are for use on a Windows system where a phpinfo page shows that PHP is

- extract loader-wizard.zip pada d:/xampp/htdocs/ioncube/loader-wizard.php

- jalankan <http://localhost/ioncube/loader-wizard.php>
- punya saya folder ada di <d:/xampp551> jadi disitu tertulis xampp551, intruksi itu akan menyesuaikan konfigurasi anda.
- ikuti intruksi installasinya, yaitu download versi zip
- extract hasil download ke <d:/xampp/php/ioncube>

 Professional PHP Solutions  
**ionCube®**

**IMPORTANT: Ensure that This Script Is Removed When No Longer Required**

## ionCube Loader Wizard

Please note that the following problem currently exists with the ionCube Loader installation:

- The necessary zend\_extension line could not be found in the configuration.

To use files that have been protected by the [ionCube PHP Encoder](#), a component called the ionCube Loader must be installed.

For a **local** server you should install the ionCube Loader using the `php.ini` configuration file. ([Please click here if you are not on a local server.](#))

### Installation Instructions

- Download one of the following archives of Windows VC11 x86 Loaders:
  - [zip](#)
  - [MS Windows installer](#)

Please note that the MS Windows installer version is suitable either for direct installation on a Windows machine or for uploading from a local PC to your server.

A Loaders archive can also be downloaded from <http://loaders.ioncube.com/>.
- Put the Loader files in `D:\xampp551\php\ioncube`
- Edit the file `D:\xampp551\php\php.ini` and **before** any other zend\_extension lines ensure that the following is included:  
`zend_extension = "D:\xampp551\php\ioncube\ioncube_loader_win_5.5.dll"`  
Alternatively, replace your current `D:\xampp551\php\php.ini` file with [this new php.ini file](#).
- Restart the Apache server software.
- When the server software has restarted, [click here to test the Loader](#).

Copyright ionCube Ltd. 2002-2015 | Loader Wizard version 2.49 (current) | [wizard start](#) | [loader test](#) | [loaders](#)


- edit file D:\xampp\php\php.ini
- tambahkan zend\_extension = "D:\xampp\php\ioncube\ioncube\_loader\_win\_5.5.dll" setelah [PHP]

```


1 [PHP]
2 zend_extension = "D:\xampp551\php\ioncube\ioncube_loader_win_5.5.dll"
3
4 ;;;;;;;;;;;;;;;;;
5 ; About php.ini ;
6 ;;;;;;;;;;;;;;;;;
7 ; PHP's initialization file, generally called php.ini, is responsible for
8 ; configuring many of the aspects of PHP's behavior.
9

```

- restart apache anda pada xampp control (klik stop dan start lagi pada modul apache)



- pada halaman <http://localhost/ioncube/loader-wizard.php> klik link **loader test**, akan muncul status bahwa loader telah sukses diinstall



The screenshot shows a web browser window with the URL `localhost/ioncube/loader-wizard.php?timeout=0&ini=0&page=loader_check`. The page header features the ionCube logo and the text "Professional PHP Solutions". A dark red banner contains the text "IMPORTANT: Ensure that This Script Is". Below this, the heading "ionCube Loader Wizard" is displayed. A green box contains the message "Loader Installed Successfully" and "The ionCube Loader version 5.0.2 for PHP 5.5 is installed and encoded files should run successfully." Below the green box, it says "Please contact the script provider if you do experience any problems running encoded files." and "For security reasons we advise that you remove this Wizard script from your server now that". At the bottom, a footer contains the text "Copyright ionCube Ltd. 2002-2015 | Loader Wizard version 2.49 (current) | [wizard start](#) [loader test](#) [loaders](#)". The "loader test" link is highlighted with a black box.

← → ↻ `localhost/ioncube/loader-wizard.php?timeout=0&ini=0&page=loader_check`

**Professional PHP Solutions**  
**ionCube®**

**IMPORTANT: Ensure that This Script Is**

## ionCube Loader Wizard

**Loader Installed Successfully**

The ionCube Loader version 5.0.2 for PHP 5.5 **is installed** and encoded files should run successfully.

Please contact the script provider if you do experience any problems running encoded files.

**For security reasons we advise that you remove this Wizard script from your server now that**

---

Copyright ionCube Ltd. 2002-2015 | Loader Wizard version 2.49 (current) | [wizard start](#) [loader test](#) [loaders](#)

- Selesai