

Email- message send through localhost:

This php program send a message to any email through by localhost in php without using PHP Mailer.

Follow these steps and change some code in XAMPP folder in C drive.

Step1.

1. Go to xampp folder and open Php folder.
2. In Php folder open php.ini
3. Find SMTP mail function then some few change only red indicate part.

[mail function]

; For Win32 only.

; http://php.net/smtp

SMTP=**SMTP.gmail.com**

; http://php.net/smtp-port

smtp_port=**587**

; For Win32 only.

; http://php.net/sendmail-from

sendmail_from = **Your Email id**

; For Unix only. You may supply arguments as well (default: "sendmail -t -i").

; http://php.net/sendmail-path

sendmail_path = **"c:\xampp\sendmail\sendmail.exe" -t"**

4. All red text will be change and please also match above code.
5. Then save this file.

Step2: open sendmail folder in xampp.

1. In open sendmail folder then open sendmail file

2. Now open sendmail then some few change only indicate red word will be change.

[sendmail]

; you must change mail.mydomain.com to your smtp server,
; or to IIS's "pickup" directory. (generally C:\Inetpub\mailroot\Pickup)
; emails delivered via IIS's pickup directory cause sendmail to
; run quicker, but you won't get error messages back to the calling
; application.

smtp_server=**SMTP.gmail.com**

; smtp port (normally 25)

smtp_port=**587**

; SMTPS (SSL) support
; auto = use SSL for port 465, otherwise try to use TLS
; ssl = alway use SSL
; tls = always use TLS
; none = never try to use SSL

smtp_ssl=auto

; the default domain for this server will be read from the registry
; this will be appended to email addresses when one isn't provided
; if you want to override the value in the registry, uncomment and modify

default_domain=**SMTP.gmail.com**

; log smtp errors to error.log (defaults to same directory as sendmail.exe)
; uncomment to enable logging

error_logfile=**error.log**

; create debug log as debug.log (defaults to same directory as sendmail.exe)
; uncomment to enable debugging

debug_logfile=**debug.log**

; if your smtp server requires authentication, modify the following two lines

```
auth_username=Your Eail id  
auth_password=Your email password
```

; if your smtp server uses pop3 before smtp authentication, modify the
; following three lines. do not enable unless it is required.

```
pop3_server=  
pop3_username=  
pop3_password=
```

; force the sender to always be the following email address
; this will only affect the "MAIL FROM" command, it won't modify
; the "From: " header of the message content

```
force_sender=Your email id
```

3. All red text will be change and please also match above code.
4. Then save this file.

Step3: Open your email in google browser then go to setting. Now click **security** then switch **off** to the less secure app access.