

Sessions	
<b>tmux</b>	Start a new session.
<b>tmux new -s [session_name]</b>	Create a new session with a specific name.
<b>tmux attach</b>	Re-attach to the latest active session.
<b>tmux detach</b>	Disconnect from a session, but keep it running.
<b>tmux attach -t [session_name]</b> or <b>tmux -a -t [session_name]</b>	Attach to session with a specific name.
<b>tmux switch -t [session_name]</b>	Switch to a different session.
<b>tmux kill-session -a</b>	Terminate all sessions but the current one.
<b>tmux kill-session -t [session_name]</b>	Terminate a specific session.
<b>tmux kill-session -a -t [session_name]</b>	Terminate all sessions except the specified one.
<b>tmux list-sessions</b> or <b>tmux ls</b>	List all active sessions
<b>tmux rename-session -t [old_name] [new_name]</b>	Rename an existing session.
<b>tmux kill-server</b>	Terminate the server, ending all sessions, windows, and panes.
Panes	
<b>Ctrl + b then %</b>	Split the current pane vertically
<b>Ctrl + b then "</b>	Split the current pane horizontally
<b>Ctrl + b then x</b>	Close the current pane
<b>Ctrl + b then o</b>	Toggle between panes
<b>Ctrl + b then z</b>	Toggle pane zoom (make pane full screen)
<b>Ctrl + b then ;</b>	Toggle between the last two active panes
<b>Ctrl + b then {</b>	Move the current pane left
<b>Ctrl + b then }</b>	Move the current pane right
<b>Ctrl + b then SPACE</b>	Toggle through different pane layouts
<b>Ctrl + b then !</b>	Convert the current pane into a window
<b>exit or Ctrl + b</b>	Close the selected pane
<b>Ctrl + b then q</b>	Display pane number
<b>Ctrl + b then :</b>	Enter tmux Command Mode
<b>Ctrl + b + [up_arrow]</b>	Increase pane height
<b>Ctrl + b + [down_arrow]</b>	Decrease pane height
<b>Ctrl + b + [left_arrow]</b>	Increase pane width
<b>Ctrl + b + [right_arrow]</b>	Decrease pane width

Windows	
<b>Ctrl + b then c</b>	Create a new window.
<b>Ctrl + b then ,</b>	Rename the current window.
<b>Ctrl + b then w</b>	List all windows.
<b>Ctrl + b then &amp;</b>	Kill the current window.
<b>Ctrl + b then n</b>	Switch to the next window.
<b>Ctrl + b then p</b>	Switch to the previous window.
<b>Ctrl + b then l</b>	Open the last window.
<b>Ctrl + b then 0 ... 9</b>	Switch to a specific numbered window.
<b>Ctrl + b then d</b>	Detach from the current session.
<b>tmux select-window -t [window_name]</b>	Select a specific window by index or name.
<b>tmux rename-window [new_name]</b>	Rename the current window.
Command Mode	
(Use only in conjunction with Panes)	
<b>resize-pane -D</b>	Move the boundary line for the pane downward
<b>resize-pane -U</b>	Move the boundary line for the pane upward
<b>resize-pane -R</b>	Move the boundary line for the pane right
<b>resize-pane -U 10</b>	Move the boundary line up 10 cells
<b>resize-pane -t 2 -R 5</b>	Move the boundary line of cell number 2 five cells to the right
<b>resize-pane -Z</b>	Maximize the pane to full screen. Use the same command to set it back to normal
Copy Mode	
<b>Ctrl + b then [</b>	Enter copy mode
<b>q</b>	Exit copy mode
<b>ENTER</b>	Copy the selected text
<b>SPACE</b>	Start text selection in copy mode
<b>ESC</b>	Clear the selected text and exit copy mode
<b>h</b>	Move cursor left (vi mode-keys)
<b>j</b>	Move cursor down (vi mode-keys)
<b>k</b>	Move cursor up (vi mode-keys)
<b>l</b>	Move cursor right (vi mode-keys)
<b>w</b>	Move cursor one word forward (vi mode-keys)
<b>b</b>	Move cursor one word backward (vi mode-keys)
<b>Ctrl + b then ]</b>	Paste the copied text
<b>Ctrl + u</b>	Scroll up half a page (vi mode-keys)
<b>Ctrl + d</b>	Scroll down half a page (vi mode-keys)
<b>PgUp</b>	Scroll up full page
<b>PgDn</b>	Scroll down full page