

Goals:

By the end of this project you should be able to do the following:

- Handle exceptions that can occur in your program using a try-catch statement
- Throw exceptions in your program

Directions:

Don't forget to add your Javadoc comments for your classes, constructor, and methods in this activity.

For this assignment, you will be creating two classes: Division and DivisionDriver

Division: methods

- Division has two public static methods:
 - `intDivide`: takes two **int** parameters (a numerator and denominator), performs integer division, and returns the **int** result of dividing the numerator by the denominator.
 - `decimalDivide`: takes two **int** parameters (a numerator and denominator), performs floating point division (you'll have to use casting), and returns the result of dividing the numerator by the denominator.
- Test your methods in the Interactions pane:

```
Division.intDivide(10, 3)
3
Division.decimalDivide(10, 3)
3.3333333333333335
```

DivisionDriver

- DivisionDriver contains a main method only. The program will get a numerator and denominator from the user and print the integer division and decimal division result.
- Create a **dialog box** that will get the numerator and denominator as a String (you'll have to import the `JOptionPane` class in the `javax.swing` package):

```
String numInput
    = JOptionPane.showInputDialog("Enter the numerator:");

String denomInput
    = JOptionPane.showInputDialog("Enter the denominator:");
```

- Convert each to an integer value using the static `parseInt` method in the `Integer` class:

```
int num = _____.(numInput);
int denom = _____.(denomInput);
```




- Create a String object to hold the result of the division:

```
String result = "Integer division: \n"  
    + Division.intDivide(num, _____) \n  
    + "\n\nFloating point division: \n"  
    + Division._____(num, denom);
```



- Print the result in a dialog box:

```
JOptionPane.showMessageDialog(null, result,  
    "Result", JOptionPane.PLAIN_MESSAGE);
```

- Test your method by running the driver program with numerator 19 and denominator 5:



- Now try entering an invalid number in the dialogs (five and ten):



Your program should generate a run-time error in the form of a `NumberFormatException` exception:

```
----jGRASP exec: java DivisionDriver  
Exception in thread "main" java.lang.NumberFormatException: For input string: "five"  
    at java.lang.NumberFormatException.forInputString(NumberFormatException.java:65)  
    at java.lang.Integer.parseInt(Integer.java:580)  
    at java.lang.Integer.parseInt(Integer.java:615)  
    at DivisionDriver.main(DivisionDriver.java:9)  
  
----jGRASP wedge: exit code for process is 1.  
----jGRASP: operation complete.
```

- The exception occurs when the parseInt method tries to convert the String "five" to an integer. The Java API listing for parseInt lists the exception that it might throw.
- Use a try-catch statement to catch the exception and tell the user what went wrong without creating a run-time error:


```

try {
    int num = Integer.parseInt(numInput);
    int denom = Integer.parseInt(denomInput);
    String result = "Integer division: \n"
        + Division.intDivide(num, denom)
        + "\n\nFloating point division: \n"
        + Division.decimalDivide(num, denom);
    JOptionPane.showMessageDialog(null, result,
        "Result", JOptionPane.PLAIN_MESSAGE);
}
catch (NumberFormatException e)
{
    JOptionPane.showMessageDialog(null,
        "Invalid input: enter numerical integer values only.",
        "Error", JOptionPane.ERROR_MESSAGE);
}

```

Existing code

- Try entering invalid values five and ten once more for numerator and denominator once more. You should now get the following error:



Exception Throwing



- Try the following in the interactions pane:

```

Division.intDivide(10, 0)
java.lang.ArithmeticException: / by zero

```

- Try to run your driver program with the numerator 10 and denominator 0:




```

----jGRASP exec: java DivisionDriver
Exception in thread "main" java.lang.ArithmeticException: / by zero
    at Division.intDivide(Division.java:7)
    at DivisionDriver.main(DivisionDriver.java:12)


```

```
----jGRASP wedge: exit code for process is 1.
----jGRASP: operation complete.
```

- The exception is generated in the `intDivide` method and not caught/handled, so it is **propagated** to main where it is also not caught/handled. Next we want to catch the exception in the `intDivide` method so that it will not be propagated to the main method.
- In your `intDivide` method, add code that will return 0 if an `ArithmeticException` occurs and the division result otherwise:



Run `DivisionDriver` with inputs 10 and 0. The result should be 0 for integer division:



- Suppose that you do not want users to be able to divide by 0 in your `decimalDivide` method.

```
Division.decimalDivide(10, 0)
Infinity
```

The `IllegalArgumentException` in the Java API can be thrown if a particular argument (parameter) to a method is not allowed:

<http://download.oracle.com/javase/6/docs/api/java/lang/IllegalArgumentException.html>

- In your `decimalDivide` method, throw an `IllegalArgumentException` if the denominator is zero:

```
if (denom == 0) {
    throw new IllegalArgumentException("The denominator "
        + "cannot be zero.");
}
```

- Test your method again in interactions. You should now see the exception:

```
Division.decimalDivide(10, 0)
java.lang.IllegalArgumentException: The denominator cannot be zero.
```




- In your main method, add another catch statement to catch the exception that is thrown by the decimalDivide method. This time, print the exception text itself (stored by variable errorMessage):

```
catch(NumberFormatException e)
{
    JOptionPane.showMessageDialog(null,
        "Invalid input: enter numerical integer values only.",
        "Error", JOptionPane.ERROR_MESSAGE);
}

catch(_____ e)
{
    JOptionPane.showMessageDialog(null,
        e, "Error", JOptionPane.ERROR_MESSAGE);
}
```

Existing code

- Now try dividing by 0 in your program. You will get the following error message instead of a run-time error:



- Finally, submit your files to Web-CAT.