

<b>ID: R_ABR-1</b>
<b>Summary:</b>
Application interface is displayed in English, even if a different language is selected in the system and in the application
<b>Description:</b>
When the user selects any language on the device as the default language, the application interface continues to be displayed in English
<b>Steps:</b>
1. Select any language on the device and in the app
<b>Actual result:</b>
The application interface is displayed in English
<b>Expected result:</b>
The application interface is displayed in the selected language
<b>Severity:</b>
Critical
<b>Priority:</b>
A.S.A.P.
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/s9yccsqasRqXfA">https://disk.yandex.ru/i/s9yccsqasRqXfA</a>
<b>ID: R_ABR-2</b>
<b>Summary:</b>
Opening an image or coordinates during a pinned recording of a voice message cancels its recording
<b>Description:</b>
If during the pinned recording of a voice message, user opens image or coordinates in the chat, recording is automatically canceled
<b>Steps:</b>
1. Start recording a voice message and lock it
2. Open any image/coordinates in the chat

<b>Actual result:</b>
Opening an image or coordinates during a pinned recording of a voice message cancels its recording
<b>Expected result:</b>
Recording is canceled
<b>Severity:</b>
Major
<b>Priority:</b>
High
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/zALOAFt--pflog">https://disk.yandex.ru/i/zALOAFt--pflog</a>
<b>ID: R_ABR-3</b>
<b>Summary:</b>
If user deletes a text message marked "for everyone" in chats, then its text remains in the form of a pinning notification
<b>Description:</b>
If user pins a text message in any chat, and then deletes it marked "for everyone", then the text of the message remains in the form of a notification "you pinned <message text>"
<b>Steps:</b>
1. Pin any text message in any chat
2. Delete the message marked "for everyone"
<b>Actual result:</b>
Text of the message remains in the form of a notification "you pinned <message text>"
<b>Expected result:</b>
The pinning notification is deleted along with the message
<b>Severity:</b>
Medium

<b>Priority:</b>
High
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/iucPXQlhwQBrUA">https://disk.yandex.ru/i/iucPXQlhwQBrUA</a>
<b>ID: R_ABR-4</b>
<b>Summary:</b>
If message is pinned, it is not deleted
<b>Description:</b>
When user tries to delete a pinned message, when selecting the "delete" function, the message is not deleted
<b>Steps:</b>
1. Pin any message in the chat
2. Select "delete" option
<b>Actual result:</b>
The message is not deleted
<b>Expected result:</b>
The message is being deleted
<b>Severity:</b>
Medium
<b>Priority:</b>
High
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12

<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/2ZrXi-dWCTMXSA">https://disk.yandex.ru/i/2ZrXi-dWCTMXSA</a>
<b>Workaround:</b>
Delete a message marked "delete everywhere"
<b>ID: R_ABR-5</b>
<b>Summary:</b>
The notification melody is played endlessly (until the application is completely closed) when a new message is sent (the message sound is set to "Default (no sound)")
<b>Description:</b>
When a new message arrives to the user, even if the application is closed, the notification melody starts playing, although at the system level notifications are set without sound
<b>Steps:</b>
1. In the notification settings of the device, set the notification mode to "silent"
2. In the application settings, set the message sound to "Default (without sound)"
3. From a third-party device, write a message to the device under test
<b>Actual result:</b>
The notification melody is played endlessly (until the application is completely closed) when a new message is sent
<b>Expected result:</b>
No notification sound
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/KnHC4_rPYwNvYA">https://disk.yandex.ru/i/KnHC4_rPYwNvYA</a>

<b>Workaround:</b>
Select the "None" notification sound in the app
<b>ID: R_ABR-6</b>
<b>Summary:</b>
When pinning several messages in a community or secure group, the pinned message after deletion marked "delete everywhere" will remain in the pinned banner in an "empty" form
<b>Description:</b>
If a user pins several messages in a community or secure group and then deletes any of them without unpinning, then it will remain in the list of pinned in the banner in an empty form and when user press on the banner it will link to the deleted pinned message.
<b>Steps:</b>
1. Pin 2 or more messages in a community chat or secure group
2. Delete any pinned message marked "delete ewerywhere"
<b>Actual result:</b>
Pinned message after deletion will remain in the pinned banner in an "empty" form
<b>Expected result:</b>
Deleted message is not displayed in the pinned messages banner
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/-Oe8zTKgfFMyHg">https://disk.yandex.ru/i/-Oe8zTKgfFMyHg</a>
<b>ID: R_ABR-7</b>
<b>Summary:</b>
After pinning/unpinning a message in any chat, the banner with the pinned message sometimes does not appear/disappears until the chat is closed

<b>Description:</b>
When a user pins or unpins a message in any chat, the banner with the pinned message sometimes does not appear/disappears until the chat is closed
<b>Steps:</b>
1. Pin a message in any chat
<b>Actual result:</b>
Banner does not appear/disappears after pinning/unpinning the message
<b>Expected result:</b>
The banner appear/disappears after pinning/unpinning the message
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Sometimes
<b>Environment:</b>
RingI v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/DhQqfj_7R7E_rg">https://disk.yandex.ru/i/DhQqfj_7R7E_rg</a>
<b>ID: R_ABR-8</b>
<b>Summary:</b>
When user pins a message, when the "cross" icon of the pinned messages banner is clicked, the banner does not disappear, and "pinning" notifications appear in the chat
<b>Description:</b>
If a user pins a message, then when trying to close the pinned messages banner (the "cross" icon), notifications about that messages is pinned/unpinned will appear in the chat every time you click that the message. After a random number of times, the banner disappears
<b>Steps:</b>
1. Pin a message in any chat
2. Click the "cross" icon on the pinned messages banner
<b>Actual result:</b>

The banner has not closed, notifications about pinning/unpinning appears
<b>Expected result:</b>
The banner was closed, message was unpinned
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Sometimes
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/jf4beFv_kwBzQA">https://disk.yandex.ru/i/jf4beFv_kwBzQA</a>
<b>ID: R_ABR-9</b>
<b>Summary:</b>
Chat scrolling continues when you click on the pinned messages banner
<b>Description:</b>
If user press on the pinned messages banner while scrolling the chat, user will get to the message, but the scrolling will continue until it stops
<b>Steps:</b>
1. Scroll through the chat
2. Click on the pinned messages banner while scrolling
<b>Actual result:</b>
Chat scrolling continues when you click on the pinned messages banner
<b>Expected result:</b>
Scrolling stops when clicking on the pinned messages banner
<b>Severity:</b>
Minor
<b>Priority:</b>
Low

<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/Ky6wQkOggj0qGw">https://disk.yandex.ru/i/Ky6wQkOggj0qGw</a>
<b>ID: R_ABR-10</b>
<b>Summary:</b>
File sending button disappears in any chat if you select a file to send, and then send any image from the quick send feed
<b>Description:</b>
If user selects a file to send, and then sends any image from the quick file sending feed, then file sending button disappears and it will not be possible to send it unless user write something in the message field
<b>Steps:</b>
1. In any chat, select a file to send
2. Send any image from the quick send feed
<b>Actual result:</b>
File sending button disappears and user won't be able to send it if don't write something in the message field
<b>Expected result:</b>
The file submission button does not disappear
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/mlNpa-pYGQJClw">https://disk.yandex.ru/i/mlNpa-pYGQJClw</a>



<b>ID: R_ABR-11</b>
<b>Summary:</b>
In the "username" field, user can enter characters not only in one line, but also from a new line
<b>Description:</b>
In the "username" field of the profile, user can enter characters from a new line, as a result, when displaying actions in chats, participants see large notifications, and the field itself on the profile page takes up a lot of space
<b>Steps:</b>
1. Open the "Username" edit field on the profile page
2. Нажать кнопку добавления новой строки на клавиатуре
<b>Actual result:</b>
The user can enter characters from a new line
<b>Expected result:</b>
Characters can only be entered in one line
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/MpSkSCPbjYoF3w">https://disk.yandex.ru/i/MpSkSCPbjYoF3w</a> , <a href="https://disk.yandex.ru/i/6ST3D7j4fGGUJA">https://disk.yandex.ru/i/6ST3D7j4fGGUJA</a>
<b>ID: R_ABR-12</b>
<b>Summary:</b>
The "Username" field in the profile accepts even one character (must be at least five)
<b>Description:</b>
In the "Username" field in the profile, user can enter any one character and set it as a nickname, although the minimum number of characters is five
<b>Steps:</b>

1. Open the "Username" edit field on the profile page
2. Enter any one character and save it
<b>Actual result:</b>
The "Username" field in the profile accepts even one character
<b>Expected result:</b>
Notification is displayed that an invalid name has been entered + it is indicated what exactly the error is
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/182a_w2x2en-eA">https://disk.yandex.ru/i/182a_w2x2en-eA</a>
<b>ID: R_ABR-13</b>
<b>Summary:</b>
In the "User ID" field of the profile, the first character must be a letter, but there is no hint about this in the description of the field
<b>Description:</b>
When entering "User ID" in the profile, there is no hint that the letter should be the first, not the number
<b>Steps:</b>
1. Open the edit field "User ID" on the profile page
2. Enter the correct ID starting with a number
<b>Actual result:</b>
There is no hint that the letter should be the first
<b>Expected result:</b>
There are hints that the letter should be the first
<b>Severity:</b>

Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/KJjn_98eYVfhYw">https://disk.yandex.ru/i/KJjn_98eYVfhYw</a>
<b>ID: R_ABR-14</b>
<b>Summary:</b>
In the "Email" field of the profile, user can enter anything
<b>Description:</b>
In the "Profile" section, user can enter anything in the "Email" field, because there is no notification of incorrect input + there is no hint for input
<b>Steps:</b>
1. Open the "Email" edit field on the profile page
2. Enter any data and save
<b>Actual result:</b>
In the "Email" field of the profile, user can enter anything
<b>Expected result:</b>
There is a hint on how to fill in the field correctly + there is a notification about incorrect input
<b>Severity:</b>
Minor
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12

<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/WvLKBaPkQ0POzA">https://disk.yandex.ru/i/WvLKBaPkQ0POzA</a>
<b>ID: R_ABR-15</b>
<b>Summary:</b>
The pinned message counter may not change after pinning 2 or more messages in a row in any chat
<b>Description:</b>
After pinning a message in any chat, the pinned message counter may not change until the chat is closed or a new message is pinned.
<b>Steps:</b>
1. Pin or unpin 2 or more messages in a row
<b>Actual result:</b>
The message counter may not change when pinning/unpinning 2 or more messages in a row
<b>Expected result:</b>
The counter changed when pinning/unpinning 2 or more messages in a row
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Sometimes
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/xj6N-shn7vudEQ">https://disk.yandex.ru/i/xj6N-shn7vudEQ</a>
<b>ID: R_ABR-16</b>
<b>Summary:</b>
In the "Privacy and security" settings, there is a space between the list of "permissions" and "system settings"
<b>Description:</b>
There is a space between the list of "permissions" and "system settings"

<b>Steps:</b>
1. Open the settings in the profile section
2. Open the "Privacy and security" item
3. Open the "Permissions" item
<b>Actual result:</b>
There is a space
<b>Expected result:</b>
There is no space
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/CCKsffvISl8WVg">https://disk.yandex.ru/i/CCKsffvISl8WVg</a>
<b>ID: R_ABR-17</b>
<b>Summary:</b>
When creating a community or channel, when entering incorrect data, the notification "Enter at least 4 characters" is displayed as many times as the button was pressed
<b>Description:</b>
If the fields are filled in incorrectly when creating a community or channel, then when the "Done" button is pressed repeatedly, the notification is displayed as many times as the button was pressed, even if the user went to another page
<b>Steps:</b>
1. Start creating a new community/channel
2. Select any participant and click "Next"
3. Enter an incomplete number of characters in all fields (incorrect data) and press the "Done" button repeatedly

<b>Actual result:</b>
The "Enter at least 4 characters" notification is displayed as many times as the button has been pressed
<b>Expected result:</b>
The notification "Enter at least 4 characters" is displayed once, and the rest of the clicks begin to be counted only after the notification animation is completed
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/39IHqJK2k5CFbg">https://disk.yandex.ru/i/39IHqJK2k5CFbg</a>
<b>ID: R_ABR-18</b>
<b>Summary:</b>
After opening the search field, the "cross" icon does not appear to cancel the search in any type of chat and in the chat list (section "chats") until the characters are entered
<b>Description:</b>
When the user opens the search field, the "cross" icon does not appear to cancel the call in any type of chat and in the chat list (section "chats"), in view of this, the search field can only be closed by pressing the "back" button on the device
<b>Steps:</b>
1. Open the search field in any chat or in the chat list (section "chats")
<b>Actual result:</b>
After opening the search field, the "cross" icon does not appear to cancel the search in any type of chat and in the chat list (section "chats")
<b>Expected result:</b>
There is a button to cancel the search (the "cross" icon) and allows user to close the search field
<b>Severity:</b>
Minor

<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/KRJY0aKh7alulQ">https://disk.yandex.ru/i/KRJY0aKh7alulQ</a>
<b>ID: R_ABR-19</b>
<b>Summary:</b>
It is not possible to change the name of the custom folder after creation
<b>Description:</b>
The user cannot change the name of the custom folder. When yuser enter any data, a notification is displayed that a folder with the same name already exists
<b>Steps:</b>
1. In the manage folders section, create any folder
2. Edit folder name and enter any data
3. Click the "check mark" icon button
<b>Actual result:</b>
It is not possible to change the name of the custom folder after creation
<b>Expected result:</b>
The new folder name is saved if there is no folder with the same name
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Always
<b>Environment:</b>

Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/OL9JtEOOpD3DAQ">https://disk.yandex.ru/i/OL9JtEOOpD3DAQ</a>
<b>ID: R_ABR-20</b>
<b>Summary:</b>
A message input field is available while recording a voice message in any chat
<b>Description:</b>
The user can use the message input field while recording a voice message in any chat, although the interface for entering the message is hidden
<b>Steps:</b>
1. Start recording a voice message
2. While recording a voice message, click on the place where the message input field is usually located
<b>Actual result:</b>
A message input field is available while recording a voice message in any chat
<b>Expected result:</b>
The text message interface is not available while recording voice messages
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/KbxicpAHwdr5aw">https://disk.yandex.ru/i/KbxicpAHwdr5aw</a>
<b>ID: R_ABR-21</b>
<b>Summary:</b>
The "Reset all chat settings" function in the notification settings does not work
<b>Description:</b>



If user changes the notification settings and then press reset button, a notification will appear that settings have been reset, but in fact settings will remain the same
<b>Steps:</b>
1. In the notification settings, change any settings
2. Press on "Reset all chat settings" button
<b>Actual result:</b>
The settings remain the same
<b>Expected result:</b>
Settings reset
<b>Severity:</b>
Medium
<b>Priority:</b>
Normal
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/t7q--7VcRzGyRA">https://disk.yandex.ru/i/t7q--7VcRzGyRA</a>
<b>ID: R_ABR-22</b>
<b>Summary:</b>
Quick tap on the "Microphone" icon opens the interface for recording a voice message, but recording does not start
<b>Description:</b>
When user makes a short press on the "Microphone" icon, some elements of the voice message recording interface appear, but the recording does not start
<b>Steps:</b>
1. Make a quick tap on the "Microphone" icon in any chat
<b>Actual result:</b>
Quick tap on the "Microphone" icon opens the interface for recording a voice message
<b>Expected result:</b>

Voice message recording interface elements are not displayed with a short press
<b>Severity:</b>
Minor
<b>Priority:</b>
Low
<b>Reproducible:</b>
Sometimes
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/PJbx1ZsWslgt6Q">https://disk.yandex.ru/i/PJbx1ZsWslgt6Q</a>
<b>ID: R_ABR-23</b>
<b>Summary:</b>
The text can be saved as a registration PIN if user insert the previously copied text (letters) in the "Block registration" field in the "Privacy and Security" section
<b>Description:</b>
If user copies text in advance, and then, when specifying the PIN code in the "Privacy and security" section, inserts it into PIN code entry field "Lock registration", then PIN code can be saved (although only numeric input is provided, because the pad opens to enter the PIN code)
<b>Steps:</b>
1. Copy any text in advance
2. Open the "Privacy and security" settings
3. Switch the toggle switch in the "Lock registration" field
4. Paste copied text and save
<b>Actual result:</b>
The text can be saved as a registration PIN if user insert the previously copied text (letters) in the "Block registration" field in the "Privacy and Security" section
<b>Expected result:</b>
You cannot insert text (letters) in the PIN code field
<b>Severity:</b>
Minor

<b>Priority:</b>
High
<b>Reproducible:</b>
Always
<b>Environment:</b>
Ringl v1.7.0 (5308), Samsung Galaxy Note 20 Ultra SM-N985F/DS, Android 12
<b>Attachments:</b>
<a href="https://disk.yandex.ru/i/kmREhros4OI2Ug">https://disk.yandex.ru/i/kmREhros4OI2Ug</a>