

Project Details | Functionalities and Features

- 1) When a user/visitor visits the token sale page. It'll ask/pop-up for wallet connection.
- 2) When a user/visitor clicks on connect wallet button. It'll ask/pop-up for wallet connection.
- 3) Admin can add/change URL link to **Logo & Home button**. Example: <https://example.com>
- 4) Admin can add/change URLs link of social media of Telegram, Twitter, Instagram, Facebook, White Paper, Security Audit, and Token explorer (BSC Scan link).
 - If admin left empty any of above social media link. Then the social media with an empty link will not be displayed.
- 5) Admin can add/change description (Min 300 - Max 600 characters).
- 6) All the below details will be fetched from the token contract address:
 - Token Name
 - Token Symbol
 - Token Decimal
 - Token Total Supply
- 7) Admin can add/change **SoftCap & HardCap**.
- 8) Admin can add/change the details of how many tokens he/she wants to sell.
 - Example: if the total supply is **1000** and the admin offered to sell **500** tokens, then the percentage of offered tokens and quantity will be displayed.
- 9) Token price will be determined by using the below formula:
 - Offered Tokens / HardCap = Tokens per BNB.
 - Example: if offered tokens quantity is 1000 and hard cap is 50. The $1000 / 50 = 20$ token per BNB.
 - 1 BNB = 20 tokens.
- 10) Admin can add/change minimum, and maximum buying limit.
 - A minimum and maximum BNB user/holder invest to buy tokens.
 - If the minimum or maximum buying limit is set to 0. Then min & max buying fields will be not displayed at the front-end. Also, the user/holder can invest any amount he/she wants to.
- 11) Admin can add/change ICO's starting and ending date & time.
 - Date should be in "**01 Jan 2022**" format, and time should be in "**24 Hours**" format.
 - If the date and time are set beyond the current date and time. Then it'll be displayed as "**Starts In**" with the upcoming countdown. When the time hits the settled date and time, the sale will be live and the sale countdown will be started "**Starts in**" will be changed to "**Live**".
- 12) Admin can add/change "**Stage Name**"
- 13) Raised funds "**BNBs**" will be displayed in the **fund-raised progress range bar pop-up** with the **percentage**.
- 14) When the user/holder clicks on "**Max**" in the input field, All the BNBs will be added to the input field except the gas fee.
 - If the user hasn't connected the wallet yet. It'll ask/pop-up for wallet connection, and the above function will run.
- 15) When a user/holder enters any value (BNBs) in the input field, accordingly the token quantity will be displayed to them below the input field.
 - If the user/holder enters a value lower than "**minimum buying limit**" or higher than "**maximum buying limit**". Accordingly, the message will be displayed below the input field and buying button will be disabled.
- 16) Tokens will be distributed to the same wallet address from which purchased.
 - User/holders can buy tokens by sending their BNBs directly to the pre-sale contract address.
 - If the user/holder transferred BNBs don't meet the min/max limit. Tokens will not be transferred to the same wallet address.
- 17) Funding Allocation:
 - Admin can add/change "n" number of funding allocation with (**Name, Percentage, Color**)
 - The raised funds will be displayed according to the percentage in the allocated fund's list.
- 18) Disqus comment section:
 - Integrate the Disqus comment bar.