

## Request and response of the API

In the below table given,

1. API: Is the API to use for the respective modules mentioned.
2. Method : Is the HTTP method used when making a request to the server.
3. Request : Is the request parameter to send while making a request to server.
4. Response: Is the response from the server, only the code is received e.g. **0**, **00**, **01** etc. the meaning is given along with the code in the table.

### Brief note about the API:

1. **forgot\_code.php**: is for both forgot\_in and forgot\_password. To make use or to send request, send the module in request parameter with key as “module” and value as either forgot\_in or forgot\_password.

API	<a href="http://stage1.optipacotech.com/badminton/megha/forgot_code.php">http://stage1.optipacotech.com/badminton/megha/forgot_code.php</a>	
Method	Post	
Request	mail_id, module	
Response	<b>Code</b>	<b>Meaning</b>
	00	Invalid parameters
	01	Database connectivity error
	02	Database execution error
	0	Successful

2. **confirm\_otp.php**: To validate the OTP sent to the mail id.

API	<a href="http://stage1.optipacotech.com/badminton/megha/confirm_otp.php">http://stage1.optipacotech.com/badminton/megha/confirm_otp.php</a>	
Method	Post	
Request	mail_id, otp	
Response	<b>Code</b>	<b>Meaning</b>
	00	Invalid parameters
	01	Database connectivity error
	02	Database execution error
	03	Unsuccessful or OTP didn't match
	0	successful

3. reset.php: to reset both pin and password.

API	<a href="http://stage1.optipacetechn.com/badminton/megha/reset.php">http://stage1.optipacetechn.com/badminton/megha/reset.php</a>										
Method	Post										
Request	mail_id, new_password,module(pin_reset or password_reset)										
Response	<table><thead><tr><th>Code</th><th>Meaning</th></tr></thead><tbody><tr><td>00</td><td>Invalid parameters</td></tr><tr><td>01</td><td>Database connectivity error</td></tr><tr><td>02</td><td>Database execution error</td></tr><tr><td>0</td><td>successful</td></tr></tbody></table>	Code	Meaning	00	Invalid parameters	01	Database connectivity error	02	Database execution error	0	successful
Code	Meaning										
00	Invalid parameters										
01	Database connectivity error										
02	Database execution error										
0	successful										