

1、下载

2、配置

2.1 配置mongo.conf

2.2 创建dbpath和logpath

2.3 配置环境

2.4 启动命令配置start.sh

2.5 停止命令配置stop.sh

3 启动|停止

3.1 启动

3.2 停止

3.3 连接

本机命令连接

客户端工具

1、下载

```
# 下载
wget https://fastdl.mongodb.org/linux/mongodb-linux-x86_64-4.0.24.tgz
# 新建目录
mkdir -p /usr/local/mongodb/
# 解压
tar -zxvf mongodb-linux-x86_64-4.0.24.tgz -C /usr/local/mongodb/
```

2、配置

• 2.1 配置mongo.conf

```
vim /etc/mongo.conf
```

```
# mongo.conf文件内容
dbpath = /var/lib/mongo/
port = 27017
fork = true
#auth = true
logpath = /var/log/mongo/mongo.log
logappend = true
bind_ip = 0.0.0.0
```

• 2.2 创建dbpath和logpath

```
mkdir -p /var/lib/mongo/
mkdir -p /var/log/mongo/
```

• 2.3 配置环境

将下述内容写入到/etc/profile

```
vim /etc/profile
```

```
export PATH=/usr/local/mongodb/mongodb-linux-x86_64-4.0.24/bin:$PATH
```

```
source /etc/profile
```

• 2.4 启动命令配置start.sh

```
#!/bin/bash

mongod -f /etc/mongo.conf
```

- 2.5 停止命令配置stop.sh

```
#!/bin/bash
```

```
mongod -f /etc/mongo.conf --shutdown
```

```
chmod 777 start.sh
```

```
chmod 777 stop.sh
```

3 启动|停止

- 3.1 启动

```
./start.sh
```

```
tail -f /var/log/mongo/mongo.log
```

- 3.2 停止

```
./stop.sh
```

- 3.3 连接

- 本机命令连接

```
[root]# mongo
MongoDB shell version v4.0.24
connecting to: mongodb://127.0.0.1:27017/?gssapiServiceName=mongodb
Implicit session: session { "id" : UUID("689ba2b6-2165-4c1c-a12d-6635f13d36fb") }
MongoDB server version: 4.0.24
Welcome to the MongoDB shell.
For interactive help, type "help".
For more comprehensive documentation, see
    http://docs.mongodb.org/
Questions? Try the support group
    http://groups.google.com/group/mongodb-user
Server has startup warnings:
```

```
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten]
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] ** WARNING: Access control is
not enabled for the database.
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] **          Read and write
access to data and configuration is unrestricted.
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] ** WARNING: You are running
this process as the root user, which is not recommended.
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten]
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten]
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] ** WARNING:
/sys/kernel/mm/transparent_hugepage/enabled is 'always'.
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] **          We suggest setting it
to 'never'
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten]
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] ** WARNING:
/sys/kernel/mm/transparent_hugepage/defrag is 'always'.
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten] **          We suggest setting it
to 'never'
2021-06-02T04:12:17.903-0400 I CONTROL [initandlisten]
> version()
4.0.24
>
```

- 客户端工具

也可以用mongodb客户端工具进行连接，常见的工具有：Dbeaver Enterprise、Navicat Premium、Studio 3T、Robo 3T（以前叫robomongo）。