


# 3步开始使用cdn加速服务

## step1. 注册账号并登陆

进入meson.network官网 <https://meson.network>


注册成为 cdn 用户



注意勾选 cdn 用户

## step2. 创建资源加速链接

进入后台管理页面的 Client=>BindDomain 页面,



## 创建资源加速链接

#####Tutorial on how to accelerate your file #####  
for example you want a file to be accelerated :  
`https://yourdomain.com/static/testfiles/t1.jpg`  
1.you can input yourdomain.com into [add your location] then click [Check input url]  
2.if no error then click [Add Record]  
after step 2 you will have a new record [in bottom table] with a cdn url like 'coldcdn.com/api/cdn/r7JEqR'  
3.now you can simply replace the old url and get a new url:  
`https://coldcdn.com/api/cdn/r7JEqR/static/testfiles/t1.jpg`  
now request this new url and meson needs some time to deploy the file on distributed terminals globally  
anyone can request the new url which is accelerated by meson.net globally

add your location

`www.mydomain/static/img`

For http acceleration in your own application replace your location url to :

`http://coldcdn.com/api/cdn/5u58qm`

For https acceleration in your own application replace your location url to

`https://coldcdn.com/api/cdn/5u58qm`

Check Input Url

Note

simply replace your url with our url in your application,all your files will be accerlated e.g : `https://www.mydomain/static/img/*` will become `https://coldcdn.com/api/cdn/5u58qm/*`

在红色框中填写您网站静态资源的链接,例如您想给您网站中所有的图片资源加速,如果您的图片都存储在您网站根目录 /static/img 目录下,您就可以在这里填写您网站的域名+目录,比如 `www.yourdomain.com/static/img`

点击 Check Input Url

如果验证无误,按钮会变成绿色,点击 Add Record

add your location

www.mydomain/static/img

For http accerlation in your own application replace your location url to :

http://coldcdn.com/api/cdn/5u58qm

For https accerlation in your own application replace your location url to

https://coldcdn.com/api/cdn/5u58qm

Add Record

Note

simply replace your url with our url in your application,all your files will be accerlated e.g : [https://www.mydomain/static/img/\\*](https://www.mydomain/static/img/*) will become [https://coldcdn.com/api/cdn/5u58qm/\\*](https://coldcdn.com/api/cdn/5u58qm/*)

创建成功后,会在下面下方显示您创建的加速链接

id	state	active region	user url	cdn url	Action	settings
50	ON	<div>Asia Africa</div> <div>South America Oceania</div> <div>North America Europe</div> <div>Other</div>	www.mydomain/static/img	coldcdn.com/api/cdn/5u58qm	<div>Refresh</div> <div>Delete</div>	<div>settings</div>

step3. 替换网页中原静态资源链接为加速链接

替换资源链接

```
<!DOCTYPE html>
<html lang="en">
<head>
  <meta charset="UTF-8">
  <meta name="viewport" content="width=device-width, initial-scale=1.0">
  <title>Document</title>
</head>
<body>
  
  
</body>
</html>
```

将您需要加速的资源链接,替换为上一步中您生成的链接,如上图中,将红色框的内容,替换为新的链接 如果您的网页支持https,请使用 https://, 如果不支持,那就请使用 http://