


装服务器的 14:31:33

进 r510i 的界面发给我看看


du 14:31:51

好的，稍等

du 14:33:13



du 14:33:41




装服务器的 14:33:44

选择第一个

装服务器的 14:33:57

第一个

du 14:35:13



du 14:35:48

接着选择第一个么？

装服务器的 14:35:55

是的，第一个

du 14:36:26

Aptio Setup Utility - Copyright

- ▶ Save Configuration
- Select RAID Level
- Select Drives From
- ▶ Select Drives

[RAID0]  
[Uncon]

CONFIGURE VIRTUAL DRIVE PARAMETERS:

Virtual Drive Name  
Virtual Drive Size  
Virtual Drive Size Unit  
Strip Size  
Read Policy  
Write Policy  
I/O Policy  
Access Policy  
Drive Cache

0  
[GB]  
[64 KB]  
[No Re]  
[Write]  
[Direc]  
[Read]  
[Uncha]  
[No]

Initialization

装服务器的 14:36:57  
再选择 select dirvers  
装服务器的 14:37:02  
select drivers  
du 14:37:25

装服务器的 14:37:48  
就一个块盘吧，  
du 14:37:53



303

Aptio Setup Utility - Copyright (C) 2015 American

► Apply Changes

Select Media Type [HDD]  
Select Interface Type [Both]  
Logical Sector Size [Both]

CHOOSE UNCONFIGURED DRIVES:

Drive Port 0 - 3:00:00: SATA, [Disabled]  
931GB, Unconfigured Good, (512B)

Check All

Uncheck All

► Apply Changes

Version 2.17.1245. Copyright (C) 2015 American M

lenovo

du 14:38:00

就一块

装服务器的 14:38:26

把 disabled 还有 enabled

装服务器的 14:38:46

再 apply changes 一下，

装服务器的 14:39:04

把 disabled 改为 enabled

du 14:39:09

Aptio Setup Utility -

► Save Configuration

Select RAID Level

Select Drives From

► Select Drives

CONFIGURE VIRTUAL DRIVE PARAMETERS:

Virtual Drive Name

Virtual Drive Size

Virtual Drive Size Unit

Strip Size

Read Policy

Write Policy

I/O Policy

Access Policy



装服务器的 14:39:14  
再 apply changes 一下，  
du 14:39:22  
改好了  
装服务器的 14:39:25  
save configuration  
du 14:40:13

ThinkVision

## Aptio Setup Utility

Virtual Drive creation was  
successful. All free configurable  
space has been used.

装服务器的 14:40:26

回到主界面，

du 14:40:53

## Aptio Setup Utility -

- ▶ Create Virtual Drive
- ▶ Create Profile Based Virtual Drive
- ▶ Make JBOD
- ▶ Clear Configuration



装服务器的 14:40:57

把这个虚磁盘，初始化一下就能安装系统了，

du 14:41:31

怎么初始化？

装服务器的 14:41:57

回到主界面，

du 14:42:18

303

ThinkVision

## Aptio Setup Utility - Cop

- ▶ Configuration Management
- ▶ Controller Management
- ▶ Virtual Drive Management
- ▶ Drive Management
- ▶ Hardware Components



du 14:42:39

是这个主界面么？

装服务器的 14:42:40

virtual driver management

du 14:43:10

Aptio Setup Utility - Copyright

Operation [Sel]

BASIC PROPERTIES:

Name

Raid Level [RAI]

Status [Opt]

Size 931

▶ View Associated Drives

▶ Advanced...





装服务器的 14:43:27

选择第一个，

du 14:44:32

303

# Aptio Setup Utility - Copyright

## Operation

[Select

### BASIC PROPERTIES:

Name

Raid Level

[RAID0]

Status

[Optima

Size

931 GB

- ▶ View Associated Drives
- ▶ Advanced...



- Op
- Select oper
- Start Loca
- Stop Locat
- Delete Vir
- Reconfigur
- Fast Initia
- Slow Initia

du 14:44:42

是这个么？

装服务器的 14:44:49

fast initization

装服务器的 14:45:05


下面，再 go 一下就行了，

du 14:45:11

ThinkVision

Aptio Setup Utility - C

Operation



Go


BASIC PROPERTIES:

Name


Raid Level

Status

Size



View Associated Drives



Advanced...





du 14:45:46

Aptio Setup Utility - Copyright

Operation

Progress

[Select]

Initial

▶ Stop

BASIC PROPERTIES:

Name

Raid Level

[RAID0]

Status

[Optima]

Size

931 GB

▶ View Associated Drives

▶ Advanced...



陈冈 14:46:07

go 一下就行了，装系统，开机 f10 进去部署安装，

du 14:47:01

好的