



1. Complete Information About your Phone

##4636##

This code can be used to get some interesting information about your phone and battery.

Usage statistics

2. Factory data reset

##7780##

This code can be used for a factory data reset. It'll remove following things:

Google account settings stored in your phone

System and application data and settings

Downloaded applications

It'll NOT remove:

Current system software and bundled application

SD card files e.g. photos, music files, etc.

Note: Once you give this code, you get a prompt screen asking you to click on "Reset phone" button. So you get a chance to cancel your operation.

3. Format Android Phone

***2767*3855#**

Think before you give this code. This code is used for factory format. It'll remove all files and settings including the internal memory storage. It'll also reinstall the phone firmware.

Note: Once you give this code, there is no way to cancel the operation unless you remove the battery from the phone. So think twice before giving this code.

4. Phone Camera Update

##34971539##

This code is used to get information about phone camera. It shows following 4 menus:

Update camera firmware in image (Don't try this option)

Update camera firmware in SD card

Get camera firmware version

Get firmware update count

WARNING: Never use the first option otherwise your phone camera will stop working and you'll need to take your phone to service center to reinstall camera firmware.

5. End Call/Power

##7594##

This one is my favorite one. This code can be used to change the "End Call / Power" button action in your phone. By default, if you long press the button, it shows a screen asking you to select any option from Silent mode, AirPlane mode and Power off.

You can change this action using this code. You can enable direct power off on this button so you don't need to waste your time in selecting the option.

6. File Copy for Creating Backup

##273283*255*663282*##

This code opens a File copy screen where you can backup your media files e.g. Images, Sound, Video and Voice memo.

7. Service Mode

##197328640##

This code can be used to enter into Service mode. You can run various tests and change settings in the service mode.

8. WLAN, GPS and Bluetooth Test Codes:

##232339## OR ***##526##*** OR ***##528##*** - WLAN test (Use "Menu" button to start various tests)

232338 - Shows WiFi MAC address

1472365 - GPS test

1575 - Another GPS test

232331 - Bluetooth test

232337 - Shows Bluetooth device address

9. Codes to get Firmware version information:

4986*2650468 - PDA, Phone, H/W, RFCallDate

1234 - PDA and Phone

1111 - FTA SW Version

2222 - FTA HW Version

44336 - PDA, Phone, CSC, Build Time, Changelist number

10. Codes to launch various Factory Tests:

0283 - Packet Loopback

0 - LCD test

0673 OR ***0289*** - Melody test

0842 - Device test (Vibration test and BackLight test)

2663 - Touch screen version

2664 - Touch screen test

0588 - Proximity sensor test

3264 - RAM version