

MK Glow Lite

If possible, always use a **Linear Color Space, Color Grading and HDR** to get the **best** results.



Contents

1.0 Setup / Install	1
1.1 Legacy Image Effects	1
1.2 Post Processing Stack V2 and LWRP	1
1.3 URP	1
1.0 Setup Workflow	2
1.1 Threshold	2
1.2 Selective	2
2.0 Debugging	3
3.0 Setup Workflow	4
3.1 Threshold	4
3.2 Selective	4
4.0 FAQ	5
5.0 Feedback / Get in touch	6

1.0 Setup / Install

Right after the import the Install Wizard should open ("*Window/MK/Glow Lite/Install Wizard*").

1. Choose your Render Pipeline (Built-in_Legacy, Built-in_PPSV2, LWRP, URP).
2. Click the Import Package button.

The basic setup should be complete.

1.1 Legacy Image Effects

1. Attach the MK Glow Lite component to your rendering camera

1.2 Post Processing Stack V2 and LWRP

1. On your Post Processing Stack V2 Profile add the "MK/MKGlowLite" component

1.3 URP

1. On your Universal Render Pipeline Renderer Asset add the custom Renderer Feature: MK Glow Lite Renderer Feature
2. On your Volume Component add the Glow Component via "Post-processing/MK/MKGlowLite"

1.0 Setup Workflow

1.1 Threshold

The Threshold Workflow is based on the brightness of the pixels and a threshold value.

1. **Setup your threshold.** The left part of the threshold slider defines your color cutoff, while the right part defines your maximum brightness of the resulting glow. Threshold values are represented in the gamma space.
2. **Adjust the Emission.** You can simply raise the emission on your materials to make them glow.

1.2 Selective

The Selective Workflow allows you to apply a glow effect per object. This workflow is based on Unity's Replacement Rendering feature (not available in custom render pipelines (LWRP, HD)).

1. **Set your Render Layer.** Controls which layers are redrawn by the Replacement Rendering feature. The recommended setting for the selective Render Layer is *"Everything"* to avoid Z-Issues.
2. **Apply a *"MK/Glow/Selective/"* shader** to the material that is supposed to glow. All shader features are using the exact same raw glow map. The raw glow map can be viewed, by setting the debug view to *"raw"*.
3. **Adjust your glowing material.** Add a glow texture to define which parts should glow and setup the material as you wish.

2.0 Debugging

For debugging you have the DebugView option on the inspector. You can inspect every rendering step which is done while rendering.

None:	Normal rendering is done
Raw Bloom:	Shows the parts, which are glowing
Bloom:	Shows the finished result of the bloom rendering step
Composite:	Shows the combined final result

3.0 Setup Workflow

3.1 Threshold

The Threshold Workflow is based on the brightness of the pixels and a threshold value.

1. **Setup your threshold.** The left part of the threshold slider defines your color cutoff, while the right part defines your maximum brightness of the resulting glow. Threshold values are represented in the gamma space.
2. **Adjust the Emission.** You can simply raise the emission on your materials to make them glow.

3.2 Selective

The Selective Workflow allows you to apply a glow effect per object. This workflow is based on Unity's Replacement Rendering feature (not available in custom render pipelines).

1. **Set your Render Layer.** Controls which layers are redrawn by the Replacement Rendering feature. The recommended setting for the selective Render Layer is *"Everything"* to avoid Z-Issues.
2. **Apply a *"MK/Glow/Selective/"* shader** to the material that is supposed to glow. All shader features are using the exact same raw glow map. The raw glow map can be viewed, by setting the debug view to *"raw"*.
3. Adjust your glowing material. Add a glow texture to define which parts should glow and setup the material as you wish.

4.0 FAQ

Q: MK/Glow/Selective/Standard Shader is not visible or throwing a MetaPass Error

A: Fix: Right Click on the “_MK/Glow/Shaders/VariantsSelective” folder and select “reimport”

Q: Selective Workflow doesn't work when using a Custom Render Pipeline

A: Currently it's impossible to use the Selective Workflow on custom render pipelines. The Replacement rendering feature, which is required for the selective workflow seems to not get called on SRPs.

Q: When using Post-processing Stack v2 the mk glow component doesn't appear in the editor

A: Add the “UNITY_POST_PROCESSING_STACK_V2” to your Scripting Defined Symbols under Player Settings

Q: How to make Screen Spaced UI glow

A: In order to make Screen Spaced UI work, your Render Mode of the Canvas has to be set to “Screen Space - Camera”, otherwise no Post-processing is applied to Screen Spaced Elements.

5.0 Feedback / Get in touch

Do you have some cool stuff to show?

I would love to see your results (High resolution screenshots / videos) using the shader!

Questions, bug reports, feature requests, feedback:

Feel free to get in touch via support@michaelkremmel.de.