



[Hyva Banner Slider](#)

FEATURES

- **Multiple Slides :** Allow users to create and display multiple slides within the slider. Each slide should have its own image, text, link, and other customizable content.
- **Image and Video Support:** Enable users to use both images and videos as slide content. Videos could autoplay.
- **Slider Scheduling:** Implement scheduling options to automatically display and hide slides based on specified start and end dates. This is useful for running limited-time promotions.
- **Navigation Arrows and Pagination:** Include navigation arrows and pagination dots for users to manually navigate through slides.
- **Auto-play:** Allow users to enable or disable auto-play of the slider, along with options to control the auto-play interval.
- **Pause on Hover:** Include an option to pause auto-play when users hover over the slider to allow for easier interaction.
- **Slider Background Options:** Allow users to choose a background color or image for the slider area.
- **Integration with Magento CMS:** Ensure seamless integration with the Magento 2 CMS, allowing users to easily add the slider to CMS pages and blocks.
- **Multi-store Support:** Provide support for multi-store setups in Magento, allowing different sliders to be configured for different store views.
- **Caption Animation Effects:** Provide a variety of animation effects for captions, such as bounce, bounce-in-down, shake, or custom CSS animations. Users should be able to choose from these effects when creating or editing banners.

Ultimate Guide for Magento 2 Banner Slider

The Magento 2 Banner Slider Extension is a powerful tool for enhancing the visual appeal and effectiveness of your online store. This extension allows you to effortlessly create and manage banner sliders to showcase promotions, products, or any other content you wish to highlight on your Magento 2 store. In this ultimate guide, we will explore the key features and functionalities of the Banner Slider Extension, helping you make the most of this valuable tool.

- **Enhance Visual Appeal:** Capture your customers' attention with captivating banner sliders that showcase your promotions, products, and brand in an eye-catching way.
- **Flexible Display:** Display your banner sliders across various strategic locations on your Magento 2 store front end, such as the homepage, category pages, product pages, and more.
- **Clickable Banners:** Direct your customers to specific product pages, categories, or external URLs when they click on the banners, turning engagement into conversions.
- **Scheduling Power:** Plan your promotions in advance by scheduling banner displays with start and end dates, ensuring timely promotion execution.

- Management: Effortlessly manage your banners by editing, reordering them as needed through the backend grid.
-

How to install the extension

1. Install via composer (recommend)

- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **composer require mageinic/hyva-banner-slider**
- Run the command **php bin/magento module:enable MageINIC_Core Hyva_MageINICBannerSlider**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

1. Upload via ZIP/Archive

- Back up your store's database and web directory
- Download the extension zip file and extract the zip file
- Transfer the **MageINIC** folder to the Magento 2 **app/code/** directory on the server
- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **php bin/magento module:enable MageINIC_Core Hyva_MageINICBannerSlider**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

Extension Configuration

To configure the extension configuration, Please go to **Stores** → **Settings** → **Configuration** → **MagelNIC** → **Banner Slider**

General

MagelNIC Banner Slider

Manage Banners → Manage Banner

Manage Sliders → Manage Slider

Configuration → Manage Banner Slider Configuration

Reload Data

Go to Advanced Reporting

Items	Total
1	\$34.00
1	\$34.00
1	\$49.00
1	\$0.00
1	\$29.00

Configuration

Scope: Default Config

Save Config

GENERAL

CATALOG

SECURITY

CUSTOMERS

SALES

HYVA THEMES

SERVICES

MAGEINIC

Banner Slider

ADVANCED

Enable Disable for Extension

Enable (store view)

No

Enable On Frontend

General

The screenshot shows the Magento 2 Configuration interface. On the left is a sidebar with navigation links: DASHBOARD, MAGENIC, SALES, CATALOG, CUSTOMERS, MARKETING, CONTENT, REPORTS, STORES, SYSTEM, and THIRD PARTIES & EXTENSIONS. The main header is 'Configuration' with a search icon, a notification bell, and a user profile 'admin'. Below the header, there's a 'Scope' dropdown set to 'Default Config' and a 'Save Config' button. The left sidebar of the configuration panel lists categories: GENERAL, CATALOG, SECURITY, CUSTOMERS, SALES, HYVA THEMES, SERVICES, MAGENIC (expanded), Banner Slider (selected), and ADVANCED. The main content area is titled 'General' and contains a section 'General configuration for Banner Slider' highlighted with a red border. This section includes three dropdown menus: 'Enable' (set to 'Yes'), 'Enable at Home Page' (set to 'Yes'), and 'Home Slider' (set to '-- Select Slider(s) --'). Below these is a section 'Slider Settings'.

Configuration

Scope: Default Config ?

Save Config

GENERAL

CATALOG

SECURITY

CUSTOMERS

SALES

HYVA THEMES

SERVICES

MAGENIC

Banner Slider

ADVANCED

General

General configuration for Banner Slider

Enable (store view) Yes

Enable On Frontend

Enable at Home Page (store view) Yes

Enable Slider at Home Page

Home Slider (store view) -- Select Slider(s) --

Select Slider To Be Displayed on Home Page

Slider Settings

Enable - Enable/Disable Functionality for Banner Slider Extension. Yes for Enable Extension and No for Disable Extension.

Enable at Home Page - Options to Enable/Disable the Banner Slider for Home Page.

Home Slider - Select Home Slider for which Slider Display on Home Page.

Slider Settings

Failed to synchronize data to the Magento Business Intelligence service. [Retry Synchronization](#) System Messages: 1

Configuration

Scope: Default Config ? Save Config

GENERAL

CATALOG

SECURITY

CUSTOMERS

SALES

HYVA THEMES

SERVICES

MAGEINIC

Banner Slider

ADVANCED

General

Slider Settings

Slider configuration

Choose Background Color (store view) #ffffff Background color

Slider speed (store view) 400

Default Slider to Show (store view) 1

Default Slide to Scroll (store view) 1

Auto play slider (store view) No

Enable infinite looping (store view) Yes

Nav Bar Show (store view) No

Dots for slider (store view) No

Arrows for slider (store view) No

Breakpoints (store view)

Breakpoint	Slides to Show	Slides to Scroll	Dots	Action
1024	1	1	Yes	
992	1	1	Yes	
480	1	1	Yes	

Add Row

Choose Background Color - Choose Background color for Banner Slider

- **Nav Bar Show** - Enable/Disable for Nav Bar Section on bottom of the slider
- **Arrow for slider** - Enable arrow on slider via the Yes/No option
- **Dots for slider** - Enable dots on slider via the Yes/No option
- **Enable infinite looping** - Enable infinite looping on slider via the Yes/No option
- **Autoplay Slider** - Enable autoplay on slider via the Yes/No option
- **Autoplay Slider speed**- Set autoplay slider speed.
- **Default Slides to scroll** - Set banner per slide.
- **Default Slicks to scroll** - Set banner per slick.
- **Slider speed** - Set Slider speed.
- **Breakpoints** - Set Breakpoints to create responsive sliders for different sizes of windows(screens).
 - **Breakpoint** - Set Breakpoint value
 - **Slides to scroll** - Set banner per slide.
 - **Slicks to scroll**- Set banner per slick.
 - **Dots** - Enable dots on the slider via the Yes/No option

Extension Usage

Manage Banners

Please go to **MagelNIC** → **Banner Slider** → **Manage Banners**.

Failed to synchronize data to the Magento Business Intelligence service. [Retry Synchronization](#)

System Messages: 1

Banners

Search

admin

Add New Banner

Search by keyword

Filters

Default View

Columns

Actions

5 records found (1 selected)

20 per page

1 of 1

	ID	Name	Status	Target	Created	Modified	Action	Media Type	Image
<input type="checkbox"/>	1	Special Offer for You..!!	Enabled	New Tab	Aug 18, 2023 7:45:57 AM	Aug 28, 2023 12:32:02 AM	Select	Image	
<input type="checkbox"/>	2	Advance Features	Enabled	Same Tab	Aug 18, 2023 7:58:24 AM	Aug 28, 2023 12:32:27 AM	Select	Video	
<input type="checkbox"/>	3	Sale..!!	Enabled	Same Tab	Aug 20, 2023 11:54:41 PM	Aug 28, 2023 12:34:54 AM	Select	Image	

Copyright © 2023 Magento Commerce Inc. All rights reserved.

Magento ver. 2.4.6
[Privacy Policy](#) | [Report an Issue](#)

Add the Banners From the Backend

Failed to synchronize data to the Magento Business Intelligence service. [Retry Synchronization](#) System Messages: 1

New Banner

← Back Reset Save and Continue Edit **Save Banner**

Enable Banner ☒ Yes Enable/Disable for Banner

Add banner name Banner Name *

Type * ☐ Image Select for media for image or a video

Image
Maximum file size: 4 MB. Allowed file types: JPG, GIF, PNG.

Add Media Alt Media Alt *

Add caption for banner Caption Edit with Page Builder

select for animation for caption Caption Animation Please Select

select position for caption Caption Position Default

set banner link Banner Link *

set target for banner open on same tab or a new tab Target Same Tab

assign banner to the slider Assign to Sliders -- Select Slider(s) --
special offer
Home Page
New One

Drag Row, Columns, Tabs, Block, Dynamic Block or HTML Code here

Copyright © 2023 Magento Commerce Inc. All rights reserved. Magento ver. 2.4.6
[Privacy Policy](#) | [Report an Issue](#)

Please go to **Add New Banner** on the Banner grid page.

- **Enable** - Enable the banner in the slider via the Yes/No option
- **Banner Name** - Add Banner Name.
- **Type** - Set Type for Banner Image or Video.
- **Image** - Upload Banner Image or a Video.
- **Media Alt** - Add Media Alt.
- **Caption** - Add Caption for Banner.
- **Caption Animation** - Set Caption Animation.
- **Caption Position** - Set Caption Position.
- **Banner Link** - Set Banner Link.
- **Target** - Set Target for banners open on same tab or new tab.

- **Assign to Sliders** - Select Slider for assign Banner in Slider.

Manage Sliders

Please go to **MagelNIC** → **Banner Slider** → **Manage Slider**.

Failed to synchronize data to the Magento Business Intelligence service. [Retry Synchronization](#)

System Messages: 1

Sliders

Search

admin

Add New Slider

Search by keyword

Filters

Default View

Columns

Actions

4 records found

20 per page

1 of 1

ID	Title	Store View	Status	Start Date	End Date	Action
1	Home Page	All Store Views	Enabled	Mar 22, 2022 8:48:00 AM	Aug 30, 2035 7:17:00 AM	Select
2	New One	All Store Views	Enabled	Mar 22, 2022 8:48:00 AM	Aug 30, 2035 7:17:00 AM	Select

Copyright © 2023 Magento Commerce Inc. All rights reserved.

Magento ver. 2.4.6
[Privacy Policy](#) | [Report an Issue](#)

Add the Sliders From the Backend

Failed to synchronize data to the Magento Business Intelligence service. [Retry Synchronization](#)

System Messages: 1

New Slider

BackResetSave and Continue EditSave Slider

Enable/Disable Slider → Enable Slider ☒ Yes

Add Slider Title → Slider Title

Set store view → Store View

All Store ViewsMain WebsiteMain Website StorefrenchDefault Store View

Add Default Items to show on slider → Default Items To Show

Start Date Set slider start date

End Date Set slider end date

Captioncaption for sliderEdit with Page Builder

Drag Row, Columns, Tabs, Block, Dynamic Block or HTML Code here

Banners in Slider ← assign banner for slider

SearchReset Filter3 records found20 per page1 of 1

ID	Media	Media Type	Name	Position
1		Image	Special Offer for You..!!	
2		Video	Advance Features	
3		Image	Sale..!!	

Copyright © 2023 Magento Commerce Inc. All rights reserved.


Magento ver. 2.4.6Privacy PolicyReport an Issue

Please go to **Add New Slider** on the Banner grid page.

- **Enable** - Enable the slider in the banner slider via the Yes/No option
- **Slider Name** - Add Slider Name.
- **Store View** - Set Store View.
- **Default Items To Show** - Add Default Items To Show in slider.
- **Start Date** - Set Start Date.
- **End Date** - Set End Date.

- **Banners in Slider** - Assign Banners for slider. You can set banner sort order using banner position in slider.

Add a Slider via Widget form



Widget Options

Select Slider → Select Slider from here using Widget

Background Colour for slider → choose background color for banner slider

Arrow for slider ☐ Yes ☐ No → Display arrows on slider

Dots for slider ☐ Yes ☐ No → Display dots on slider

NavBar Show ☐ Yes ☐ No → Display For NavBar on slider

Infinite looping ☐ Yes ☐ No → set for infinite looping

Autoplay Slider ☐ Yes ☐ No → set for autoplay on slider

set auto play speed → Auto speed


Number of slide to show → Slides to Show

Number of banner to clicks to scroll → Slicks to Scroll

set slider speed → Slider speed

- **Select Slider** -select slider for widget.
- **Background Color for slider** - Choose Background color for slider.
- **Arrow for slider** - Enable arrow on slider via the Yes/No option
- **Dots for slider** - Enable dots on slider via the Yes/No option
- **Infinite looping** - Enable infinite looping on slider via the Yes/No option
- **Autoplay Slider** - Enable autoplay on slider via the Yes/No option
- **Auto speed** - Set autoplay slider speed.
- **Default Slides to scroll** - Set banner per slide.
- **Default Slicks to scroll** - Set banner per slick.
- **Slider speed** - Set Slider speed.
- **Nav Bar** - Set Nav Bar for slider on the bottom.

Banner Slider on Frontend Side



Add Banner Slider Programmatically

Add Banner Slider in layout files.

```
<block class="MageNIC\BannerSlider\Block\Widget\BannerSlider"
    name="mageinic.block_unique_name.slider">
    <action method="setSliderId">
        <argument name="slider_id" xsi:type="string">1</argument>
    </action>
    <action method="setColorOption">
        <argument name="color_option" xsi:type="string">#ffffff</argument>
    </action>
    <action method="setArrowSlider">
        <argument name="arrow_slider" xsi:type="string">1</argument>
    </action>
    <action method="setDotsSlider">
        <argument name="dots_slider" xsi:type="string">1</argument>
    </action>
    <action method="setInfiniteLooping">
        <argument name="infinite_looping" xsi:type="string">1</argument>
    </action>
```

```

        <action method="setAutoPlay">
            <argument name="autoplay" xsi:type="string">1</argument>
        </action>
        <action method="setAutoplaySpeed">
            <argument name="autoplay_speed" xsi:type="string">2000</argument>
        </action>
        <action method="setDefaultSlide">
            <argument name="default_slide" xsi:type="string">3</argument>
        </action>
        <action method="setDefaultSlick">
            <argument name="default_slick" xsi:type="string">1</argument>
        </action>
        <action method="setSliderSpeed">
            <argument name="slider_speed" xsi:type="string">400</argument>
        </action>
    </block>

```

Add Banner Slider in .phtml file

```

<?=
$this->getLayout()->createBlock(\MageNIC\BannerSlider\Block\Widget\BannerSlider::class)
    ->setSliderId("1")->setColorOption("#ffffff")
    ->setArrowSlider("1")->setDotsSlider("1")
    ->setInfiniteLooping("1")->setAutoPlay("1")
    ->setAutoplaySpeed("2000")->setDefaultSlide("3")
    ->setDefaultSlick("1")->setSliderSpeed("400")->toHtml()
?>

```

Add Banner Slider in CMS Page, Block, etc.

```

{{widget type="MageNIC\BannerSlider\Block\Widget\BannerSlider" slider_id="12"
    color_option="#e098e0" arrow_slider="1" dots_slider="1" navbar="1"
    infinite_looping="1" autoplay="1" autoplay_speed="500" default_slide="1"
    default_slick="1" slider_speed="500"}}
slider_speed="500"}}

```

Note

- In cases where the widget attribute is not supplied, the module will retrieve the value from the store configuration.