



[Quick View GraphQL](#)

FEATURES

- The Quick View module offer GraphQL to get store configuration of it.

How to install the extension

1. Install via composer (recommend)

- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **composer require mageinic/quick-view-graphql**
- Run the command **php bin/magento module:enable MagelNIC_Core MagelNIC_QuickViewGraphQL**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

2. Upload via ZIP/Archive

- Back up your store's database and web directory
- Download the extension zip file and extract the zip file
- Transfer the **MagelNIC** folder to the Magento 2 **app/code/** directory on the server
- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **php bin/magento module:enable MagelNIC_Core MagelNIC_QuickViewGraphQL**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

Store Configuration

- Please include the following query in the body section to fetch the module store configuration value.

End Point : `{{baseurl}}/graphql`

{

```

storeConfig {
    quickview_enable,
    quick_view_link_text,
    additional_information,
    show_related_product_block,
    show_upsell_product_block,
    show_checkout_button,
    time_to_close_popup
}
}

```

Response :

```

{
  "data": {
    "storeConfig": {
      "quickview_enable": "1",
      "quick_view_link_text": "Quick View",
      "additional_information": "1",
      "show_related_product_block": "1",
      "show_upsell_product_block": "1",
      "show_checkout_button": "1",
      "time_to_close_popup": null
    }
  }
}

```

You receive store configuration data set on the backend, including:

- **quickview_enable** : You receive a module configuration that enables or disable.
- **quick_view_link_text** : Receive link text which is set in backend.
- **additional_information** : Get addition information like detail,more Information tab etc.
- **show_related_product_block** : Show related product section on popup.
- **show_upsell_product_block** : Show upsell product section on popup.
- **show_checkout_button** : Show checkout button on popup after addtocart from popup.
- **time_to_close_popup** : You can set popup close time in second after addtocart from poupp.

Note: Please note that if you receive "1" in the response, it indicates that the admin has set "Yes" in the backend. On the other hand, if you receive "0" in the response, it means "No."