



Shipping Progress Bar

FEATURES

- We show the Shipping Progress Bar in all pages.
- We can set the progress bar message in admin.
- After add to cart any product you will achieved the minimum order amount then you can eligible for free shipping.
- You can enable and disable extension the from configuration.

Ultimate Guide for Magento 2 Shipping Progress Bar

Introducing Magento 2 Shipping Progress Bar extension. This extension increase your store selling By showing the shipping progress bar on all pages.

- We can write the initail messaged from the configuration and it's show on the progress bar.
 - We can write the In Progress Message from the configuration and it's show when reaiming amount to get free shipping.
 - We can write the Achieved Message from the configuration and it's show when you eligible for free shipping.
-

How to install the extension

1. Install via composer (recommend)

- Enable maintenance mode **php bin/magento maintenance:enable**
- Run the command **composer require mageinic/shipping-progress-bar**
- Run the command **php bin/magento module:enable MagelNIC_Core MagelNIC_ShippingProgressBar**
- Run the command **php bin/magento setup:upgrade** to install the extension
- Run the command **php bin/magento cache:clean** to clean the cache
- Disable maintenance mode **php bin/magento maintenance:disable**
- Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.

2. Upload via ZIP/Archive

- Back up your store's database and web directory
 - Download the extension zip file and extract the zip file
 - Transfer the **MagelNIC** folder to the Magento 2 **app/code/** directory on the server
 - Enable maintenance mode **php bin/magento maintenance:enable**
 - Run the command **php bin/magento module:enable MagelNIC_Core MagelNIC_ShippingProgressBar**
 - Run the command **php bin/magento setup:upgrade** to install the extension
 - Run the command **php bin/magento cache:clean** to clean the cache
 - Disable maintenance mode **php bin/magento maintenance:disable**
 - Check the store environment if everything is working properly. If, at any point, the store displays an error, check the Magento logger for more details.
-

Extension Configuration

To configure the extension configuration, Please go to **Stores → Settings → Configuration → MagentoNIC → Shipping Progress Bar**.

Shipping Bar

Enable Shipping Progress Bar - We can enable and disable extension.

Minimum Order Amount - After add the Minimum Order Amount in below path it will automatically show that amount in this “Minimum Order Amount” field.

Please go to **Stores → Settings → Configuration → Sales → Delivery Methods → Free Shipping → Minimum Order Amount**.


Initial Message - Set the message which you need to show in the progress bar, It's show before any product add to cart.

In Progress Message - Set the message here after add to cart product which message show in progress bar. Means cart subtotal not achieved Minimum Order Amount that time this message show in the progress bar.


Achieved Message - Set the message when customer eligible for free shipping.

Extension Usage

- Title show which we set in configuration.



- After achieved the minimum amount progress bar message change.



- Free Shipping option is visible.
- We can place order without shipping charges.

[Sign In](#)

Shipping Address

Email Address * ?
You can create an account after checkout.

First Name *

Last Name *

Company

Street Address *

Country *

State/Province *

City *

Zip/Postal Code *

Phone Number * ?

Order Summary

5 Items in Cart

Shipping Methods

- ☐ \$0.00 Free Free Shipping
- ☐ \$25.00 Fixed Flat Rate

[Next](#)

Note

- Make sure your Free shipping delivery methods is enable.