

# SQLite安装指南



---

目录

---

<b>1</b>	<b>SQLite安装</b>	<b>3</b>
1.1	在Windows上安装SQLite	3
<b>2</b>	<b>SQLite Installation</b>	<b>3</b>
2.1	SQLite on Windows	3

## 1 SQLite安装

SQLite的一个重要特性是零配置，这意味着不需要复杂的安装和管理。本文将介绍在Windows上的安装设置。

### 1.1 在Windows上安装SQLite

- 请访问SQLite下载页面，从Windows区下载预编译的二进制文件。
- 您需要下载**sqlite-tools-win32-\*.zip**和**sqlite-dll-win32-\*.zip**压缩文件。
- 创建文件夹C:\sqlite，并在此文件夹下解压上面两个压缩文件，将得到**sqlite3.def**、**sqlite3.dll**和**sqlite3.exe**文件。
- 添加C:\sqlite到PATH环境变量，最后在命令提示符下，使用**sqlite3**命令，将显示如下结果。

```
1 C:\>sqlite3
2 SQLite version 3.7.15.2 2013-01-09 11:53:05
3 Enter ".help" for instructions
4 Enter SQL statements terminated with a ";"
5 sqlite>
```

## 2 SQLite Installation

An important feature of SQLite is zero configuration, which means that no complex installation and administration is required. This document describes the installation of SQLite on Windows:

### 2.1 SQLite on Windows

- Visit the SQLite download page, download the precompiled binary file from Windows area.
- Download two zip files **sqlite - tools - win32 - \*.zip** and **sqlite dll-win32 - \*.zip**.
- Create the folder C: \ sqlite and extract the above two zip files under this folder, will get **sqlite3. def**, **sqlite3. dll** and **sqlite3. exe**.
- Add the C: \ sqlite to the PATH environment variables, finally at the command prompt, run **sqlite3** command, will show the following message:

```
1 C:\>sqlite3
2 SQLite version 3.7.15.2 2013-01-09 11:53:05
3 Enter ".help" for instructions
4 Enter SQL statements terminated with a ";"
5 sqlite>
```