

~/gits/dotty-dotties/root/etc/fstab

```
1 # /etc/fstab: static file system information.
2 #
3 # Use 'blkid' to print the universally unique identifier for a
4 # device; this may be used with UUID= as a more robust way to name devices
5 # that works even if disks are added and removed. See fstab(5).
6 #
7 ##### Version 250306
8 #
9 # <file system>                <mount point>  <type>  <options>          <dump>  <pass>
10 # =====|=====|=====|=====|=====|=====
11 #                v                v      v                v      v
12 # / was on /dev/nvme0nlp3 during curtin installation
13 /dev/disk/by-uuid/b556a2e3-bffe-4dbc-875e-eafe75c13bc9 /          ext4    defaults          0      1
14 #
15 # /boot/efi was on /dev/nvme0nlp1 during curtin installation
16 /dev/disk/by-uuid/10EA-F890          /boot/efi    vfat    defaults          0      1
17 #
18 # /home was on /dev/nvme0nlp4 during curtin installation
19 /dev/disk/by-uuid/8b3db897-66d7-40ad-8f46-9a7286c8134d /home        ext4    defaults          0      1
20 #
21 # /var was on /dev/nvme0nlp5 during curtin installation
22 /dev/disk/by-uuid/e653bdfc-3d62-4ccf-afe2-53d3960a7873 /var          ext4    defaults          0      1
23 #
24 # /swap was on /dev/nvme0nlp2
25 /dev/disk/by-uuid/91fbe929-7e61-4f3d-957e-dcf6d30be97c none          swap    sw                0      0
26 #
27 # External backup disk partions:
28 /dev/disk/by-partlabel/bkp_ntfs          /media/xneb/p2dejadup    ntfs    rw,umask=0002,locale=sv_SE.UTF-8,uid=1000,gid=1000,nosuid,nodev,nofail,noauto,x-gvfs-show 0 0
29 /dev/disk/by-partlabel/bkp_ext4          /media/xneb/pltimeshare  ext4    nosuid,nodev,nofail,noauto,x-gvfs-show 0 0
30 #
31
```