

MIDI mapping for Traktor Pro 3.0 with Novation Twitch

Top Left Quadrant:

- 2.1 5.15 DRY/WET
- 2.2 5.16 1
- 2.3 5.17 2
- 2.4 5.18 3
- 2.5 FX 1
- 2.6 FX 2
- 5.13 Remix C
- 5.14 Remix D
- 2.7 5.19 Slot1 Mute
- 2.8 5.20 Slot2 Mute
- 2.9 5.21 Slot3 Mute
- 2.10 5.22 Slot4 Mute

Top Right Quadrant:

- 3.7 MIXER FX GAIN
- 3.4 HIGH
- 3.4 HIGH
- 3.7 MIXER FX GAIN
- 3.8 MIXER FX ON/OFF
- 3.5 MID
- 3.5 MID
- 3.8 MIXER FX ON/OFF
- 3.7 MIXER FX SELECT
- 3.6 LOW
- 3.6 LOW
- 1.8 LOOP SET/ SLICE SIZE
- 3.9
- 3.9

Bottom Left Quadrant:

- 1.4 SYNC MASTER
- 1.5 SHIFT
- 1.24 DECK A / DECK C
- 1.6 REVERS KEYLOCK
- 1.7 FLUX
- 1.3 - TEMPO + RESET
- 1.2 TOUCHSTRIP
- 1.1 SWIPE
- 1.10 DROP
- 1.11
- 1.12 5.1 HOT CUES
- 1.13 5.2 LOOPROLL BEATJUMP
- 1.14 5.3 FX
- 1.15 5.4 FREEZE
- 1.16 2.11 5.5
- 1.17 2.12 5.6
- 1.18 2.13 5.7
- 1.19 2.14 5.8
- 1.20 2.15 5.9
- 1.21 2.16 5.10
- 1.22 2.17 5.11
- 1.23 2.18 5.12

Bottom Right Quadrant:

- 3.10 BROWSER
- 3.11 MIX
- 3.12 BOOTH
- 3.13 MASTER
- 4.4 LIST SCROLL
- 4.2 BACK
- 4.1 OPEN / CLOSE FAVORITE
- 4.3 FWD
- 4.5 LOAD A/C
- 4.6 4 DECK
- 4.7 LOAD B/D
- DECK B / DECK D
- 1.25
- 1.4 SYNC MASTER
- 1.5 SHIFT
- 1.6 KEYLOCK
- 1.7 FLUX
- 1.3 - TEMPO + RESET
- 1.2 TOUCHSTRIP
- 1.1 SWIPE
- 1.10 DROP
- 1.11
- 1.12 5.1 HOT CUES
- 1.13 5.2 LOOPROLL BEATJUMP
- 1.14 5.3 FX
- 1.15 5.4 FREEZE
- 1.16 2.11 5.5
- 1.17 2.12 5.6
- 1.18 2.13 5.7
- 1.19 2.14 5.8
- 1.20 2.15 5.9
- 1.21 2.16 5.10
- 1.22 2.17 5.11
- 1.23 2.18 5.12

Central Interface:

novation
Traktor Pro 3
pj.weber

3.2 3.3 3.1

No	Function	SHIFT	Activ 1.12	Activ 1.13	Activ 1.14	Activ 1.15	
1 - Deck							
1	Play/Pause						
2	Cue	To Start Track					
3	Tempo	Tempo fast					
4	Sync on/off	Master on/off					
5	Shift						
6	Revers	Keylock on/off					
7	Flux on/off						
8	Loop set/activ	Mixer FX select					Freeze size
9	Tempo adjust select						
10	Seek position select						
11	Touchstrep						
12	Hot cue mode						
13	Looproll / Beatjump mode						
14	FX Deck on/off mode						
15	Freeze mode						
16		Delete hot cue 1	Hot cue 1	Looproll 1/8	FX1 on/off	Slice 1	
17		Delete hot cue 2	Hot cue 2	Looproll 1/4	FX2 on/off	Slice 2	
18		Delete hot cue 3	Hot cue 3	Looproll 1/2	FX3 on/off	Slice 3	
19		Delete hot cue 4	Hot cue 4	Looproll 1	FX4on/off	Slice 4	
20		Delete hot cue 5	Hot cue 5	Beatjump - loopsize	FX Stop Turntable	Slice 5	
21		Delete hot cue 6	Hot cue 6	Beatjump -	FX Slice Laser	Slice 6	
22		Delete hot cue 7	Hot cue 7	Beatjump +	FX Gater 1/4	Slice 7	
23		Delete hot cue 8	Hot cue 8	Beatjump + loopsize	FX Gater 1/8	Slice 8	
24	Deck select A/C						
25	Deck select B/D						

	<i>No</i>	<i>Function</i>	<i>SHIFT</i>	
2 - FX				
	1	Dry/Wet		
	2	Effect1 level	Effect select	
	3	Effect2 level	Effect select	
	4	Effect3 level	Effect select	
	5	FX1 panel select		
	6	FX2 panel select		
	7	Single effect on	Single/Group mode	
	8	Effect1 on/off		
	9	Effect2 on/off		
	10	Effect3 on/off		
	<i>No</i>	<i>Function</i>	<i>SHIFT</i>	
3 - Mixer				
	1	Crossfader		
	2	Channel Fader A/C		
	3	Channel Fader B/D		
	4	EQ High		
	5	EQ Mid		
	6	EQ Low		
	7	Mixer FX	Gain	
	8	Mixer FX On/Off		
	9	Headphone on/off	Load	
	10	Headphone Level		
	11	Monitor Mix		
	12	Booth Level		
	13	Master Level		

	<i>Nº</i>	<i>Function</i>	<i>SHIFT</i>	
4 - Browser				
	1	List Scrol / open/close	Favorites Scroll	
	2	Back		
	3	Forvard		
	4	Open Browser		
	5	Layoute selector	Remix deck C/D	
	6	Load A/C		
	7	Load B/D		

No	Function	SHIFT	Activ 5.1	Activ 5.2	Activ 5.3	Activ 5.4
5 - Remix Deck						
1	Sample page1 (1,2)					
2	Sample page1 (3,4)					
3	Sample page2 (1,2)					
4	Sample page2 (3,4)					
5	Slot1 Cell1	FX1 on/off	Slot1 Cell1	Slot3 Cell1	Slot5 Cell1	Slot7 Cell1
6	Slot1 Cell2	FX2 on/off	Slot1 Cell2	Slot3 Cell2	Slot5 Cell2	Slot7 Cell2
7	Slot1 Cell3		Slot1 Cell3	Slot3 Cell3	Slot5 Cell3	Slot7 Cell3
8	Slot1 Cell4		Slot1 Cell4	Slot3 Cell4	Slot5 Cell4	Slot7 Cell4
9	Slot2 Cell1	FX1 on/off	Slot2 Cell1	Slot4 Cell1	Slot6 Cell1	Slot8 Cell1
10	Slot2 Cell2	FX2 on/off	Slot2 Cell2	Slot4 Cell2	Slot6 Cell2	Slot8 Cell2
11	Slot2 Cell3		Slot2 Cell3	Slot4 Cell3	Slot6 Cell3	Slot8 Cell3
12	Slot2 Cell4		Slot2 Cell4	Slot4 Cell4	Slot6 Cell4	Slot8 Cell4
13	Select adjust Remix C					
14	Select adjust Remix D					
15	Volume Slot1	Filter Slot1				
16	Volume Slot2	Filter Slot2				
17	Volume Slot3	Filter Slot3				
18	Volume Slot4	Filter Slot4				
19	Mute Slot1	Stop/Delete Slot1				
20	Mute Slot2	Stop/Delete Slot2				
21	Mute Slot3	Stop/Delete Slot3				
22	Mute Slot4	Stop/Delete Slot4				

Importing controller mappings in Traktor Pro 3


- 1 Unzip or extract the files to your desktop.
- 2 Plug in your Novation Twitch in to USB.
- 3 Open Traktor Pro 3.
- 4 Click the Preferences or gear icon in the top right corner.



- 5 Click Import from the bottom of the Preferences window.



- 6 Locate the Twitch mapping file, and click Open.
- 7 Leave the default Category boxes checked as below unless you have your GUI or layout setup for 4 decks. Click OK to import the settings.



- 8 You need to import this mapping twice ensure all effect settings load correctly. Repeat steps 5-7 to ensure this.