

WP BINARY MLM

USER MANUAL

BINARY MLM PRO V2.0

WP BINARY MLM

TABLE OF CONTENTS

S.No.	TOPIC	Page No.
1	INSTALLATION	3
2	PLUGIN CONFIGURATION	4
2.1	Create First User in the Network	4
2.2	License Settings	5
2.3	Currency Setting	5
2.4	Eligibility Settings	6
2.5	Payout Settings	7
2.6	Bonus Settings	8
3	RUNNING PAYOUTS	10
4	USER REPORTS	11
5	WITHDRAWALS	12
5.1	Pending User Withdrawals	12
5.2	Process Individual User Withdrawal	12
5.3	Processed Withdrawals Report	13
6	MEMBER'S AREA	14
6.1	Network Details	14
6.2	Genealogy Page	15
6.3	My Payouts Page	16
6.4	Payout Details Page	17
7	MULTILINGUAL FEATURE	18
8	LIST OF PAGES AND SHORT CODES	19

WP BINARY MLM

1. INSTALLATION

1) Upload the entire binary-mlm-pro folder to the /wp-content/plugins/ directory.

2) Activate the plugin through the 'Plugins' menu in WordPress.

You will find '**Binary MLM**' menu in your WordPress admin panel.

WP BINARY MLM

2. PLUGIN CONFIGURATION

2.1 Create First User in Network

Binary MLM -> Settings -> Create First user

Create Username *	<input type="text" value="tradebooster"/>
Create Password *	<input type="password" value="....."/>
Confirm Password *	<input type="password" value="....."/>
Email Address *	<input type="text" value="support@wpbinarymlm.com"/>
Confirm Email Address *	<input type="text" value="support@wpbinarymlm.com"/>


Submit

As the first step towards configuring your plugin, please create the first user of your network. This would be the topmost user in the network. All other users would be registered under this First User.

Please note that the default Wordpress Admin user is NOT a part of the network. Hence if you visit any of the front end pages using the default Wordpress admin user, you might notice some errors.

WP BINARY MLM

2.2 License Settings



License Settings

Binary MLM -> Settings -> Licence Settings

License Details :

Domain Name

License Key

[Update Details](#)

Binary MLM -> Settings -> License

In order to generate the license key for your URL, you can login to your account at <http://wpbinarymlm.com>. Click the View button against your order, input your URL. The system would generate a license key for your URL. Click the Save Button.

Copy and Paste this license key in the license key field of the License Tab under Binary MLM -> Settings and click Update Details.

The system would validate this license key and show you a success message if the validation is successfully passed.

Please note, that one license key is valid for 1 URL only. So if you intend to use the plugin on 2 or more sites simultaneously then you would need to purchase additional licenses. However, you can update the license URL any number of times if you ever change the URL of your Wordpress deployment and get a new key for the new URL.

2.3 Currency Setting



Binary MLM -> Settings -> General

Currency

[Update Options »](#)

Binary MLM -> Settings -> General

WP BINARY MLM

Select the base currency of your MLM Network. This option is very important as all calculations will be performed in this base currency. Once this currency is chosen and saved, it CANNOT be changed later. The entire network will need to be reset if you decide to change the currency at a later date.

2.4 Eligibility Settings



The screenshot shows a web interface for setting eligibility criteria. At the top, a breadcrumb trail reads "Binary MLM -> Settings -> Eligibility". Below this, there are three input fields, each with a label and a red asterisk indicating it is required:

- "No. of direct paid referral(s) *:" with a text input containing the number "2".
- "No. of paid referral(s) on right leg *:" with a text input containing the number "1".
- "No. of paid referral(s) on left leg *:" with a text input containing the number "1".

At the bottom left of the form is a blue button labeled "Update Options »".

Binary MLM -> Settings -> Eligibility

Use this screen to define the eligibility criteria for a member to start earning pair commissions in the network.

No. of Direct Paid Referrals - The number of members that a member will need to directly and personally refer in the network before he can start earning commissions.

No. of paid referral(s) on right leg - The number of paid direct and personal referrals a member needs to introduce in this right leg before he can start earning commissions.

No. of paid referral(s) on left leg - The number of paid direct and personal referrals a member needs to introduce in this left leg before he can start earning commissions.

WP BINARY MLM

2.5 Payout Settings

Binary MLM -> Settings -> Payout

Pair *	1	:	1
Initial Pairs *	1		
Initial Pair Amount *	100		
Further Pair Amount *	80		
Direct Referral Commission:	50		
Service Charge (If any) :	10		
Tax Deduction :	12.5	%	
Cap Limit Amount:	5000		

Update Options »

Binary MLM -> Settings -> Payout

Use this screen to define the basic parameters of your pay plan.

Pair - How many paid members in the left and right leg individually will make 1 pair for calculating commissions.

Initial Pairs - To incentivise members in the initial stages the amount paid for initial pairs is slightly higher than the regular payout amount. Specify the number of initial pairs for which you would like to pay a higher payout amount.

Initial Pair Amount - This is the per pair amount that is paid for each Initial Pair.

Further Pair Amount - This is the payout amount for every Pair after the Initial Pairs.

WP BINARY MLM

Direct Referral Commission - This is the amount paid to a sponsor for sponsoring a new member in the network. This amount is paid for an infinite number of referrals. The eligibility criteria is NOT applied for earning direct referral commission.

Service Charges - An amount that is deducted from each Payout paid to the member as a fixed Service Charge. eg. \$2 as processing fee for each payout.

Tax Deduction - Some countries have a legislation of deducting Income Tax at source while making commission payments to your members. This is specified as a percentage amount.

Cap Limit - Maximum amount that can be paid to a member in one payout cycle. Anything above the cap limit will be flushed out.

2.6 Bonus Settings

Binary MLM -> Settings -> Bonus

Bonus Criteria * ☐ No. of Pairs

Select	No. of Pairs	Amount
<input checked="" type="checkbox"/>	2	500

Binary MLM -> Settings -> Bonus

In case you have a bonus option in your Network, use this tab to configure the bonus settings.

Bonus Criteria - The bonus amount can be paid on the basis of Total number of Pairs in a members network or the Total number of members referred Personally by a member. Select the option that suits your network.

Bonus Slabs - Specify the total number of pairs or members that a member needs to achieve and the corresponding bonus amount for the same. To add a new slab click the Add Row button. Specify the number of pairs / members and the corresponding amount for the next slab. When you are done creating the slabs click the Update Options button.

Example Slab Figures

WP BINARY MLM

Unit	Amount
------	--------

5	10.00
---	-------

10	20.00
----	-------

20	40.00
----	-------

This implies that a member is paid a commission of 10 on achieving 5 pairs or personal referrals.

On achieving the NEXT 10 pairs or personal referrals the member is paid a commission of 20. So now the member has either 15 pairs or 15 personal referrals in total.

On achieving the NEXT 20 pairs or personal referrals the member is paid a commission of 40. So now the member has either 35 pairs or 35 personal referrals in total.

WP BINARY MLM

3. RUNNING PAYOUTS

Binary MLM -> Run payouts

Distribute Commission and Bonus

Run Payout Routine

S.No	Username	Name	Commission	Direct Referral Commission	Bonus	Cap Limit	Service Charge	Tax	Net Amount
1	samyad		80.00	800.00	0.00	600.00	10.00	75.00	515.00(capped)

Something wrong. Cancel

All is Well. Commit

Binary MLM -> Run Payouts

Use this screen to run the Payout routine for your network. While testing the plugin use the Distribute Commission and Bonus button below after adding a few members to the network (don't forget to mark them as paid in Users -> All Users, otherwise no commissions will be distributed for anybody). On a live site the following URL needs to be scheduled (cron job) to run at least every hour (or a lesser frequency, say every 30 mins or 15 mins depending on how fast your network is growing) for the commission and bonus routines.

<http://www.yourdomainname.com/wp-content/plugins/binary-mlm-pro/cronjobs/commission-bonus.php>

The commission and bonus routines would simply keep distributing the commission and bonus amounts in the member accounts. They would not show up in their account till the time the Payout Routine is not run. This script can be run manually once every week, every fortnight or every month depending on the payout cycle of your network. Alternately, you can schedule (cron job) the following URL as per the frequency of your payout cycle.

<http://www.yourdomainname.com/wp-content/plugins/binary-mlm-pro/cronjobs/paycycle.php>

4. User Reports

Binary MLM -> User Reports

Input a member's username or email address in the input box below to get complete information about the member's account. No more switching back and forth into different member accounts to check their account details.

Binary MLM -> User Report

Search By username or email address :

Back to User Dashboard

Search »

WP BINARY MLM

5. WITHDRAWALS

5.1 Pending User Withdrawals

Binary MLM -> Pending User Withdrawals

Member Username	Member Email	Withdrawal Initiate Date	Withdrawal Comment	Amount	Payout Id	Payout Date	Action
samyad	prakash1@webpathfinders.com	July 6, 2013	First payment	515.00	2	July 6, 2013	Process Delete

Binary MLM -> User Withdrawals

This screen shows the list of all pending User Withdrawals.

Process - Input the payment details for the withdrawal. These payment details would also show up on the User's Payout Details Page.

Delete - This would mark the withdrawal as deleted. The user would need to initiate a fresh withdrawal for this payout from his interface.

5.2 Process Individual User Withdrawal

Member Id	1		
Member User Name	samyad		
Payout Id	2		
Member Email	prakash1@webpathfinders.com		
Amount	515.00		
Payment Mode	<input type="radio"/> Cash		
	<input checked="" type="radio"/> Cheque		
	<input type="text" value="Cheque Number"/>	<input type="text" value="mm/dd/yyyy"/>	<input type="text" value="Bank Name"/>
	<input type="radio"/> Bank Transfer		
	<input type="radio"/> Other		
	<input type="button" value="Process"/>		

Binary MLM -> Pending User Withdrawals -> Process

Use this form below to process an individual user withdrawal.

© wpbinarymlm.com

WP BINARY MLM

Cash - Simply records a cash payment against the withdrawal with no further details.

Cheque - Specify the Cheque Number, Cheque Date and Bank Name.

Bank Transfer - Specify the Beneficiary Name, Account Number, Bank Name and Bank Transfer Code (optional).

Other - For any other mode of payment. Just specify the payment details in the input box provided.

5.3 Processed Withdrawals Report

MLM Menu > User Withdrawal Report							
User Name	User Email	Payout Id	Payout Date	Withdrawal Date	Withdrawal Amount	Payment Mode	Payment Details
samoyad	prakash1@webpathfinder s.com	2	July 6, 2013	July 6, 2013	515.00	Cash	Date: July 6, 2013
User Name	User Email	Payout Id	Payout Date	Withdrawal Date	Withdrawal Amount	Payment Mode	Payment Details

Binary MLM -> Processed Withdrawals Report

This report lists the details of all the processed withdrawals in the system.

6. MEMBER'S AREA

6.1 Network details

Network Details

Affiliate URL : http://demos.tradebooster.com/binary-mlm-pro?page_id=1849&sp=826057143

Personal Information

Title Details

Name

Address

City

Contact No.

DOB

[Edit](#)

[View Genealogy](#)

My Payouts

Date	Amount	Action
06 Jul 2013	INR 165	View
06 Jul 2013	INR -5	View

Network Details

Left Leg Sales

Total on Left Leg: 2	Active: 2
chandan2	Active
chandan	Active
View All	

Right Leg Sales

Total on Right Leg: 2	Active: 2
chandan3	Active
chandan1	Active
View All	


Personal Sales

My Personal Sales: 4	Active: 4
chandan3	Active
chandan2	Active
chandan1	Active
chandan	Active
View All	

WP BINARY MLM

This is the member's dashboard which shows a summary of all activity for the member viz. Personal Information, Payouts, Genealogy, Left Leg, Right Leg and Personal Referrals.

6.2 Genealogy page



This page shows a member's genealogy view. The member can click on View on an occupied node to see the genealogy of that member. The member can also search for a member using the search form on top. Clicking on YOU brings the member back to his own Genealogy.

6.3 My Payouts page

My Payouts			Network -> My Payouts
Date	Amount	Action	
06 Jul 2013	INR 165.00 (capped)	View	
06 Jul 2013	INR 410	View	

This page lists all the payouts earned by the member. Clicking on View against a particular payout will open the details page for that payout.

WP BINARY MLM

6.4 Payout Details page

Personal Information		Payout Details	
Title	Details	Commission	
Name		User Name	Amount
ID	826057143	chandan2,chandan3,	INR 80.00
Payout ID	2	Direct Referral Commission	
Date	06 Jul 2013	User Name	Amount
		chandan	INR 200.00
		chandan1	INR 200.00
		chandan2	INR 200.00
		chandan3	INR 200.00
Payout Summary			
Commission Amount		INR 80.00	
Direct Referral Commission Amount		INR 800.00	
Bonus Amount		INR 0.00	
Sub-Total		INR 880	
Cap Limit		INR 600	
Service Charge		INR 10.00	
Tax		INR 75.00	
Net Amount(capped)		INR 515	
<input type="text"/>		<input type="button" value="Initiate withdrawal"/>	

This page shows the details of a particular payout. It shows the breakup of the pair commissions, Direct Referral Commission, Bonus and the Payout Summary. The member can click on the initiate withdrawal button to make a full withdrawal for this payout. The system does not permit partial withdrawals as of now.

7. MULTILINGUAL FEATURE

The plugin has built in translations for the following languages. However, all these translations have been done in-house. If you notice, any discrepancy with any of the language strings, please do drop us an email at support@wpbinarymlm.com with the correct translation for the string. In case you would like to contribute by adding support for another language please do write to us at support@wpbinarymlm.com and we shall get back to you with further details.

List of available languages:

1. English (en_US)
2. French (fr_FR)
- 3 Spanish (es_ES)
4. German (de_DE)
5. Portuguese (pt_PT)
6. Chinese (zh_CN)
7. Tamil (ta_LK)
8. Russian (ru_RU)
9. hindi (hi_IN)

If your language are not available in this list and you would like to translate it yourself, copy an existing language file and rename it with your language code (<http://www.w3.org/WAI/ER/IG/ert/iso639.htm>).

Edit the file and input the translation strings for your language in the following format.

msgid "Sponsor does not exist in the system." (English Translation)

msgstr " " (Add your translation string for the above msgid)

After completing the changes convert your .po file to .mo file. You can use the .mo converter tool at <http://tools.konstruktors.com> and place both the files in language folder of the plugin. (/wp-content/plugins/binary-mlm-pro/languages)

8. LIST OF PAGES AND SHORT CODES

Page Title	Short-Code
Register New User	[register-mlm-page]
Network	[view-mlm-binary-network]
Genealogy	[view-mlm-binary-network]
Network Details	[mlm-network-details]
Left Group	[mlm-left-group]
Right Group	[mlm-right-group]
Personal Group	[mlm-personal-group]
My Consultants	[mlm-consultant-group]
My Payouts	[mlm-payouts]
My Payouts Details	[mlm-payout-details]
Update Profile	[mlm-update-profile]
Change Password	[mlm-change-pass]

NOTE: Please do not change the short codes used in the above pages as they will have a direct impact on the functionality of the relevant page.